HyperCard Script Language Guide

The HyperTalk Language

Apple Computer, Inc.
© 1996 Apple Computer, Inc.
All rights reserved.

No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, mechanical, electronic, photocopying, recording, or otherwise, without prior written permission of Apple Computer, Inc. Printed in the United States of America.

The Apple logo is a trademark of Apple Computer, Inc. Use of the "keyboard" Apple logo (Option-Shift-K) for commercial purposes without the prior written consent of Apple may constitute trademark infringement and unfair competition in violation of federal and state laws. No licenses, express or implied, are granted with respect to any of the technology described in this book. Apple retains all intellectual property rights associated with the technology described in this book. This book is intended to assist application developers to develop applications only for Apple Macintosh computers.

Apple Computer, Inc. 20525 Mariani Avenue Cupertino, CA 95014 408-996-1010

Apple, the Apple logo, APDA, AppleCD SC, AppleLink, AppleTalk, ImageWriter, HyperCard, HyperTalk, LaserWriter, Macintosh, MPW, MultiFinder, PowerBook, SANE, and Stackware are trademarks of Apple Computer, Inc., registered in the United States and other countries.

AppleScript, Chicago, Finder, Geneva, Macintosh Quadra, Monaco, New York, QuickDraw, QuickTime, ResEdit, System 7, and WorldScript are trademarks of Apple Computer, Inc. Adobe Illustrator and PostScript are trademarks of Adobe Systems Incorporated, which may be registered in certain jurisdictions. FileMaker, MacPaint, and MacWrite are trademarks of Claris Corporation.

FrameMaker is a registered trademark of Frame Technology Corporation.

Helvetica and Palatino are registered trademarks of Linotype Company.

ITC Zapf Dingbats is a registered trademark of International Typeface Corporation.

Microsoft is a registered trademark of Microsoft Corporation.

Simultaneously published in the United States and Canada.

LIMITED WARRANTY ON MEDIA AND REPLACEMENT

ALL IMPLIED WARRANTIES ON THIS MANUAL, INCLUDING IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, ARE LIMITED IN DURATION TO NINETY (90) DAYS FROM THE DATE OF THE ORIGINAL RETAIL PURCHASE OF THIS PRODUCT.

Even though Apple has reviewed this manual, APPLE MAKES NO WARRANTY OR REPRESENTATION, EITHER EXPRESS OR IMPLIED, WITH RESPECT TO THIS MANUAL, ITS QUALITY, ACCURACY, MERCHANTABILITY, OR FITNESS FOR A PARTICULAR PURPOSE. AS A RESULT, THIS MANUAL IS SOLD "AS IS," AND YOU, THE PURCHASER, ARE ASSUMING THE ENTIRE RISK AS TO ITS QUALITY AND ACCURACY.

IN NO EVENT WILL APPLE BE LIABLE FOR DIRECT, INDIRECT, SPECIAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGES RESULTING FROM ANY DEFECT OR INACCURACY IN THIS MANUAL, even if advised of the possibility of such damages.

THE WARRANTY AND REMEDIES SET FORTH ABOVE ARE EXCLUSIVE AND IN LIEU OF ALL OTHERS, ORAL OR WRITTEN, EXPRESS OR IMPLIED. No Apple dealer, agent, or employee is authorized to make any modification, extension, or addition to this warranty.

Some states do not allow the exclusion or limitation of implied warranties or liability for incidental or consequential damages, so the above limitation or exclusion may not apply to you. This warranty gives you specific legal rights, and you may also have other rights which vary from state to state.

Contents

	Figures and Tables xiii
Preface	About This Guide xix
	What's in This Book? xix Notation Conventions xxi Changes Since the First Edition of This Guide xxii Apple Developer Programs xxiii
Chapter 1	What's New Since 2.0? 1
	HyperCard System Requirements 1 HyperCard Enhancements 2 WorldScript Compatibility 3 HyperCard and Other Scripting Systems 3 Open Scripting Architecture 4 AppleScript 5 Script Attachability 6 Script Editor Enhancements 7 Button Dialog Modifications 7 New Button Features 8 Field Dialog Modifications 12 New Field Features 13 Integrated Stand-Alone Application Builder 14 Enhanced HyperTalk 15
Chapter 2	HyperTalk Basics 23
	What Is HyperTalk? 23 Objects 24 Buttons and Fields 24 Cards, Backgrounds, and Stacks 25

Messages 25 Scripts 26 Message Handlers 26 **Function Handlers** 27 Windows 28 Card Windows 28 HyperCard's Built-in External Windows 30 Menus 30 Chapter Summary 32

Chapter 3 The Scripting Environment 33

Getting to the Script 33 35 The Script Editor Manipulating Text 37 38 Searching for Text Replacing Text **Entering Comments** 39 40 Formatting Scripts Line Length and Script Size 41 Script Editor Command Summary 41 The Debugger Environment Setting Checkpoints HyperTalk Debugger Windows 45 Message Watcher 46 47 Variable Watcher 48 Custom Message Watcher and Variable Watcher XCMDs 49 Debugger Command Summary Chapter Summary 50

Chapter 4 Handling Messages 51

The HyperCard Environment 51
Sending Messages 52
System Messages 52
Statements as Messages 53

Message Box Messages Messages Resulting From Commands 54 Receiving Messages 55 Message-Passing Hierarchy 56 Where Messages Go Messages to Buttons and Fields 58 The Current Hierarchy The Target The User-Defined Hierarchy 62 The Dynamic Path 67 The Go Command and the Dynamic Path The Send Keyword and the Dynamic Path 69 Handlers Calling Handlers 71 Subroutine Calls Recursion Using the Hierarchy 73 73 Sharing Handlers 76 Intercepting Messages Parameter Passing Chapter Summary 79

Chapter 5 Referring to Objects, Menus, and Windows 81

Names, Numbers, and IDs 81 Object Names 83 84 Object Numbers Part Numbers 85 87 **Button Families** 87 Special Ordinals Object Numbers and Tab Order 87 Object ID Numbers 89 Special Object Descriptors Identifying a Stack 89 Naming a Stack 91 Combining Object Descriptors 93 Referring to Menus and Menu Items

Menu and Menu Item Names 93 Menu and Menu Item Numbers 93 Referring to Windows 96 Chapter Summary 97

Values Chapter 6 99 99 Constants Literals 100 **Functions** 100 Properties 101 Numbers 101 Standard Apple Numerics Environment 102 Precision 102 Number Handling 103 Containers 103 **Fields** 104 **Buttons** 104 Variables 105 Scope of Variables 106 106 Parameter Variables The Variable It 106 107 Menus 107 The Selection The Message Box 108 Chapter Summary 109

Chapter 7 Expressions 111

Complex Expressions 111
Factors 111
HyperTalk Operators 113
Operator Precedence 117
Operators and Expression Type 118
Chunk Expressions 118
Syntax of Chunk Expressions 119

Characters 120 Words 120 Items 120 Lines 121 Ranges 121 Chunks and Containers 122 Chunks as Destinations as Well as Sources 123 Nonexistent Chunks 124 Chapter Summary System Messages Chapter 8 125 Messages and Commands 125 126 Messages Sent to a Button Messages Sent to a Field 128 Messages Sent to the Current Card 131 Message Order 138 Control Structures and Keywords Chapter 9 141 Keywords in Message Handlers 141 144 Message Handler Example 145 Keywords in Function Handlers Function Handler Example 149 Repeat Structure 149 Repeat Statements 150 If Structure 155 Single-Statement If Structure 155 Multiple-Statement If Structure 156 Nested If Structures 157

166

Commands

Redefining Commands

Syntax Description Notation

165

165

Chapter 10

System 7 Commands 167 Command Descriptions 167

Chapter 11 Functions 289

Function Calls 289

Syntax Description Notation

Function Descriptions 291

Chapter 12 Properties 357

Retrieving and Setting Properties 357

Object Properties 358

Stack Properties 359

Background Properties 360

Card Properties 361

Field Properties 362

Button Properties 365

Rectangle Properties 367

Environmental Properties 368

Global Properties 369

Painting Properties 372

Window Properties 374

Menu, Menu Bar, and Menu Item Properties 375

Message Watcher and Variable Watcher Properties 376

290

HyperCard Property Descriptions 377

Appendix A External Commands and Functions 503

Definitions, Uses, and Examples 503

XCMD and XFCN Resources 503

Uses for XCMDs and XFCNs 504

Using an XCMD or XFCN 504

Invoking XCMDs and XFCNs 505

Message-Passing Hierarchy 505

```
507
Guidelines for Writing XCMDs and XFCNs
Attaching an XCMD or XFCN
                                 508
                                  509
Parameter Block Data Structure
  Passing Parameters to XCMDs and XFCNs
                                               510
    ParamCount
                     510
    Params
                510
  Passing Back Results to HyperCard
                                        510
    ReturnValue
                    510
    PassFlag
                 511
  Callbacks
               511
    EntryPoint
                   511
    Request
                511
              511
    Result
               512
    InArgs
                 512
    OutArgs
Callback Procedures and Functions
                                      512
                        513
  HyperTalk Utilities
  Memory Utilities
                      514
  String Utilities
                    514
  String Conversions
                        515
  Field Utilities
                   518
  Miscellaneous Utilities
                            519
  Creating and Disposing of External Windows
                                                  522
  Window Utilities
                       525
  Text Editing Utilities
                          529
                          530
  Script Editor Utilities
  Variable Watcher Support
                               532
  Debugger Support
                        533
                      534
External Windows
  Events in External Windows
                                 536
    Handling Events
  Closing an External Window
                                  540
                                540
  Special XCmdBlock Values
    Message Watcher
                         541
    Variable Watcher
                         541
                    541
    Script Editor
                  542
    Debugger
```

XTalkObject 542
Window Layer Management 543
Flash: An Example XCMD 545
Flash Listing in MPW Pascal 546
Flash Listing in MPW C 548
Flash Listing in 68000 Assembly Language 550

Appendix B Constants 553

Appendix C Enhancing the Execution Speed of HyperCard 555

Change Stacks as Seldom as Possible 556 Use Variables, Not Fields, for Operations 556 557 Refer to a Remote Card Rather Than Going There 558 Migrate to XCMDs and XFCNs for Repetitive Tasks Set LockScreen to True to Avoid Needless Redrawing 558 Set LockMessages to True During Card-to-Card Data Collection 558 558 Combine Multiple Messages Take Unnecessary Code Out of Loops 559 Use In-Line Statements Rather Than Handler Calls 559 Do Complex Calculations Once 560 Watch Overuse of Variable References 560

Appendix D	Extended ASCII Table	561	
Appendix E	Operator Precedence Ta	able	565
Appendix F	HyperCard Synonyms	567	
Appendix G	HyperCard Limits 569		
Appendix H	HyperCard Syntax Sumi	mary	573
Appendix H	HyperCard Syntax Sumi Syntax Description Notation	mary 573	573
Appendix H			573
Appendix H Appendix I			573
	Syntax Description Notation	573	573
	Syntax Description Notation	573	573
	Syntax Description Notation HyperTalk Vocabulary	573	573

Figures and Tables

Chapter 1	What's New	Since 2.0? 1				
	Figure 1-1	Two applications exchanging information using the AppleScript capabilities of HyperCard 2.2 4				
	Figure 1-2	Button Info dialog box 8				
	Figure 1-3	The Button Contents dialog box 9				
	Figure 1-4	New button styles 10				
	Figure 1-5	Oval style button (shown in Button tool with Show Name checked) 11				
	Figure 1-6	Field Info dialog box 13				
	Figure 1-7	List fields 13				
	Figure 1-8	Building a stand-alone application from your stack 14				
	Table 1-1	Enhanced HyperTalk commands 15				
	Table 1-2	Enhanced HyperTalk functions 16				
	Table 1-3	Enhanced HyperTalk properties 17				
	Table 1-4	Enhanced HyperTalk messages 20				
Chapter 2	HyperTalk Basics 23					
	Figure 2-1	HyperCard objects 24				
	Figure 2-2	Relationship between the location of a card and a card window 29				
Chapter 3	The Scripting	g Environment 33				
	Figure 3-1	The Objects menu 33				
	Figure 3-2	Button Info dialog box 34				
	Figure 3-3	Script editor window 36				
	Figure 3-4	Script menu 37				
	Figure 3-5	Find dialog box 38				
	Figure 3-6	Replace dialog box 39				
	Figure 3-7	Nested control structures 40				
	Figure 3-8	The Debugger menu 44				
	Figure 3-9	The Message Watcher window 46				

	Figure 3-10 Figure 3-11	The Variable Watcher window 47 A selected variable in the Variable Watcher window 48
	Table 3-1 Table 3-2	Script editor command summary 41 Debugger command summary 49
Chapter 4	Handling Mes	sages 51
	Figure 4-1 Figure 4-2 Figure 4-3 Figure 4-4 Figure 4-5 Figure 4-6 Figure 4-7 Figure 4-8 Figure 4-9 Figure 4-10 Figure 4-11 Figure 4-12 Figure 4-13 Figure 4-14 Figure 4-15 Figure 4-16 Table 4-1	Handler that responds to message openStack 55 Message-passing hierarchy 57 Layered buttons and fields 58 Message traversing current hierarchy 59 Command sent as a message 60 The target 61 One stack added to the message-passing hierarchy 63 Two stacks added to the message-passing hierarchy 64 Removing a stack from the message-passing hierarchy 66 Static path before the go command executes 68 Dynamic path after the go command executes 69 Using the send keyword 70 Handler in a card script 74 Handler in a stack script 75 Intercepting a message 77 Parameter passing 79 HyperTalk's keywords 54
Chapter 5	Referring to O	bjects, Menus, and Windows 81
-	Figure 5-1 Figure 5-2 Figure 5-3 Figure 5-4 Figure 5-5	Card Info dialog box and descriptors for the same card 82 A pathname 90 New Stack dialog box 91 New Stack dialog card-size pop-up menu 92 A custom menu 95
Chapter 6	Values 99	
	Figure 6-1	Manipulating the selection 107

	Figure 6-2	The Message box 109
Chapter 7	Expressions	111
	Figure 7-1 Figure 7-2 Figure 7-3	Lines in a field 121 Chunk expressions 122 Combining chunks and objects 123
	Table 7-1 Table 7-2	HyperTalk operators 113 Operator precedence 117
Chapter 8	System Messa	ges 125
	Table 8-1 Table 8-2 Table 8-3 Table 8-4	Messages sent to a button 127 Messages sent to a field 129 Messages sent to the current card 132 HyperCard message sending order 139
Chapter 10	Commands	165
	Figure 10-1 Figure 10-2 Figure 10-3	Answer command dialog boxes 170 Answer command display of the standard file dialog box 171 The PPC Browser produced using the answer program command 172
	Figure 10-4 Figure 10-5	Ask command dialog box 176 Tools palette 179
	Table 10-1 Table 10-2	Effects of the arrowKey command 173 ControlKey message parameter values 189
Chapter 12	Properties 3	57
	Figure 12-1 Figure 12-2 Figure 12-3 Figure 12-4	An object's Info dialog box 358 Brush Shape dialog box and property values 387 Patterns palette and pattern numbers 445 The scroll property 466
	Table 12-1	Stack properties 359

	Table 12-2 Table 12-3 Table 12-4 Table 12-5 Table 12-6 Table 12-7 Table 12-8 Table 12-9 Table 12-10 Table 12-11	Background properties 360 Card properties 361 Field properties 363 Button properties 365 Rectangle properties 367 Global properties 369 Painting properties 373 Window properties 374 Menu, menu bar, and menu item properties 376 Message Watcher and Variable Watcher properties 377
Appendix A	External Comr	nands and Functions 503
	Figure A-1 Figure A-2	Message-passing hierarchy, including XCMDs and XFCNs 506 HyperCard window layers 544
Appendix B	Constants 5	553
	Table B-1	HyperTalk constants 553
Appendix D	Extended ASC	II Table 561
	Table D-1 Table D-2	Control character assignments 561 Character assignments in Macintosh Courier font 562
Appendix E	Operator Prece	edence Table 565
	Table E-1	Operator precedence 565
Appendix F	HyperCard Sy	nonyms 567
	Table F-1	HyperTalk synonyms 567
Appendix G	HyperCard Lin	nits 569
	Table G-1	HyperCard limits 569

Appendix H	HyperCard Syntax Summary 573			
	Table H-1	HyperTalk command syntax 574		
	Table H-2	HyperTalk function syntax 581		
Appendix I	HyperTalk V	ocabulary 589		
	Table I-1	HyperTalk vocabulary 589		

About This Guide

This book provides detailed information about HyperTalk, the scripting language of HyperCard. Even a little knowledge of HyperTalk enables you to customize buttons and other parts of HyperCard stacks for your own purposes, and you can use HyperTalk to make the stacks you create act the way you want.

While you're using HyperCard, you can find information about HyperTalk in the HyperCard Help stack and the HyperTalk Reference stack. These stacks make use of some of HyperCard's best features, such as multiple windows, computer-supported cross-referencing, and fast text searching.

Some of the concepts in this book, such as message handling and objects, may be new to you. Use this guide as it suits your own style of learning: you might be the kind of person who understands best by thoroughly studying the explanations, or you might be the kind who learns by skimming the material and then playing with HyperTalk—writing scripts or copying the examples and trying them out.

Reference material for beginning scriptors can be found in the *HyperCard Reference* and the *HyperTalk Beginner's Guide*, which are available in the HyperCard software package.

What's in This Book?

Here's a brief description of the contents of this book:

Chapter 1, "What's New Since 2.0?" discusses the differences between earlier versions of HyperCard and HyperCard 2.2. If you are already familiar with HyperTalk as described in the original edition of this book, you can use this chapter as a guide to new information in this edition. If you're new to HyperTalk, however, and haven't used the original edition, you'll probably want to skip Chapter 1 initially and come back to it later.

Chapter 2, "HyperTalk Basics," introduces the basic concepts of HyperTalk, showing how it is used in the HyperCard environment.

xix

Chapter 3, "The Scripting Environment," explains how to create and modify scripts in HyperCard objects.

Chapter 4, "Handling Messages," describes how HyperTalk works, how it carries out actions, and how it responds to events in the HyperCard environment.

Chapter 5, "Referring to Objects, Menus, and Windows," explains how to refer to objects—the parts of HyperCard that contain HyperTalk scripts and that respond to and initiate actions. It describes how you can use names, numbers, and ID numbers to identify and work with objects, menus, and windows.

Chapter 6, "Values," explains the elements within HyperTalk that contain values.

Chapter 7, "Expressions," describes HyperTalk's operators and explains how HyperTalk evaluates expressions—the descriptions of how to get a value.

Chapter 8, "System Messages," describes the messages that HyperCard generates in response to events (such as mouse clicks) that happen in its environment.

Chapter 9, "Control Structures and Keywords," describes the handlers within which you write all HyperTalk scripts to enable objects to respond to messages and function calls. It also describes the control structures of HyperTalk that let you specify how and when sections of scripts execute, and it describes the keywords that you use in control structures.

Chapter 10, "Commands," describes each of HyperTalk's built-in commands—the action statements that make HyperCard do things.

Chapter 11, "Functions," describes HyperTalk's built-in functions—named values that reflect conditions in the HyperCard environment.

Chapter 12, "Properties," describes the properties of HyperCard objects—characteristics that determine how objects look and act.

Appendix A, "External Commands and Functions," contains general information about XCMDs and XFCNs, extensions to HyperTalk that can be written by expert programmers to increase the power of HyperCard.

Appendix B, "Constants," describes HyperTalk's built-in constants—named values that don't change.

Appendix C, "Enhancing the Execution Speed of HyperCard," provides some helpful hints for scriptors who want to increase the efficiency of HyperCard.

Appendix D, "Extended ASCII Table," lists the decimal values of the standard Macintosh character set used by HyperCard.

Appendix E, "Operator Precedence Table," summarizes the order in which HyperTalk performs operations when it evaluates expressions.

Appendix F, "HyperCard Synonyms," lists the abbreviations and alternate spellings for HyperTalk terms.

Appendix G, "HyperCard Limits," lists various minimum and maximum sizes and numbers of elements defined in HyperCard.

Appendix H, "HyperTalk Syntax Summary," shows the syntax of HyperTalk's command and function parameters in abbreviated form.

Appendix I, "HyperTalk Vocabulary," lists alphabetically each of the primary HyperTalk terms that HyperCard understands, names the category it's in, and provides a brief description of its meaning.

This book also contains a glossary of terms commonly associated with the HyperCard environment and an index to help you quickly find specific information contained in this guide.

Notation Conventions

Before you read this guide, you should know about a few typographic conventions. Words or phrases in a monospaced font like this are HyperTalk language elements or are to be typed exactly as shown. New terms are shown in **boldface** type when they are first introduced and defined. The glossary contains definitions of these terms and other related technical terms.

In descriptions of HyperTalk syntax for commands and other language elements, words in *italic* type describe general elements, not specific names—you must substitute the actual instances. (These elements are called *metasymbols* in this book.) Brackets ([]) enclose optional elements, which may be included if you need them. (Don't type the brackets.) In some cases, optional elements change what the message does; in other cases they are helper words that have

no effect except to make the message more readable. The vertical bar symbol (1) indicates a choice of elements: the syntax accepts either the element to the left or the element to the right of the vertical bar. Syntax descriptions for some language elements have a particular format, which is explained at the beginning of the chapter about that language element.

It doesn't matter whether you use uppercase or lowercase letters in commands or variable names; message names that are formed from two words are shown in small letters with a capital in the middle (likeThis) merely to make them more readable.

Changes Since the First Edition of This Guide

This edition of the *HyperCard Script Language Guide* is different from the first edition in several ways. Of course, it has new information in it that reflects the new features of HyperCard. In addition, the page format and design are different, and to make finding information easier, a few chapters have been divided into smaller chapters and others have been reorganized.

Chapter 1, "HyperTalk Basics," is now two chapters: Chapter 2, "HyperTalk Basics," which describes HyperTalk, and Chapter 3, "The Scripting Environment," dedicated to the script editor. Chapter 4, "Values," is now Chapter 6, "Values," and Chapter 7, "Expressions." Chapter 5, "Keywords," is now Chapter 9, "Control Structures and Keywords."

Chapter 12, "Properties," now has one main alphabetical list of properties, rather than having the properties grouped by the object or environment to which they can apply. For each property, the objects or environments to which it can apply are listed on the first line after the heading. Also, at the beginning of the chapter, there are tables that list properties by object or environment (button properties, field properties, painting properties, and so forth).

Apple Developer Programs

Apple's goal is to provide developers with the resources they need to create new Apple-compatible products. Apple offers two programs: the Partners Program, for developers who intend to resell Apple-compatible products, and the Associates Program, for developers who don't intend to resell products and for other people involved in the development of Apple-compatible products.

As an Apple Partner or Associate, you will receive monthly mailings including a newsletter, Apple II and Macintosh Technical Notes, pertinent Developer Program information, and all the latest news relating to Apple products. You will also receive Apple's *Technical Guide Book* and automatic membership in APDA. You'll have access to developer AppleLink and to Apple's Developer Hotline for general developer information.

As an Apple Partner, you'll be eligible for discounts on equipment, and you'll receive technical assistance from the staff of Apple's Developer Technical Support department.

For more information about Apple's developer support programs, contact Apple Developer Programs at the following address:

Apple Developer Programs Apple Computer, Inc. 20525 Mariani Avenue, M/S 75-2C Cupertino, CA 95014

This chapter is most useful for those who are already familiar with HyperCard because it describes the enhancements made to HyperCard since HyperCard 2.0. If you haven't done any scripting with HyperCard before, you should start with Chapter 2, "HyperTalk Basics," and work your way through the rest of the book. If you are already familiar with HyperCard, you can use this chapter as a guide to locations in the book that cover the new features of HyperTalk in more detail.

HyperCard 2.2 provides more power and flexibility across the entire range of Macintosh computers, starting with the Macintosh Plus. It incorporates features that improve the use of any HyperCard application on the smaller screen of the Macintosh PowerBook, Macintosh Plus, and Macintosh SE and on larger screens commonly used on the Macintosh II and other modular Macintosh computers.

Most of the new features of this HyperCard release are transparent and cannot be seen in the user interface. However, there have been several changes to the dialog boxes and their associated functioning. (For a more detailed description of the user interface, see the *HyperCard Reference*.) In addition, HyperCard 2.2 stacks are now globally localizable and can be scripted with scripting languages like AppleScript so that stacks can easily exchange information with other programs.

HyperCard System Requirements

HyperCard version 2.0 and later requires system software version 6.0.5 or later. Stacks created with earlier versions of HyperCard are opened as read-only in HyperCard version 2.0 or later. The earlier version stacks are write-protected until converted to the 2.0 format by choosing the Convert Stack command from the File menu.

Stacks that wish to take advantage of WorldScript features, open scripting, and the stand-alone application building capabilities of HyperCard 2.2 require system software version 7.1.

HyperCard Enhancements

HyperCard 2.2 provides several feature enhancements that make scripting easier and that enable your HyperCard stacks to be more flexible, robust, and powerful. You have always been able to use HyperTalk scripts to automate and customize your HyperCard application, but now, with Apple's Open Scripting Architecture (OSA) extensions to HyperCard 2.2, you can use scripts to integrate HyperCard with other applications so that you can use features of other applications in your stacks by exchanging data with those applications.

Most of the features of this release are controllable from the HyperTalk script language and can be easily used from any existing HyperCard script. Almost all of the improvements of this release are transparent, but are nonetheless important in making your stacks increase the execution speed of HyperCard. The following list summarizes the new features of HyperCard 2.2.

- WorldScript compatibility, which makes it easy to produce localizable stacks
- support for Apple's Open Scripting Architecture and communication between applications, including
 - $\hfill \square$ support for the AppleScript script language and other OSA-compliant scripting languages
 - □ script attachability so that you can choose the scripting language you wish to use in the HyperCard environment
 - ☐ HyperTalk equivalents to some AppleScript commands
 - ☐ HyperTalk support for embedded AppleScript instructions
- support for new button styles and features, including
 - standard buttons (rounded rectangle style without a shadow); similar to those found in most dialog boxes for the Cancel button
 - □ default buttons (with the additional 3-pixel-wide outline); similar to the OK button found in most standard dialog boxes
 - oval buttons (transparent, to overlay circular and oval shapes); HyperCard respects the actual shape of the button when tracking mouse actions

		pop-up menu buttons, which include a resizable title field and a menu area
		behavior conforming to the standards of <i>Macintosh Human Interface Guidelines</i> built into checkbox and radio button styles
		the family, partNumber, and enabled properties
ı	fie	elds that behave as lists, including highlighting of list items when clicked
ı	ar	integrated stand-alone application builder
•		iscellaneous improvements to HyperTalk made in response to developer quests; some examples are
		mouseDoubleClick system message
		script-controlled enabling and disabling of buttons
		text sorting by sort keys

WorldScript Compatibility

Software and Stackware are more commonly distributed worldwide now than when HyperCard was created, and the Macintosh system is now easily localized. Modifications have been made throughout HyperCard 2.2 to make it sensitive to the current key script or the current font script, as appropriate, in determining whether to invoke its special-case code for handling non-Roman text characteristics.

Also, the convert command now works with dates and times written in any format supported by any script installed in your system. See the convert command in Chapter 10, "Commands."

HyperCard and Other Scripting Systems

Using any scripting system that's compliant with Apple's Open Scripting Architecture (defined in the next section), like AppleScript, you can write scripts that extend the functionality of your stacks by integrating them with other scriptable applications, such as Claris FileMaker Pro 2.0 and Microsoft Excel 4.0. For example, you might want to store records detailing a large library of films and film clips in a database program like Claris's FileMaker Pro, which is built to handle large amounts of data efficiently.

The stack in Figure 1-1 uses AppleScript statements to request the FileMaker Pro Films database to look up a film (*Vertigo*) and send all the information it contains about the film to the HyperCard stack. The HyperCard stack then adds the information to its Hitchcock films stack, which is a smaller subset of all the films in the larger database.


The HyperCard stack also contains a script that examines the information sent back from the database to determine if a QuickTime clip of that movie exists. The HyperCard films stack then takes the information sent back from the Trailer cell in the films stack to look up the film clip and play it.

By working with another application, this HyperCard stack has extended what both applications can accomplish.

Open Scripting Architecture

Apple System software's **Open Scripting Architecture (OSA)** provides a standard mechanism that allows users to control multiple applications with scripts written in a variety of scripting languages.

Figure 1-1 Two applications exchanging information using the AppleScript capabilities of HyperCard 2.2



Each scripting language that utilizes OSA has a corresponding scripting component within its own application. When an application's scripting component executes a script, it performs the actions described in the script, much like HyperCard executes HyperTalk scripts.

HyperCard 2.2 users can now use its AppleScript extensions to communicate with applications and objects that are outside of HyperCard. This process is enabled by sending and receiving OSA-defined messages called **Apple events**.

Applications typically use Apple events to request services and information from other applications or to provide services and information in response to such requests.

AppleScript

The AppleScript component of the OSA, which implements the AppleScript scripting language, is the implementation provided by Apple that allows applications to exchange information and data.

AppleScript has a number of features that set it apart from other scripting systems:

- The AppleScript language makes it easy to refer to data within applications. Scripts refer to objects that closely correspond to familiar objects in applications. For example, a script can refer to paragraph, word, and character objects in a word-processing document and to row, column, and cell objects in a spreadsheet.
- You can script many different applications. Although there are applications that include built-in scripting or macro languages, most of these languages work for only one application. In contrast, you can use AppleScript to control any of the applications that support it. You don't have to learn a new language for each application.
- You can write scripts that control applications on more than one computer. A single script can control any number of applications, and the applications can be on any computer within a given network.
- AppleScript supports multiple dialects. These additional dialects can use words from another human language, such as Japanese, and have a syntax that resembles a specific human language or programming language. You can convert a script from one dialect to another without changing what happens when you run the script.

Comparing AppleScript and HyperTalk

AppleScript and HyperTalk are fairly similar. They both work by sending messages to objects within their systems. The major difference is that the system encompassing HyperTalk is the HyperCard application, whereas the system for the AppleScript language is the Macintosh system software. Essentially, this means that whereas HyperTalk instructions can be understood only by HyperCard, any application could potentially understand and act on a set of AppleScript instructions.

AppleScript works by sending messages, called *Apple events*, from scripts in one application to an object. An example could be an application within the environment of your Macintosh. HyperTalk works by sending messages, called *system messages, commands*, and *functions*, to HyperCard objects, like stacks, cards, backgrounds, buttons, and fields.

HyperCard 2.2 supports AppleScript by implementing a set of related Apple events called Apple event **suites**, as defined in the *Apple Event Registry*, including the Required suite, the Core suite, and the Text suite. It adds to these suites the HyperCard suite, an extension to the Apple events understood by AppleScript that exposes the functionality of HyperTalk to external scripting systems. The HyperCard suite includes AppleScript equivalents for most of the commands, functions, and properties defined in this book.

You can learn more about the AppleScript language and its tools from the *AppleScript Language Guide*.

Script Attachability

In HyperCard 2.2, scripts of HyperCard objects can be written either in HyperTalk or in a language defined by any external scripting system, such as AppleScript, that implements the optional attachability interface defined by the Open Scripting Architecture.

When HyperCard 2.2 passes a message to an object, it checks to see whether the script attached to that object is a HyperTalk script or a script belonging to an external scripting system, such as AppleScript.

If the script is a HyperTalk script, HyperCard uses its built-in mechanism for invoking HyperTalk message handlers. However, if the script is from an external scripting system like AppleScript, then HyperCard translates the message into an Apple event and uses a system software extension to invoke the relevant message handler.

A script attached to a HyperCard object receives HyperCard system messages according to its position in the inheritance hierarchy, regardless of its language. For example, a card script can handle the standard openCard message whether it's written in HyperTalk, AppleScript, or UserTalk.

Scripts can also pass messages to other scripts without regard to their language. When HyperCard receives an OSA-defined event, it translates the event to a message and sends it along the current message path.

Script Editor Enhancements

The script editor in HyperCard 2.2 is capable of editing text-based scripts belonging to any OSA-compliant scripting system, such as AppleScript. The script editor now has a pop-up menu that lists the available scripting systems, including HyperTalk, and lets you select the scripting system you want to use for the currently displayed script. You can also use the global property scriptingLanguage to set the scripting language you want to use for a stack in a startUp script. See the scriptingLanguage property in Chapter 12, "Properties."


Button Dialog Modifications

The Button Info dialog box contains these new items:

- a Preview area displaying a picture of the button with its currently selected attributes
- static text displaying the button's part number
- a checkbox for setting the button's enabled property
- a pop-up menu for selecting a number for the button's family property
- a Contents button for editing the contents of the button
- a Text Style button for setting the text font, size, and style of the button's name (and contents for pop-up buttons)
- a pop-up menu for selecting the button's style property (this replaces the set of radio buttons for button styles used by previous versions of HyperCard)
- a text-entry area, displayed only for pop-up buttons, for setting the button's titleWidth property

In addition, the Button Info dialog box is now a movable modal dialog box and can be dragged to new positions by the user. HyperCard 2.2 remembers the positions of movable modal dialog boxes while running; it does not remember their positions after you quit the program. Figure 1-6 shows the new Button Info dialog box.

Figure 1-2 Button Info dialog box




New Button Features

In HyperCard 2.2, buttons are now valid HyperTalk containers; thus, they can contain data. The contents of buttons can be edited in a dialog box that's accessible from the Button Info dialog box (see the Contents button in Figure 1-6). A button on the Clipboard can be pasted along with its contents by holding down the Shift key (the same as pasting a field and its contents). In HyperTalk, button expressions are now valid; they evaluate to the contents of the specified button (the same as field expressions evaluating to the specified field's contents).

The contents of a pop-up button have a special purpose. You use them to create the menu that pops up when the user clicks the pop-up button. Each line within the contents of the button becomes a menu item in the menu. Figure 1-3 shows the Button Contents dialog box containing the list of menu items for the SodaPopup button in Figure 1-6.

Figure 1-3 The Button Contents dialog box



Scripts can determine the number and text of the pop-up menu item that is currently selected by using the selectedLine and selectedText functions, described in Chapter 11, "Functions." You can use the contents of other types of buttons for any purpose.

Support for new styles of buttons in HyperCard 2.2 makes it easier to create stacks that comply with the *Macintosh Human Interface Guidelines*. For instance, you can now easily create the standard default buttons that appear in many Macintosh dialog boxes. HyperCard 2.2 also makes it easier to create radio

buttons and checkboxes that behave according to *Macintosh Human Interface Guidelines* standards without requiring a lot of scripting to get the standard behavior. Some of these buttons are shown in Figure 1-4.

Cancel OK Test Popup item2

In Figure 1-4, the Cancel button, shown in the standard button style; the OK button, shown in the default button style; and the Test Popup button, shown in the pop-up button style, illustrate three of the new styles.

As shown in Figure 1-4, pop-up buttons have both a title area and a menu area. The title of the button is drawn to either the right or the left of the menu area, depending on the script system of the button's font. If the script system is a left-to-right script system, the title is drawn on the left; otherwise, it is drawn on the right.

When the user resizes the pop-up button by dragging it from one of its corners, the width of the title area remains fixed. The user can drag the dividing line between these areas to widen one and narrow the other. You also can change the title area's width either by changing the Title Width value in the Button Info dialog box, or by setting the titleWidth property of the button from a script.

The default button style does not automatically provide the behavior a user expects from clicking a default button. You can provide that behavior by including a returnKey handler and an enterKey handler in the card, background, or stack script. Here is an example:

```
on returnKey
  if the selection is empty then pressDefaultBtn
  else pass returnKey
end returnKey

on enterKey
  if the selection is empty then pressDefaultBtn
  else pass enterKey
end enterKey
```

```
on pressDefaultBtn
   -- click the default button
  put the number of buttons into btnCount
  repeat with i = 1 to btnCount
    if the style of button i is default then
       click at the loc of button i
       exit pressDefaultBtn
    end if
  end repeat
end pressDefaultBtn
```

Also new is the oval style button, which is transparent. In the Button tool, both the rectangular and oval frames are visible, as shown in Figure 1-5.

Figure 1-5 Oval style button (shown in Button tool with Show Name checked)



The transparency of oval buttons makes them useful for overlaying oval or circular shapes. HyperCard respects this oval shape when tracking the mouse above it for highlighting or for sending messages. For example, mouseWithin messages aren't sent until the pointer enters the oval, and mouse clicks must be within the oval to count as clicks within the button. The shape of an oval button is defined by its rect property. Oval buttons whose rect property is a square are, not surprisingly, circular.

There are other less visible changes that have been made to buttons. For instance, there are five new button properties:

- The family property, which you can use to group buttons, makes it easy to get the behavior Macintosh users expect from a group of radio buttons.
- The partNumber property, which was invented specifically to give you read/write access to a property that represents the ordering of buttons and fields within their backgrounds and cards. The partNumber property of a

- button or field represents the ordinal position of the button or field among the objects of both kinds—buttons and fields—of the same card or background.
- The enabled property determines whether the button appears and behaves in an enabled or a disabled state. When a button is enabled, it appears and behaves normally. When it is disabled, the button is dimmed and it ignores mouse clicks—it neither highlights nor receives mouse messages.
- The scriptingLanguage property determines the scripting system of the button's script. For example, you can use the scriptingLanguage property to set a button to accept scripts written in AppleScript.
- The titleWidth property determines the width of the title area of a popup button. You can change the title area's width by changing the Title Width value in the Button Info dialog box, or by setting the titleWidth property of the button from a script.

You can read more about these properties in Chapter 12, "Properties."


Field Dialog Modifications

The Field Info dialog box contains these new items:

- a Preview area displaying a picture of the field with its currently selected attributes
- static text displaying the field's part number
- checkboxes for setting the field's autoHilite and multipleLines properties (described in the section "New Field Features")
- a pop-up menu for selecting the field's style property (this replaces the set of radio buttons for field styles used by previous versions of HyperCard)

In addition, the Field Info dialog box is now a movable modal dialog box and can be dragged to new positions by the user. HyperCard 2.2 remembers the positions of movable modal dialog boxes while running; it does not remember their positions after you quit the program. Figure 1-6 shows the new Field Info dialog box.

Figure 1-6 Field Info dialog box




New Field Features

HyperCard 2.2 lets you create fields that behave as lists. When the lockText and autoHilite properties of a field are set to true, the field responds to mouse clicks by highlighting the line that was clicked. If the multipleLines property is true, the user can hold down the Shift key and click again to extend the range of highlighted lines. Scripts can determine the range of lines that are currently selected in a list field by using the selectedLine function, and they can get the text of the selected lines by using the selectedText function, described in Chapter 11, "Functions." Figure 1-7 shows two list field examples.

Figure 1-7 List fields





The scrolling list field allows the user to click an item in the list to select it or to scroll through the list to peruse its contents without selecting anything. You can read more about the standard behavior of scrolling lists in the *Macintosh Human Interface Guidelines*.


Like buttons, fields also have a partNumber property and a scriptingLanguage property. See the discussion in the previous section for more information. You can read more about these properties in Chapter 12, "Properties."

Integrated Stand-Alone Application Builder

HyperCard 2.2 enables you to build a stand-alone application without the use of specialized external tools. This capability requires system software version 7.0 or later.

The standard file dialog box, shown in Figure 1-8, appears when you choose Save a Copy from the File menu. This dialog box contains a pop-up menu from which you can choose a file format. The choices in the pop-up menu are, at a minimum, Stack and Application, representing the standard stack and application formats, respectively. Third-party developers can add more file format choices by creating additional file translation modules for use with HyperCard 2.2, such as a stack-to-ScriptX translator or a stack-to-text translator.

Figure 1-8 Building a stand-alone application from your stack



Enhanced HyperTalk

The HyperTalk vocabulary has been enlarged to accommodate the new features within HyperCard. Table 1-1 describes the enhanced HyperTalk commands. Table 1-1 also includes the enhanced keword do. Table 1-2 describes the enhanced HyperTalk functions. Table 1-3 describes the enhanced HyperTalk properties. Note that the information in the "Definition" column of Tables 1-2 and 1-3 describes only new functionality. Table 1-4 describes the enhanced HyperTalk messages. See the appropriate chapters for syntax, definitions, and examples of items in these tables.

Table 1-1 Enhanced HyperTalk commands

Command

```
answer program promptText [of type processType]
close [docPathname with | in] appPathname
convert [chunk of] container|literal [[from format][and format]]¬
 to format [and format]
delete part
disable menu
disable menuItem of menu
disable button
do expression as scriptingLanguage
doMenu itemName [,menuName][without dialog]¬
    [with modifierKey [,modifierKey]]
enable button
find [international] text [in field][of marked cards]
find chars [international] text [in field][of marked cards]
find string [international] text [in field][of marked cards]
find whole [international] text [in field][of marked cards]
find word [international] text [in field][of marked cards]
lock error dialogs messages recent
open [fileName with] application
picture [fileName,fileType,windowStyle,visible,depth,floatingLayer]
```

Table 1-1 Enhanced HyperTalk commands (continued)

Command

```
read from file fileName [at [-]start]¬
    for numberOfChars|until char|constant

reply expression[with keyword expression]
reply error expression

request expression from program
request appleEvent class|id|sender|data

select line number [to number] of field
select line number of button

sort [lines|items of] container [sortDirection]¬
    [sortStyle] [by sortKey]

unlock error dialogs|messages|recent

visual [effect] push left|right|up|down [speed] [to image]
write text to file fileName [at [-]start|end|eof]
```

Table 1-2 Enhanced HyperTalk functions

Function	Definition
destination	Returns the full pathname of the destination stack when HyperCard is in the process of going to another stack.
diskSpace	Returns the amount of free space on any mounted volume.
number	Returns the number of menu items in a specified menu or the number of parts of a card or background. (These are new features of the number function. For a complete description of the number function, see Chapter 11, "Functions.")
programs	Returns a return-delimited list of all the System 7–friendly processes currently running on your machine.

Table 1-2 Enhanced HyperTalk functions

Function	Definition
selectedButton	Returns the name of the button that is highlighted in a family of buttons.
selectedLine	Returns the line number of the selected line (or lines) in a list field or pop-up style button.
selectedText	Returns the text of the selected line (or lines) in a list field or pop-up style button.
sum	Returns the sum of a list of comma-delimited numbers.
systemVersion	Returns a decimal string that represents the running version of system software.

 Table 1-3
 Enhanced HyperTalk properties

Property	Definition
address	Global; determines where HyperCard is running—that is, the full path, including network zone and machine name. This property works only in System 7.
autoHilite	Fields; defines a list field if the lockText property is also set to true.
bottom	Menu bar; determines the value of item four of the rectangle property (left, top, right, bottom) when applied to the menu bar.
bottomRight	Menu bar; determines the value of items three and four of the rectangle property (left, top, right, bottom) when applied to the menu bar.
dialingTime	Global; determines how long HyperCard waits before closing the serial connection to a modem after dialing.
dialingVolume	Global; sets the volume of the touch tones generated through the Macintosh speaker by the dial command.

 Table 1-3
 Enhanced HyperTalk properties (continued)

Property	Definition
enabled	Buttons; determines or changes whether the specified button appears and behaves in an enabled or a disabled state.
environment	Global; determines the environment of the currently running HyperCard application; returns development if it is the fully enabled development version and returns player if the HyperCard player is running.
family	Buttons; groups two or more buttons together into a family specified by the numbers 1 to 15, inclusive. If the button is part of a button family, clicking one of the buttons highlights it and unhighlights the rest of the buttons in that family.
height	Menu bar; determines the vertical distance, in pixels, occupied by the rectangle of the menu bar.
hilite	Buttons; determines whether the specified button is highlighted (displayed in inverse video). If the hilite property of a button in a family is set to true, the hilite property of the other buttons is automatically set to false.
ID	Windows, menus, and applications; determines the permanent ID number of a window or menu and determines the application signature of an application.
itemDelimiter	Global; determines what delimiter is used to separate a list of items. HyperCard resets the delimiter to its default, the comma, when the computer is idle.
left	Buttons, fields, and windows; determines the value of item one of the rectangle property (left, top, right, bottom) when applied to the specified object or window.

 Table 1-3
 Enhanced HyperTalk properties (continued)

Property	Definition
lockErrorDialogs	Global; determines or changes whether HyperCard displays an error dialog box in response to an error while executing a script.
lockText	Fields; defines a list field if the autoHilite property is also set to true.
name	Windows and HyperCard itself; determines the name of the specified object.
[english] name	Menus and menu items; the adjective english lets your code test for the names of menus and menu items.
number	Windows; determines the number within the window layer of any window on your screen.
owner of card	Cards; returns the name or ID of the background shared by this card.
owner of window	Windows; returns the name of the entity that created the window; this could be HyperCard or the name of an XCMD like Picture, for example.
partNumber	Buttons and fields; determines or changes the number that represents the ordering of the buttons and fields within their enclosing card or background. Setting this property can have the effect of either bringing the object closer or moving it farther (behind) other buttons and fields.
rect[angle]	Menu bar; reports the size of the menubar rectangle. This is a read-only property.
right	Menu bar; determines the value of item three of the rectangle property (left, top, right, bottom) when applied to the menu bar.
scriptingLanguage	Objects that can have a script and HyperCard itself; the scripting system used for the scripts of objects.

 Table 1-3
 Enhanced HyperTalk properties (continued)

Property	Definition
style of button	Buttons; new button styles are standard, default, oval, and popup.
titleWidth	Pop-up buttons; determines or changes the width of the title field for a pop-up button.
top	Menu bar; determines the value of item two of the rectangle property (left, top, right, bottom) when applied to the menu bar.
topLeft	Menu bar; determines the value of items one and two of the rectangle property (left, top, right, bottom) when applied to the menu bar.
visible	Menu bar; determines or changes whether the menu bar is shown or hidden on the screen.
width	Menu bar; determines the horizontal distance, in pixels, occupied by the rectangle of the menu bar.

Table 1-4 Enhanced HyperTalk messages

Message	Definition
appleEvent class, id, sender	Sent to the current card when an Apple event is received.
<pre>closePalette paletteWindowName, paletteWindowID</pre>	Sent to the current card when a palette that was opened with the palette command is closed.
closePicture pictureWindowName, pictureWindowID	Sent to the current card when a window that was created with the picture command is closed.
errorDialog	Sent to the current card when a script execution error occurs and lockErrorDialogs is set to true.

Table 1-4 Enhanced HyperTalk messages (continued)

M	es	sa	a	е

mouseDoubleClick

openPalette
paletteWindowName,
paletteWindowID

openPicture
pictureWindowName,
pictureWindowID

Definition

Sent to a button, field, or card after a second mouse click is released, when all of the following conditions are true:

- The second click is within the double-click time interval set in the Mouse control panel.
- The second click is at a location within 4 pixels of the first click.
- The second click is within the same object as the first click.

Sent to the current card when a palette is opened with the palette command.

Sent to the current card when a window is created with the picture command.

This chapter explains HyperTalk's place in the HyperCard system and describes some of HyperTalk's characteristics.

Most concepts are discussed only briefly in this chapter, with more detailed discussion left for later chapters.

What Is HyperTalk?

HyperTalk is the scripting language of the HyperCard environment. It allows you to perform actions on HyperCard objects: buttons, fields, cards, backgrounds, and stacks as well as other elements of HyperCard, such as menus and windows.

You use HyperTalk to send messages to and from HyperCard objects. You generate a message by (among other means) clicking the mouse, opening a card, typing a statement into the Message box, or choosing a menu item. Or you can generate a message by sending an Apple event message from a program—or process—outside HyperCard.

How a given object responds to a particular message depends on the object's script, or in the case of menu items, the menu message for that menu item. Most HyperCard scripts are written in HyperTalk, though version 2.2 of HyperCard makes AppleScript another scripting option.


Objects


There are five kinds of **objects** in HyperCard: buttons, fields, cards, backgrounds, and stacks. (See Figure 2-1.)

Buttons and Fields

Buttons are action objects or "hot spots" on the screen. For example, clicking a button with the Browse tool can take you to the next card in a stack. Clicking a pop-up button lets you choose an action from a menu.

Figure 2-1 HyperCard objects





Fields contain editable text. The Browse tool pointing hand changes to an I-beam when it's over an unlocked field. (The card or background might also contain Paint text characters. Such characters are not editable once they are placed; they become part of the picture on the card or background.)

Cards, Backgrounds, and Stacks

The basic unit of information is the **card:** when you look at the screen of a Macintosh computer running HyperCard, what you see foremost is a card. Cards are viewed through card windows. Cards can be larger than the card window and can be scrolled in the card window with the Scroll command in the Go menu. The **background** is where you place elements that you want a group of cards to have in common. Each card has one background. The card overlays the background; both are the same size. What you see in the card window belongs to the card or to the background. Both the card and background can contain buttons, fields, and pictures. Cards are grouped in **stacks**; each stack is a Macintosh file. Each stack can have multiple backgrounds.

The card that is currently displayed, the background associated with it, and the stack they are in are termed the current card, background, and stack. The concept of being current doesn't apply to buttons or fields. Chapter 5, "Referring to Objects, Menus, and Windows," contains details about referring to objects.

Messages

HyperCard objects interact with each other, with the user, with HyperCard, and with the Macintosh environment by sending messages. Some messages are descriptions of things that happen in the environment, such as that the mouse has been clicked or a card opened: these are **system messages**. They are like news flashes announced to the community of objects. For example, if you press the mouse button down, HyperCard sends the message mouseDown; when you let the mouse button up, HyperCard sends the message mouseUp. Chapter 8, "System Messages," contains more information about system messages.

Messages are sent to various objects in a particular order. For example, system messages generated by the mouse go first to the topmost button or field (if any) under the pointer on the screen. Next those messages go to the card, then to

Messages 25

the background, then the stack, then the Home stack, and finally to HyperCard itself. (You'll find a detailed discussion of this hierarchical sequence in Chapter 4, "Handling Messages.")

HyperTalk **commands** are also messages—orders to do some particular thing, like add two numbers or go to another card. A command, whether executed in a script or typed into the Message box, is sent as a message.

Scripts

Every HyperCard object has a script (although the script can be completely empty). A **script** is a collection of any number of handlers. A **handler** is a collection of HyperTalk statements; each statement ends with a return character. Any part of a statement following HyperTalk's double-hyphen comment character (--) is ignored by HyperCard.

A handler is invoked when a particular message is received by the object whose script contains the handler. A simple handler looks like this:

```
on mouseUp

go to next card
end mouseUp
```

The first line of a handler always begins with one of two words—either on or function. The last statement of a handler always begins with the keyword end. All HyperTalk statements always appear within handlers in a script.

You must place handlers in the scripts of objects that will receive the messages you want the handlers to respond to. The message-passing hierarchy, which determines where messages are sent, is described in Chapter 4, "Handling Messages."

Message Handlers

A handler that begins with on is called a **message handler**. The example in the previous section is a message handler. This particular message handler is in the script of a button; it handles the message mouseUp, and then goes to the next card.

The message to which a handler responds begins with the word following the word on. In this case, the message is mouseUp. When you release the mouse button while the Browse tool is inside a button's rectangle on the screen, HyperCard sends the message mouseUp to the button. HyperCard looks in the button's script for a handler matching the message mouseUp. If it finds a match, it executes the HyperTalk statements between on mouseUp and end mouseUp—in this case, go to next card.

Function Handlers

In addition to message handlers, scripts can contain user-defined **function handlers**. Function handlers begin with the word function instead of the word on; the name of the function they handle is the second word. A function handler looks like this:

```
function day
   return first item of the long date
end day
```

This function handler responds to a HyperTalk statement containing the function's name followed by parentheses—a **function call**. Here's an example:

```
put day() into message box
```

The function call is day()—the rest of the line and the function call together form a statement. When the function call is made, HyperCard looks for the matching function handler. If it finds one, it executes the lines between function day and end day. The value derived from the expression first item of the long date is returned to the put statement in place of day(). In the example, the value returned by the function (Friday, for example) is put into the Message box.

Function calls use the same message-passing hierarchy as messages; it's described in Chapter 4, "Handling Messages." Message and function handler structures are described in detail in Chapter 9, "Control Structures and Keywords."

Scripts 27

Windows

Windows are another HyperCard element that you can control with the HyperTalk language. Windows share many properties with objects but are not HyperCard objects because they do not have scripts or respond to messages. (Scripts and messages are described earlier in this chapter; see the section "Properties" in Chapter 6, "Values," for an introduction to HyperCard properties.)

HyperCard windows include card windows, the FatBits window, the Tools palette, the Patterns palette, the Scroll window, the Message box window, and external windows.

HyperCard's built-in external windows include the script editor, the Message Watcher, the Variable Watcher, and the Navigator palette. User-defined external windows include windows created with the picture command and windows created with external commands. (The picture command is described in Chapter 10, "Commands," and external commands, which control external windows, are described in Appendix A, "External Commands and Functions.")

Card Windows

You view the cards in a HyperCard stack through a card window. Card windows have a title bar, a zoom box, and if there is more than one stack open at the same time, a close box. A stack's card window can be the same size as or smaller than the current card size. You can reposition card windows by dragging them or setting HyperTalk properties.


HyperTalk allows you to control the following features of a stack's card window:

- the current size of the card window
- the current location of the card window
- the type of title shown in the title bar of the card window
- the current position or scroll of the card within the card window

Card windows are resized automatically when the card is resized from either the Stack Info dialog box or with HyperTalk. You can resize card windows

independently of the card. Card windows are located within the global coordinates of the screen. Cards are located within the card window's local coordinates. The representation of the relationship between the location of the card window and a larger card is shown in Figure 2-2. You can scroll the contents of a card that is larger than the current card window with the

Figure 2-2 Relationship between the location of a card and a card window



Windows 29

scroll property. See the location, rectangle, and scroll properties in Chapter 12, "Properties," for more information about moving and sizing card windows and cards.

To find out how to refer to HyperCard card windows with the HyperTalk language, see Chapter 5, "Referring to Objects, Menus, and Windows."

HyperCard's Built-in External Windows

HyperCard has several built-in external windows. They are the script editor windows, the Message Watcher window, and the Variable Watcher window. You can control the following properties of these windows with HyperTalk:

- the current font and style of text to use in the script editor window
- the current location of the Message Watcher window
- the current location of the Variable Watcher window
- the current size of the Variable Watcher window
- the positions of the horizontal and vertical bars of the Variable Watcher window

For more information about the script editor window, the Message Watcher window, and the Variable Watcher window, see Chapter 3, "The Scripting Environment."

Menus

You can also control the behavior of HyperCard menus with HyperTalk commands. Menus are not, however, HyperCard objects either, because like windows, they do not have a script and can't respond to messages. (Messages and scripts are described earlier in this chapter.)

Menus are containers. They contain menu items. Menu items can send messages to HyperCard objects with menu messages. If a menu item has a menu message, the menu message is sent to the current card or specified object when the menu item is chosen.

HyperTalk allows you to perform the following actions on menus:

- create new menus in the HyperCard menu bar with the create menu command
- add menu items to menus with the put command
- change the behavior of menu items by modifying a menu item's menu message with the menuMsg property
- change the style of menu item text with the textStyle property
- assign Command-key equivalents to menu items with the commandChar property
- assign checkmarks for menu items (to show they are chosen) with the checkMark and markChar properties
- determine the name of menus or menu items with the name property
- disable menus and menu items with the disable command
- enable menus and menu items with the enable command and enabled property
- delete menu items with the delete command (except in the Font, Tools, and Patterns menus)
- delete entire menus with the delete command (once deleted, they're gone, unless you recreate them)
- reset the HyperCard menu bar with the reset menubar command (once reset, all custom menus created with the create menu command are deleted)

To find out how to refer to HyperCard menus and menu items with the HyperTalk language, see Chapter 5, "Referring to Objects, Menus, and Windows."

Menus 31

Chapter Summary

Here is a summary of the material covered in this chapter:

- HyperTalk controls the properties of HyperCard objects: buttons, fields, cards, backgrounds, and stacks.
- HyperTalk also controls the properties of HyperCard windows and HyperCard menus, although these elements do not have scripts as objects do.
- HyperCard objects interact by sending and receiving messages.
- How an object responds to a message is specified by its script, which is written in HyperTalk or another HyperCard-compatible language like AppleScript.
- Scripts are collections of message handlers and function handlers.

This chapter describes the environment for creating and editing the scripts of HyperCard objects. It also describes the built-in script debugger that is part of the scripting environment.

Getting to the Script

You can get to an object's script through the Objects menu, shown in Figure 3-1. The Objects menu has five object Info items, one for each of the five types of objects: the buttons and fields belonging to the current card and background, the current card, its background, and the stack to which the current card belongs.

Figure 3-1 The Objects menu



You must be at level 5


The user level must be set to 5 for you to be able to look at scripts. To change the user level, choose Preferences from the Home menu and select Scripting on the Preferences card, or set the user level to 5 from the Message box with this statement:

```
set userLevel to 5 ◆
```

To edit the script of the current card, background, or stack, choose the appropriate Info menu item for the object whose script you want. This action brings up information about the object in an Info dialog box (see Figure 3-2). To open the object's script, click the Script button in that object's Info dialog box.

To get to the script of a button or field, first select the button or field (with the Button tool or Field tool), then choose the appropriate Info item from the Objects menu. It is not necessary to be working in the background to open the script of an existing background button or field. You must be working in the

Figure 3-2 Button Info dialog box



background, however, to create new background buttons and fields. (Working in the background may also help you to select background buttons and fields, because when you're in the background, HyperCard doesn't display card buttons and fields.)

Shortcuts

To get to the Info dialog box of a button or field quickly, double-click the button or field with the Button or Field tool chosen.

To open a button script directly, hold down Command-Option while you click anywhere inside the object's surrounding rectangle. To open a field script directly, hold down Command-Option-Shift while you click anywhere inside the object's surrounding rectangle. To open the script of the current card, press Command-Option-C. To open the script of the current background, press Command-Option-B. To open the script of the current stack, press Command-Option-S. ◆

You can close a script by choosing the Close Script command in the File menu, by pressing Command-W, or by clicking the close box in the upper-left corner. You can save a script by choosing the Save Script command in the File menu or pressing Command-S. To close the script without saving changes, press Command-period.

Shortcut


To save and close a script quickly, press the Enter key. ◆

The Script Editor

The HyperCard **script editor** lets you create and modify handlers in an object's script. You can have more than one script open at a time. The scripts may be from within the same stack or from different stacks (see Figure 3-3). The number of possible open scripts depends on the available memory in the Macintosh computer. When you work on a script, you are working in a script window. You can resize script windows and drag them to any position on the screen.

The Script Editor 35

Figure 3-3 Script editor window



Note

The script editor is implemented as an external window; you can replace it with a custom script editor that you define as an external command. See Appendix A, "External Commands and Functions," for information on external commands and external windows; see the scriptEditor property in Chapter 12, "Properties," for how to change to a custom script editor.

While a script window is active, the script editor menu bar, which includes a menu called Script, is accessible (see Figure 3-4). The commands in the Script menu are described later in this chapter.

Figure 3-4 Script menu

Script	
Find	₩F
Find Again	₩G
Find Selection	***
Scroll to Selecti	on
Replace	≆R
Replace Again	≆Т
Comment	Ж −
Uncomment	æ =
Check Syntax	**
Set Checkpoint	₩D

When you have a script window open, you can still use the regular HyperCard menu bar by making a card window, rather than a script window, active. If any part of a card window is visible, you can make it active by clicking it. You can also use the Next Window command from the Go menu or press Command-L to bring a card window to the front.

Manipulating Text

Many standard text editing features are available in the script window. You can use the arrow keys to move the text insertion point around in the script. If your script extends beyond the right border of the script window, you can scroll horizontally by using the scroll bar at the bottom of the script window. You can save the current script with Command-S and close it with Command-W. You can also print the current script with Command-P.

The Script Editor 37


The mouse manipulates an I-beam pointer with which you can place an insertion point or select text. You can double-click to select a word or triple-click to select a whole line. You can perform cut, copy, and paste operations using Command-X, Command-C, and Command-V, respectively. The selection that you've cut or copied remains in the Clipboard until you cut or copy again, in case you want to paste the material more than once. You can also paste it into a field as regular text or on a card or background as Paint text. You can undo a cut, copy, clear, or paste or any typing operation with Command-Z or by choosing Undo from the Edit menu.

You can change the font or size in which script text is displayed with the properties scriptTextFont and scriptTextSize. See Chapter 12, "Properties," for more information about these properties.

Searching for Text

The Find command in the Script menu is different from the HyperCard Find command in the regular HyperCard Go menu. If you choose Find from the Script menu (or press Command-F), you get the dialog box shown in Figure 3-5. The script editor locates and selects the first occurrence, following the current insertion point, of a string you type into the Find field. You can search for a whole word or a partial word. If you don't check Case Sensitive, Find ignores whether the letters in the word are uppercase or lowercase. If you check Case Sensitive, the case of each letter in the search string and the target string must match exactly. If you check Wraparound Search, Find searches for a string starting from the current insertion point to the end of the script, and then wraps around to the beginning of the script to continue the search. If Wraparound Search isn't checked, Find locates a string only if it is after the current insertion point.

Figure 3-5 Find dialog box



Replacing Text

Choosing Replace in the Script menu or pressing Command-R brings up the dialog box shown in Figure 3-6. Replace locates and replaces the first occurrence, following the current insertion point, of a string you type into the Find field with the string you type into the "Replace with" field. For locating the string to be replaced, you have the same options as for the Find command: whole or partial word, case sensitive or not, and wraparound search or not. You can also specify that HyperCard replace the string, replace every occurrence of the string, or just find and highlight the string.

Figure 3-6 Replace dialog box

Find:	
Replace with:	
○ Whole Word	☐ Case Sensitive
● Partial Word	■ Wraparound Search
Replace Repl	ace All) Find Cancel

Entering Comments

You can put comments in your script by preceding the comment text with two hyphens (--). HyperCard ignores any text on a line after the double hyphen. If a comment wraps to the next line in a script, it must have a double hyphen at the beginning of that line, too. You can insert a double hyphen at the insertion point by choosing Comment from the Script menu, by pressing Command-hyphen, or by typing two hyphens.

You can remove the double hyphen from a line with Command–equal sign or by choosing Uncomment from the Script menu. For the Uncomment command to work properly, you must place the insertion point next to one of the hyphens, or select any part of the line, as long as the selection includes the hyphens.

The Script Editor 39

The double hyphen is also useful when debugging or trying to improve the syntax in your scripts. You can precede statements in a handler with the double hyphen to prevent them from executing. To have HyperCard ignore an entire handler, you need to add the double hyphen to just the first line. This allows you to comment out a part of your script to see if that part is causing a problem.

Formatting Scripts

The HyperCard script editor indents control structures for you. It automatically indents all of the lines inside a handler structure when you finish typing a statement and press the Tab key, press the Return key at the end of the last line, or close its script window. (See Figure 3-7.) When if and repeat structures are nested inside each other or within handlers, the lines are indented further. (You can't nest handler structures inside each other or any other structure.)

Error checking

Automatic formatting provides some degree of error checking while you write a script: if you press the Tab key and the ending line in your handler isn't flush with the left margin of the script editor window, you probably left something out or made a syntax error in a HyperTalk command. •

Figure 3-7 Nested control structures

```
💵 Script of stack Prajna:HyperTalk (Prajna):Latest HyperC: 💵
  Scripting language: HyperTalk
                                                                     ⇧
    repeat with curBkgnd = 1 to the number of bkgnds
      set cursor to busy
      go to card 1 of bkgnd curBkgnd
       if the script of this bkgnd contains pattern
      then edit script of bkgnd curBkgnd
      repeat with curBqBtn = 1 to the number of bkqnd buttons
        set cursor to busy
        if the script of bkgnd button curBgBtn contains pattern
         then edit script of bkgnd button curBgBtn
      end repeat
      repeat with curBgField = 1 to the number of bkgnd fields
         set cursor to busy
         if the script of bkgnd field curBgField contains pattern
         then edit script of bkgnd field curBgField
      end repeat
    end repeat
```

Line Length and Script Size

The script editor doesn't wrap lines that are too long to fit in a script window. Lines too long to fit in the script window simply extend out of sight. Line length is, however, limited to 255 characters. A single script cannot exceed 30,000 characters, including spaces, return characters, and other invisible characters. If you reach this limit, think about moving some of your handlers to another object, such as a hidden field or button, and send messages to it as required. If you don't want statements to extend beyond the right boundary of the script window, you can break a single statement into multiple lines by pressing Option-Return where you want a line to break. This "soft" return appears in HyperCard scripts as a logical NOT symbol (¬). HyperCard treats lines broken in this way as single HyperTalk statements continuing to the next actual return character.

You can't break a literal

You can't put a "soft" return inside a quoted literal expression. (Chapter 6, "Values," describes literals.) ◆

Script Editor Command Summary

Table 3-1 is a summary of the script editor commands you can invoke from the keyboard.

Table 3-1	Script 6	editor	command	summary
I able 5-1	OCHE	Juitoi	COMMINIANA	Sullillary

Voy proce	Action
Key press	Action
Command-A	Select all
Command-C	Copy selection to Clipboard
Command-D	Set or clear temporary checkpoint at selected line (for debugger)
Command-equal sign	Uncomment selected line
Command-F	Display Find dialog box

 Table 3-1
 Script editor command summary (continued)

Key press	Action	
Command-G	Find again	
Command-H	Find the string currently selected elsewhere in the script	
Command-hyphen	Comment selected line	
Command-K	Check syntax (enabled only when scriptingLanguage is AppleScript)	
Command-L	Next window to front	
Command-Option-B	Open the script of the current background	
Command-Option-C	Open the script of the current card	
Command-Option-S	Open the script of the current stack	
Command-P	Print script or selection	
Command-period	Close script without saving changes	
Command-R	Display the Replace dialog box	
Command-S	Save script	
Command-T	Replace again	
Command-V	Paste Clipboard contents at insertion point	
Command-W	Close script	
Command-X	Cut selection to Clipboard	
Command-Z	Undo last operation	
Enter	Save changes and close script	
Option-click	Set or clear temporary checkpoint at selected line (for debugger)	
Option-click close box	Close all open scripts	
Option-Return	Carry statement onto new line ("soft" return \neg)	
Tab	Format script	

The Debugger Environment

This section describes the HyperTalk script debugger. The script debugger is integrated with the script editor to provide a set of easy-to-use debugging tools. You may find it easier to understand the features of the script debugger after learning more about HyperTalk, so you may want to skip this section and return to it later.

The HyperTalk script debugger has the following features:

- integration with the script editor for setting checkpoints within scripts
- debugging tools in the Debugger menu
- two windows for watching the progress of a script while it executes or while you step through the statements in a handler

In HyperTalk, a checkpoint serves the same purpose as a breakpoint in traditional development environments. You set a checkpoint at the location in a script at which you want to enter the debugger. You can also enter the debugger with the Command-Option-period key combination anytime while a script is executing. For example, you can get to the debugger by pressing Command-Option-period right after clicking a button that goes to another stack.

When HyperTalk enters the debugger, it pauses execution of the script, displays the script in a window, puts a box around the next line of the script to be executed, and displays a Debugger menu at the right end of the HyperCard menu. The Debugger menu, shown in Figure 3-8, has several menu items you can use to debug your scripts.

You can step through the remaining statements in the script with Command-S or by choosing Step from the Debugger menu. Each step executes the statement with a box around it, then moves the highlight to the next statement in that handler.

Figure 3-8 The Debugger menu

影		
Step	жs	
Step Into	ЖI	
Trace		
Trace Into	ЖΤ	
Go	₩G	
Trace Delay		
Set Checkpoint	₩D	
Abort	₩A	
Variable Watcher		
Message Watcher		

You can step into the trail of subhandlers with Command-I or by choosing Step Into from the Debugger menu. Step Into allows you to follow execution among multiple handlers when one handler calls another. When you choose Step Into and a message is sent from the currently executing handler, you go to the location in the current object's script or any object's script in the message-passing hierarchy that has a handler for that message. That message handler becomes a subhandler to the originally executing handler. You can then continue to step through the subhandler until its completion. After completion of the subhandler and any of its subhandlers, you go back to the line in your original handler following the statement that sent the message to the first subhandler. Subhandlers could be in any object script within the current message-passing hierarchy. (See Chapter 4, "Handling Messages," for information about handlers calling handlers and the message-passing hierarchy.)

You can trace the current handler to completion by choosing Trace from the Debugger menu. When you choose Trace, HyperCard executes each line in the current handler. Use Command-T or choose Trace Into in the Debugger menu to execute each line of the current handler including all of the subhandlers until the script's completion without having to manually step through the handlers. You can set the amount of time HyperCard waits between execution of the lines in a handler during a trace by choosing Trace Delay in the Debugger menu. The

trace delay value can also be set with the global property traceDelay. See Chapter 12, "Properties," for information about the traceDelay property.

You can exit the debugger with Command-G or by choosing Go from the Debugger menu.

Setting Checkpoints

You can set temporary and permanent checkpoints in a script. To set a temporary checkpoint in a HyperTalk script, set the insertion point anywhere in a line of a handler at which you want to enter the debugger and choose Set Checkpoint from the Script menu or press Command-D. You can also click anywhere in the line while pressing the Option key. A temporary checkmark appears in the margin to the left of the chosen location. To remove a temporary checkpoint, perform any one of the previously mentioned operations on the line with the checkmark. You can clear all the checkpoints in a script by clicking any checkpoint in the script while pressing Shift-Option.

You can have up to 16 temporary checkpoints per script in a maximum of 32 scripts. Temporary checkpoints are not saved with the script when you quit HyperCard.

You set permanent checkpoints in a script by inserting the HyperTalk statement debug checkpoint anywhere within a handler. There is no practical limit to the number of permanent checkpoints in a script. Permanent checkpoints are permanent in that they are saved with the script—they can be removed by deleting the debug checkpoint statement.

Checkpoints are ignored by HyperCard when userLevel is set lower than Scripting (user level 5).

HyperTalk Debugger Windows

The debugger windows are named the Message Watcher and the Variable Watcher. You can display one or both of these windows in two ways. They can be called by HyperTalk commands in a script or the Message box, or they can be displayed by choosing Variable Watcher or Message Watcher from the Debugger menu while you're in the debugger environment.

Message Watcher

The Message Watcher, shown in Figure 3-9, is an external window. It appears as a floating movable window that displays both HyperTalk messages and XCMD-generated messages as they are sent. You can display the Message Watcher window with either of these HyperTalk statements:

```
show Message Watcher set the visible of window "Message Watcher" to true
```

When you're in the debugger, you can also display the Message Watcher window by choosing Message Watcher from the Debugger menu.

Figure 3-9 The Message Watcher window



The Message Watcher window is always in front of the active window, which may be a card window or script window. (If you call the Message box, it appears in front of the Message Watcher.) You can close the Message Watcher window by clicking the close box or with either of these statements:

```
hide Message Watcher
set the visible of window "Message Watcher" to false
```

When you're in the debugger, you can close the window by choosing Message Watcher from the Debugger menu.

When "Hide unused messages" is checked, the Message Watcher displays only those messages that are handled by scripts. If "Hide unused messages" is not checked, you see all messages that are sent whether or not they are intercepted

by a handler. Each message that isn't handled in the message-passing hierarchy is displayed in parentheses. For example, (mouseWithin) displayed in the list indicates that there was no handler for the mouseWithin message in the message-passing hierarchy.

When "Hide idle" is checked, the Message Watcher doesn't display idle messages. If "Hide idle" isn't checked, idle messages are displayed.

The Message Watcher stores the last 150 lines of messages. Older messages are removed as the new messages fill the buffer.


Variable Watcher

The Variable Watcher, shown in Figure 3-10, is an external window. It appears as a floating window that displays the HyperTalk global variables and local variables set by the current script. (Variables are explained in Chapter 6, "Values.") Variables are displayed in a two-column format with the variable name in the left column and the current values in the right column. You can display the Variable Watcher window with either of these HyperTalk statements:

```
show Variable Watcher set the visible of window "Variable Watcher" to true
```

When you're in the debugger, you can also display it by choosing Variable Watcher from the Debugger menu.

Figure 3-10 The Variable Watcher window




The Variable Watcher window is always in front of the active window, which may be a card window or a script window. You can close the Variable Watcher window by clicking the close box or with either of these statements:

```
hide Variable Watcher
set the visible of window "Variable Watcher" to false
```

When you're in the debugger, you can close the window by choosing Message Watcher from the Debugger menu.

You can temporarily modify the values of global and local variables to see how they affect your stack application or scripting environment with the Variable Watcher. Drag the Variable Watcher size box to expand the window so that you can see the area below the thick horizontal line in the window. Click the variable name that you want to modify. The variable value is highlighted and placed in the field below the horizontal bar, as shown in Figure 3-11. You can edit the variable value by typing into the field. When you have finished changing the value, press the Enter key. The value for that variable is changed.

Figure 3-11 A selected variable in the Variable Watcher window



Custom Message Watcher and Variable Watcher XCMDs

The Message Watcher and Variable Watcher are implemented as external windows, so they can be replaced with custom external commands written in a programming language such as Pascal.

The Scripting Environment

To replace either the Message Watcher or Variable Watcher window with your own custom tools, set the global property messageWatcher or variableWatcher to the name of your tool with a HyperTalk statement like

set variableWatcher to "MyToolWindow"

For more information about creating external windows, see Appendix A, "External Commands and Functions."

Debugger Command Summary

Table 3-2 is a summary of the debugger commands you can invoke from the keyboard.

Table 3-2 Debugger command summary

Key press	Action	
Command-A	Stop the handler	
Command-D	Clear the current checkpoint	
Command-G	Go back to application	
Command-I	Step into and follow the path through any subhandlers	
Command-Option- period	Open the debugger while a script is running	
Command-period	Stop the handler	
Command-S	Step to the next line in current handler; step through any subhandler	
Command-T	Trace the handler and its subhandlers to completion; same as Step Into, but user interaction isn't required	

The Scripting Environment

Chapter Summary

Here is a summary of the material covered in this chapter:

- You can create and edit scripts with the HyperCard script editor.
- You can debug scripts with the built-in debugger.

This chapter explains how HyperCard objects send and receive messages and how HyperCard executes scripts.

The HyperCard Environment

HyperCard provides the environment in which HyperTalk scripts execute. The HyperCard environment consists of objects connected by a message-passing hierarchy and the HyperTalk language through which they communicate.

Although you could write a stand-alone program in a single HyperTalk script, you would not be making use of the power and flexibility of the HyperCard environment. Instead, you use HyperTalk to define the ways in which objects interact with each other and with the user.

HyperCard is user oriented. When using HyperCard, the user opens and closes cards, reads and changes text in fields, draws pictures on cards, and so on. HyperCard constantly sends messages to objects in response to these actions (and to the user's inactivity when doing nothing), and the objects in turn respond with other messages and other actions. The basic purpose of HyperTalk scripts is to enable objects to handle those messages and to specify succeeding actions by sending further messages.

Most of the time, scripts carry out specific actions for the user: setting properties of objects, going to other cards, and so on. HyperTalk can do automatically almost everything the user can do manually with the mouse and keyboard.

Sending Messages

All HyperCard actions are initiated by messages sent to objects. Messages are sent to objects in four ways:

- An event (such as a mouse click or a key pressed on the keyboard) can cause HyperCard to send a system message.
- Handler statements (other than keywords) are sent as messages when a handler executes.
- HyperCard sends the contents of the Message box as a message when the user presses Return or Enter.
- HyperCard sometimes sends a message when it executes a command.

System Messages

HyperCard sends system messages constantly in response to events in the Macintosh environment. For example, if you move the pointer so that it's over a button on the screen, as soon as the pointer enters the button's rectangle, HyperCard sends the message mouseEnter to the button. As long as the pointer remains inside the button rectangle, HyperCard continuously sends the message mouseWithin to the button. As soon as you move the pointer outside the button area, HyperCard sends the message mouseLeave to the button.

HyperCard sends other system messages when you press certain keys on the keyboard, close a field, choose a menu item, or quit HyperCard. When you open a card, HyperCard sends the message openCard to the card itself; when you leave the card, it sends closeCard. Similar messages are sent to cards when their backgrounds and stacks are opened and closed. If nothing at all is happening, HyperCard continuously sends the message idle to the current card.

One of the most commonly used messages is mouseUp. Buttons often contain handlers that respond to the mouseUp message; the mouseUp message is sent to a particular button when you click it. (HyperCard actually sends two messages to a button when it is clicked: mouseDown and mouseUp. The

mouseUp message is sent only if you release the mouse button with the pointer over the same screen button it was over when you pressed it down.)

HyperCard also sends mouse messages to a locked field when you click it. If the field isn't locked, mouseDown and mouseUp aren't sent—the click opens the field for text editing and HyperCard sends the message openField to the field. (You can send mouse messages to an unlocked field, however, by holding down the Command key while you click the field.)

Clicking outside all buttons and fields sends mouseDown and mouseUp directly to the current card.

Chapter 8, "System Messages," describes all of HyperCard's system messages.

Statements as Messages

When a handler executes, its statements are sent as messages, first to the object that contains that handler, then to succeeding objects in the message-passing hierarchy (described later in this chapter). When an object gets a message it can handle—that is, for which it has a handler in its script—the statements contained in the handler are in turn sent as messages. When all statements in the handler (and in any other handlers invoked along the way) have executed, the action stops.

Message Box Messages

When you type something into the Message box and press Return or Enter, HyperCard does one of these things: evaluates a valid expression and puts the result into the Message box, sends what you typed as a message to the current card, or sends a message to another destination if you use the send command. (See Chapter 7, "Expressions," for an explanation of evaluating expressions.)

You use send to direct a message to a specific object rather than sending it to the current card. Send is one of the HyperTalk keywords. You can use the keywords do, if...then...else, and send in the Message box. If you try to use a keyword other than these in the Message box, HyperCard displays an error dialog box. Table 4-1 contains all of HyperTalk's keywords.

Chapter 9, "Control Structures and Keywords," contains explanations of HyperTalk's keywords.

Table 4-1	HyperTalk's keywords	
do	next	
else	on	
end	pass	
exit	repeat	
function	return	
global	send	
if	then	

Messages Resulting From Commands

HyperCard sometimes sends a system message to the current card while executing a command. For example, when you create a card with the New Card menu command, HyperCard sends the message newCard to the card as soon as it's created; when you delete a card, it sends deleteCard. Similar messages are sent when other objects are created and deleted. These messages are among the results of commands executing, rather than commands themselves—they are like announcements of what is happening.

External commands can send messages

Experienced programmers can write definitions for new commands in development languages such as Pascal, C, and 68000 assembly language. Such external commands act much like built-in HyperTalk commands. External commands can send messages to the current card when they execute. See Appendix A, "External Commands and Functions," for information about external commands.

Receiving Messages

As senders and receivers of messages, objects all work exactly the same way. Every object has a script, and the type of object makes no difference to the execution of its handlers.

How objects differ

As elements of the HyperCard user interface, objects differ according to their function: buttons share a set of properties or characteristics that determine how they look and act; fields also share a set of properties, but it is different from the set of button properties. (See Chapter 12, "Properties," for a description of object properties.) •

When a message is sent to an object, HyperCard checks the object's script for a handler whose name—the second word on the first line of the handler—matches the message name—the first word of the message. If it finds a match, it executes each statement in the handler. (See Figure 4-1.) After the handler has run, the message is sent no further, unless it is explicitly passed with the pass keyword (discussed in Chapter 9).

Figure 4-1 Handler that responds to message openStack

```
If handler name on openStack
matches message
name,
then lines in that handler execute.

on openStack
global userName
if userName is empty then
ask "Please enter your name"
if it is not empty then put it into userName end if
pass openStack
end openStack
```

If the object has no handler for the message, the message passes to the next object in the hierarchy, and the process repeats. The message-passing hierarchy is explained in the next section.

If no object in the hierarchy has a handler matching a message name, HyperCard looks for a command by that name. Commands are like built-in handlers that cause some action to take place; mouseUp and most other system messages have no built-in handlers and cause no action. If a message gets all the way through the hierarchy and is not a system message or a command, HyperCard displays an error dialog box with the words Can't understand followed by the name of the message.

External commands can be in stacks

External commands can exist in stack files, as well as in the HyperCard application itself. See Appendix A, "External Commands and Functions," for information about external commands. •

Message-Passing Hierarchy


Messages are passed to objects according to a **message-passing hierarchy**. The message-passing hierarchy determines the path by which messages are passed from one object to another: buttons and fields are at the same level, followed (in order) by card, background, stack, the Home stack (the one stack that HyperCard requires), and HyperCard.

HyperCard allows you to add stacks to the message-passing hierarchy so you can use their scripts as shared-code libraries. More about the user-definable message-passing hierarchy is explained later in this chapter.

Where Messages Go

The position of an object in the message-passing hierarchy determines whether or not the object receives a given message and where subsequent messages that the object sends go. Most system messages are initially sent by HyperCard to the current card, as shown in Figure 4-2.


Figure 4-2 Message-passing hierarchy



Messages to Buttons and Fields

Any mouse message (for example, mouseEnter) is sent initially to the topmost button or field, if there are any, under the pointer. Any buttons or fields that are layered farther under the one initially receiving the message are ignored. Figure 4-3 shows layered buttons and fields. If the topmost button or field doesn't have a handler for the mouse message, the message is passed to the current card.

Figure 4-3 Layered buttons and fields



Background buttons and fields come before cards

HyperCard first sends mouse messages to the topmost button or field under the pointer, whether the button or field belongs to the card or the background, before passing the message on to the card. Background buttons and fields, however, are always farther away than card buttons and fields. •


Other than mouse messages, the only system messages that are sent first to buttons are deleteButton and newButton; system messages sent first to fields are closeField, commandKeyDown, deleteField, enterInField, exitField, keyDown, newField, openField, returnInField, and tabKey. The entry point in the hierarchy for all other system messages is the current card.

For a complete list of all system messages, see Chapter 8, "System Messages."

The Current Hierarchy

The current hierarchy consists of the buttons and fields belonging to the current card and its background, the card and background themselves, their stack, the Home stack, and HyperCard. System messages and those typed directly into the Message box always traverse the current hierarchy. Messages sent from executing handlers traverse the hierarchy in which their containing object belongs—in most cases, the current one. Figure 4-4 shows how a message traverses the current hierarchy.

Figure 4-4 Message traversing current hierarchy




When a handler executes, HyperCard sends each statement as a message, unless it begins with a keyword. It sends the message first to the object containing that handler, as shown in Figure 4-5. If that object doesn't have a

handler for the message, the message is passed down the object hierarchy; if none of the succeeding objects has a handler for it, the message ends up at HyperCard itself.

Function calls use the message-passing hierarchy

Function calls work like messages in the way they traverse the object hierarchy. When you make a function call with the syntax that uses parentheses, HyperCard looks in the script of each object in the hierarchy for a matching function handler. If none is found, the function call is passed to HyperCard itself. See Chapter 11, "Functions," for information about functions.

Figure 4-5 Command sent as a message



The Target

The object to which the message is first sent is the **target**. If HyperCard finds a handler in the target that matches the message name, the handler's statements start executing. If, however, the target has no matching handler, the message is passed down the hierarchy. HyperCard may find a matching handler in another object, which then begins executing, as shown in Figure 4-6.

The function the target returns the name of the original target, so that handlers in succeeding objects can determine where a message was originally sent. In Figure 4-6, although the executing handler is in the background script, target, used in the background handler, results in identifying the new button that originally received the system message newButton.

Buttons and fields

Cards

Backgrounds

Stacks

HyperCard

The target

On newButton set autoHilite of the target to true end newButton

HyperCard

The target

On newButton set autoHilite of the target to true end newButton

The User-Defined Hierarchy

HyperCard allows you to add stacks to the message-passing hierarchy, thereby extending the current hierarchy. Stacks added to the message-passing hierarchy act as shared code libraries. The code that they share is their script.

HyperTalk's message-passing hierarchy always includes the Home stack and HyperCard itself. Scripts in any stack can call handlers in the script of the Home stack, and external commands in the resource fork of either the Home stack or HyperCard because they are always in the hierarchy.


When a stack is added to the hierarchy, it is inserted between the current stack and the Home stack, as shown in Figure 4-7. That stack's script and all of the stack's resources can now be shared with objects higher in that hierarchy.

To add a stack to the message-passing hierarchy, use the HyperTalk command start using in a handler like this:

```
on openStack
   start using stack "HD:Trees"
end openStack
```


After the start using command in the example handler is executed, the handlers in the script of the stack Trees and any of its external commands and resources are available for use by Flora.

Figure 4-7 One stack added to the message-passing hierarchy



Each additional stack that is added to the hierarchy is inserted after the current stack, as shown in Figure 4-8. The maximum number of stacks you can have in a user-defined hierarchy is 16. If a stack that is already being used is used again with the start using command, it is moved in the hierarchy to the location just before the last stack that was inserted with the start using command.

Figure 4-8 Two stacks added to the message-passing hierarchy



The current hierarchy described earlier in this chapter isn't changed when you create a user-defined hierarchy—it is extended with the new stacks added to the hierarchy. Messages still traverse the hierarchy in the same way: they go down from the buttons and fields belonging to the current card and its background, to the card and background, to their stack, to any added stacks, to the Home stack, and finally to HyperCard.

Note

If you have a handler with the same name in more than one stack in a user-defined hierarchy, the handler highest in the hierarchy is executed when a message that calls that handler is sent. So if there's a handler for that message in the current stack, that's the one that gets executed. If there are handlers with the same name in two stacks that have been added to the hierarchy, the one in the most recently added stack is executed because it's higher in the hierarchy. •

The names of the stacks in the current hierarchy are stored in the global property <code>stacksInUse</code> in the form of a return-separated list of the stacks in the order in which they receive messages. If you create a card field, and then use the statement put the <code>stacksInUse</code> into <code>card field "Myfield"</code> in the Message box, it will return the list of stack names in the card field you created. Each stack that is placed in the hierarchy with the <code>start using</code> command is on a separate line in the field. If no stacks are added to the hierarchy, <code>stacksInUse</code> returns empty.

You can remove a stack from the user-defined hierarchy with the command stop using in the following statement:

stop using stack "Trees"

The stack is removed from the hierarchy, as shown in Figure 4-9.

Figure 4-9 Removing a stack from the message-passing hierarchy **Buttons** and fields Cards Backgrounds Current stack Flora Flora Added stack Fauna Fauna The statement Added stack **Trees** stop using stack "Trees" removes the stack Trees from the message-passing hierarchy Home stack

HyperCard

The Dynamic Path

When a message is traversing the hierarchy of a card different from the current one, HyperCard inserts a dynamic path into the static path the message normally follows. The **static path** is the route defined by an object's own hierarchy. For example, a card passes messages to its own background, the background passes them to its own stack, and so on. When that hierarchy is not the one stemming from the current card (the one currently active), HyperCard passes messages through the current card's hierarchy as well—that's the **dynamic path**.

Examples of situations in which a message traverses a hierarchy different from the current one, invoking the dynamic path, are

- when an executing handler contains a command that takes you to another card (such as go or a command to create or delete the current card)
- when you use the send keyword to send a message to an object not in the current hierarchy


When any message that has not been received by a handler reaches the stack, HyperCard checks to see if the current card is in a different hierarchy. If so, HyperCard passes the message to the current card, and it traverses the current card, background, and stack before it passes to the Home stack.

If any handler receives the message and passes it explicitly with the pass keyword, HyperCard does not invoke the dynamic path unless the current hierarchy is in a different stack from the static path. If either of the hierarchies is in the Home stack, the message is not passed again to the Home stack.

The Go Command and the Dynamic Path


Figure 4-10 and Figure 4-11 show how a handler containing a go command invokes the dynamic path.

Figure 4-10 Static path before the go command executes



In Figure 4-10, the mouseUp handler executes the statement beep 2, which is sent as a message along the current hierarchy beginning with the button containing the handler. After the go command executes, the current card changes. Nonetheless, the button's mouseUp handler continues to execute, sending subsequent statements as messages through its own hierarchy, in this case the beep 3 statement. In addition, however, HyperCard now sends messages to the card, background, and stack of the new current hierarchy, as shown in Figure 4-11.

Figure 4-11 Dynamic path after the go command executes



The Send Keyword and the Dynamic Path

You can use the send keyword to direct a message to

- any object in the current stack
- any other stack on any disk or file server accessible to your Macintosh computer (but not any individual object in those stacks, unless you go to that stack first); the stack need not be in the current hierarchy
- HyperCard itself

For example, you can type the following statement into the Message box:


```
send "greetings" to stack "Birds"
```

HyperCard looks in the script of the object to which the message is sent (in this case, stack "Birds") for a matching handler, just as if it were in the current hierarchy. If the matching handler isn't found (in this case, a handler named greetings), the message goes down the hierarchy stemming from the object to which it was sent (that is, from stack "Birds"). If the target of the send command is an object other than the current one, HyperCard invokes the dynamic path.

Figure 4-12 shows the path of a message directed with the send keyword.

The executing handler, the one currently in control, need not be in the hierarchy belonging to the current card. Which handler has control is determined solely by which object receives a message.

Figure 4-12 Using the send keyword



For details about the send keyword, see Chapter 9, "Control Structures and Keywords."

Handlers Calling Handlers

When a handler executes, HyperCard sends each statement as a message first to the object containing the executing handler so that other handlers in the same script, as well as those in any other script lower in the message-passing hierarchy, can be used as subroutines. A handler can also call itself, which is known as **recursion**.

Subroutine Calls

You can use handlers in HyperCard the way you use procedures or subroutines in other languages. You invoke a subroutine call in HyperTalk by executing a statement that begins with the name of a handler. That name is sent as a message, first to the object that contains the executing handler, then along the current object hierarchy.

You can include a subroutine in a script by writing a handler in the same script (or any other script lower in the object hierarchy) with whatever name you'd like to call it. In the following example, the handler greetings is defined in the same script as the one from which the message greetings is sent:

```
on mouseUp
   greetings
end mouseUp

on greetings
   Put "You've just been drafted!" into the Message box
end greetings
```

When HyperCard executes the statement consisting of the subroutine handler name and a match is found between the name and its handler, control passes to the subroutine handler. After it has finished executing, control passes back to the calling handler. But it's entirely possible for the subroutine handler to issue a similar message, beginning execution of a third handler. The third handler

must finish executing before control passes back to the second handler, which in turn must finish executing before control passes back to the first. The execution of a handler that has invoked another handler is suspended until the handler it has called finishes executing.

Stopping execution

A handler can avoid giving control back to pending handlers by executing the exit to HyperCard keyword statement. You can interrupt an executing handler at any time (and bypass pending handlers) by pressing Command-period. •

Any handler can act as a subroutine for any other handler. The called handler either has to be in the same script or in a script lower in the object hierarchy. However, you can also use the send keyword to send the message (the subroutine handler name) directly to the object that contains the handler. (See Chapter 9, "Control Structures and Keywords," for details on using send.) Generally, handlers that act as subroutines are placed in the same script as the handlers that call them.

IMPORTANT

Handlers can't be nested. That is, they can't be defined with one inside another—a handler definition must not appear between the on statement and the end statement of another handler. ▲

Recursion

If you need to repeat an operation over and over, you can have a handler call itself. In the following example, the handler decrement subtracts 1 from a number in the Message box until the number is reduced to 1 (a number must be in the Message box before you call the handler). To do the subtraction, the handler summons itself:

```
on decrement
  subtract 1 from the message box
  if the value of the message box > 1 then decrement
end decrement
```

Generally, subroutine calls and recursion don't cause any problems. In fact, they are natural consequences of the good programming technique of separating scripts into functional units. However, HyperCard has a limit on the number of pending handlers. The actual number depends on the complexity of the handlers and other factors. It doesn't matter whether a handler is invoking itself or another handler—either type of invocation causes another level of pending execution.

In particular, watch out for endless recursion, as in the following handler (if it were in a stack script or the script of every card):

```
on openCard

go to next card
end openCard
```

The go to next card command results in an openCard message, so the handler recurses again and again, and you get an error dialog box. The HyperCard limit for such a recursion is limited by memory.

Using the Hierarchy

Where you place a handler in the hierarchy determines when it will be called. All objects that are higher in the hierarchy can call handlers in objects lower in the hierarchy. Lower objects can't call handlers in higher objects unless they use the send keyword. Messages that are sent when a statement in a handler executes always go first to the object containing the executing handler. Then they traverse the hierarchy stemming from that object until they find a matching handler or reach HyperCard itself. Therefore, the farther down the hierarchy a handler is placed, the greater the number of objects that can pass messages to it.

Sharing Handlers

In effect, every object has access to the handlers of all the objects lower than it in the hierarchy, which also includes the handlers in stacks put into the message-passing hierarchy with the start using command. If you want


every card in a stack to have a certain capability (that is, to respond to a certain message), you put the appropriate handler in the stack script. Every card can use the handler by passing the message down to the stack.

Figure 4-13 and Figure 4-14 show the effect of placing a handler at different positions in the hierarchy. The example handler responds to the message moveOn (the message name is for example only). The handler takes you to the next card:

```
on moveOn

go to next card
end moveOn
```


Figure 4-13 Handler in a card script



You can place the handler in the script of one card, as in Figure 4-13. Then, if you send moveOn from the Message box, you invoke the handler and go to the next card only if the current card is the one with the handler. If the current card is not the one with the handler, however, the moveOn message produces an error.

In Figure 4-14, the handler is in the script of the stack, so the handler is invoked by sending moveOn to any card in the stack.

Figure 4-14 Handler in a stack script



Intercepting Messages

You can also make any card you want an exception in the way it responds to a given message, without affecting the other cards in the stack, by putting a special handler for the message in that card's script: you write two different handlers with the same message name—one in the stack script and one in the card script. Then, for that same message, if the message comes through that particular card, the card's handler runs; from any other card, the stack's handler runs.

For instance, in the previous example, putting the handler in the stack script caused the message moveOn to take you to the next card from any card in the stack:

```
on moveOn

go to next card
end moveOn
```

But if you want the last card in the stack to be an exception, from which the message moveOn takes you back to the Home stack, put the following handler in the last card's script:

```
on moveOn


go to stack "home"
end moveOn
```

Figure 4-15 illustrates this example of one object intercepting a message.

A handler can intercept a HyperTalk command

In the same way that you can give one card a unique way of handling a message that would ordinarily be handled in the background or stack script, you can write a handler with the same name as a HyperTalk command and place it anywhere in the hierarchy. But remember that your handler is the one that will ordinarily run in response to the command message, not HyperCard's built-in one. HyperTalk functions can be redefined in a similar manner, and the same warning applies. •

Figure 4-15 Intercepting a message



Parameter Passing

When a HyperTalk message is sent, the first word is the message name. For example, in the message

searchScript "WildCard", "Help"

the message name is searchScript. Any other words (or characters) are the **parameters.** In the example, the parameters are "WildCard" and "Help". Each receiving object in the hierarchy looks for a message handler with a matching name. If the object finds a matching handler, the parameters are passed into that handler.

Parameter Passing 77

Parameters are passed into handlers as a list of comma-separated expressions. (Chapter 7, "Expressions," describes expressions.) These expressions are evaluated before the message is sent by the current object and, when the message is received by the receiving object, placed into a list of comma-separated **parameter variables** appearing on the first line of the matching handler definition. (See Figure 4-16.) That is, parameters are passed by value into handlers. In the searchScript handler example shown in Figure 4-16, the parameter variables pattern and stackName are replaced by the parameter values "WildCard" and "Help".

Parameter variables are local variables of the handler in which they appear. Parameter variables are also called **formal parameters**, to contrast them to the **actual parameters**, which are the parameter values passed to them.

Function handler parameters


HyperCard passes parameters into function handlers and message handlers in the same way, except that the syntax of the function call requires the parameters to be placed between parentheses. Placement of the parameter variables on the first line of function handlers is identical to that of message handlers. •

The value of the first expression in the message is placed into the first parameter variable in the handler, the value of the second expression into the second parameter variable, and so on. If there are more expressions in the message's parameter list than there are parameter variables in the first line of the handler, the extra parameters are ignored. If there are more parameter variables than parameters, the extra parameter variables are given an empty value (equal to a string of zero length).

Passing parameters to redefined commands

HyperTalk command parameters are often more complex than a comma-separated list of expressions. Some built-in commands take parameters to which user-written handlers have no access. So, if you redefine a command, you may not be able to pass all of the parameters to your handler. •

Figure 4-16 Parameter passing



Chapter Summary

Here is a summary of the material covered in this chapter:

- The HyperCard environment consists of objects related to each other in a hierarchy using HyperTalk as the means of communicating.
- Messages sent to objects initiate all HyperCard actions.
- Messages are generated by system events, executing handlers, statements typed into the Message box, and the execution of some commands.
- When an object receives a message, HyperCard tries to match the message name with a handler in the object's script; if it finds a match, it executes the handler; otherwise it passes the message to the next object.

- The object hierarchy determines how messages are passed from one object to another.
- You can modify the message-passing hierarchy to use stacks as sharedcode libraries.
- You can send a message directly to any object in the current stack, to another stack, or to HyperCard using the send keyword.
- A handler can initiate execution of another handler as a subroutine call.
- Every object can use the handlers of objects lower than it in the hierarchy by passing messages; conversely, an object can intercept a message to perform a different action.
- The values of a series of expressions following the first word of a message statement are passed to variables in the first line of the receiving handler.

Referring to Objects, Menus, and Windows

This chapter explains how to refer to HyperCard's objects, menus, and windows.

A HyperCard object has three characteristics:

- It can send and receive messages.
- It has properties, which are its defining characteristics, and one of those properties is its script.
- It has a visible representation on the Macintosh screen (although the object need not always be visible).

HyperCard menus, windows, and the menu bar share many of the characteristics of HyperCard objects, except that they don't have the script property.

You refer to an object when you use the go command (to go to a particular card, background, or stack) or the send keyword (to send a message to a particular object), and when you want to manipulate an object's properties. Fields are unique because they are HyperCard objects and are also sources of values (described in Chapter 6, "Values").

You can think of HyperCard itself as an object, because it can send and receive messages and has global properties, including a "script" of built-in handlers or commands. When this book talks about objects, however, it usually refers to buttons, fields, cards, backgrounds, and stacks.

Names, Numbers, and IDs

You refer to objects using **object descriptors**. An object descriptor is formed by combining a generic name with its specific designation. Generic names are stack, card (abbreviated cd), background (abbreviated bkgnd or bg),

Referring to Objects, Menus, and Windows

button (abbreviated btn), field, part (which refers to a field or button), or family (which refers to a group of buttons).

HyperCard considers all references to buttons, button families, and parts to be card buttons, card families, or card parts and all references to fields to be background fields unless you specify otherwise. For example, button "buttonName" and card button "buttonName" both refer to the card button, and field "fieldName" refers to the same field as background field "fieldName". To refer to background buttons, you must include background in the descriptor—for example, bkgnd button "buttonName". If you want to refer to card fields, you must include card—for example, card field "fieldName".

The only specific designation of a stack is its name. (See "Identifying a Stack," later in this chapter.) The specific designation of all other objects (buttons, fields, backgrounds, and cards) can be the objects's name, number, or ID number. The unambiguous form of an object descriptor begins with an object's generic name, immediately followed by its particular name, number, or ID number. (See Figure 5-1.)

Figure 5-1 Card Info dialog box and descriptors for the same card



Card 1
First card
Card one
Card "Welcome to É"
Card ID 3916

Referring to Objects, Menus, and Windows

Descriptor phrasing

Be careful to phrase descriptors so that they mean what you intend. For example, using a descriptor such as card field id 7, you could mean that the name of the card is in the background field with ID number 7, or you could be referring to the card field with ID number 7. HyperCard assumes that you're referring to the card field. If you want HyperCard to get the card name from the background field, enclose its descriptor in parentheses:

card (field id 7) ◆

Object Names

Names are optional for cards, backgrounds, buttons, and fields. You assign a name for any of these objects by typing into the Name box in the object's Info dialog box, which appears when you choose the object's Info command from the Objects menu.

Object names can include any characters, even spaces. When you use a name (background button "belly") in a statement, put quotation marks around the object name to ensure that HyperCard recognizes it as a literal and doesn't look for a variable by that name. Names are not optional for stacks. You must provide a name for each new stack you create. A stack name must be a valid Macintosh filename.

Be careful with names

It's difficult to manipulate a name that extends out of the naming window, although you can scroll it left and right (and up and down if it has more than one line) by dragging. It's also difficult to refer by name to an object if you put a double quotation mark in its name. Also, if you use numbers for an object's name, HyperCard could misinterpret the name: it takes card "1812" to mean a card whose *number*, rather than name, is 1812. ◆

Referring to Objects, Menus, and Windows

The name of an object is one of its properties. (See Chapter 12, "Properties," for an explanation of properties and a description of the name property.)

The name property of an object has three forms—long, abbreviated, and short. The long name of an object includes the type of object, its name, its enclosing object (either a card or background), and the full pathname of its stack:

```
card button "Rolo" of card "Home" of stack
"MyHardDisk:Home"
```

The abbreviated form includes the type of object and its name:

```
card button "Rolo"
```

The short form includes just the name:

```
"Rolo"
```

Object Numbers

Buttons, fields, cards, and backgrounds always have numbers by which you can refer to them. An object's number represents its position within its enclosing object: buttons and fields are ordered within a card or background, as are card parts (remember that this term refers to both buttons and fields) and button families; cards and backgrounds are ordered within their stack.

For objects and parts with numbers one through ten, there are three ways to express an object's number: use an integer following its generic name (card 2), use one of the numeric constants one through ten following its generic name (card two), or use one of the ordinal constants first through tenth preceding its generic name (second card). For objects with numbers higher than ten, you have to use the integer value.

Object numbers are contiguous from one through the number of currently existing objects within the enclosing object: card buttons and card fields within their card; background buttons and background fields within their background; cards within their stack (not their background); and backgrounds within their stack. If you delete an object, its number is reassigned to the object following it in order, and so on for the succeeding objects as well.

Part Numbers

A part is the generic name for either a button or field. HyperCard thinks of buttons and fields as parts of either their enclosing backgrounds or cards and, as such, numbers them as they are generated. If you don't specify, HyperCard assumes you are referring to card parts.

The reference to generic parts rather than specific buttons or fields makes it much easier to iterate through all the buttons and fields in a stack. You can use the number function to count the number of parts of a card or background. (See number in Chapter 11, "Functions.")

This example shows a handler that searches through all the scripts of a stack to find a word pattern. It is actually a shorter form of the searchScript handler, which you can find in your Home stack, rewritten to iterate through script parts rather than buttons and fields:

```
on searchScript pattern
global ScriptFindString
push card -- remember where we are
set lockMessages to true
set lockRecent to true
if pattern is empty then
   ask "Search for what string?" with ScriptFindString
   if (it is empty) or (the result is "Cancel")
   then exit searchScript
   put it into pattern -- otherwise save it in pattern
end if
put pattern into ScriptFindString
set cursor to busy
-- search the stack script of the stack
if the script of this stack contains pattern
then edit script of this stack
```

```
-- search the background scripts
repeat with curBkgnd = 1 to the number of bkgnds
   set cursor to busy
   go to card 1 of bkgnd curBkgnd
   if the script of this bkgnd contains pattern
   then edit script of bkgnd curBkgnd
-- search the scripts of background parts
-- (bg buttons and fields)
   repeat with curPart = 1 to the number of bg parts
      set cursor to busy
      if the script of part curPart contains pattern
      then edit script of part curPart
   end repeat
end repeat
-- search the card and card part scripts of the stack
repeat with curCard = 1 to the number of cards
    set cursor to busy
   go card curCard
    if the script of this card contains pattern
    then edit script of this card
-- otherwise search through the card buttons and fields
   repeat with curCdBtnOrFld= 1 to the number of ¬
      card parts
      set cursor to busy
      if the script of card part curCdBtnOrFld ¬
      contains pattern
      then edit script of card part curCdBtnOrFld
   end repeat
end repeat
pop card -- return to where we were
set lockMessages to false
set lockRecent to false
```

```
restoreUserLevel -- set userLevel back to whatever it was answer "Search script done!" -- \Delta end searchScript
```

Button Families

Button families are specified by number only; they do not have names or IDs. Only the numbers from 1 to 15, inclusive, are valid. An example of a HyperTalk reference to a button family is

cd family 1

Special Ordinals

In addition to the ordinal constants first through tenth, HyperTalk has three special ordinals: middle, last, and any. The values of the special ordinals are resolved according to the number of objects in the set. Middle resolves to half the number of objects (rounded down to the nearest integer) plus 1. The ordinal last resolves to the number of objects. Any resolves to a random number between 1 and the number of objects. (The special ordinals also work with chunk expressions, which are described in Chapter 7, "Expressions.")

Object Numbers and Tab Order

The sequence of object numbers determines tab order for fields: you can move from field to field within a background and card using the Tab key—it moves from the lowest numbered field to the highest through the background fields first, then the card fields. The sequence also determines which button or field gets a message when several are layered on top of each other (the highest numbered one is closest and gets the message), and it determines which card or background is referred to by the special descriptor next or previous (see the section "Special Object Descriptors" later in this chapter).

Reassigning object numbers

You can reassign object numbers of buttons and fields with the Bring Closer and Send Farther menu commands. See the *HyperCard Reference Guide* for details. ◆

Object ID Numbers

HyperCard generates an object ID number for each object within a stack. This number is unique for that type of object within its enclosing object. For example, each button (the type of object) on a card (the enclosing object) has a different ID number. Object ID numbers never change, and if an object is deleted, its number is not reassigned to a newly created object (until the HyperCard object limit, listed in Appendix G, has been reached). An object's ID number is its generic name, followed by the word ID (in uppercase or lowercase), followed by an integer (for example, card id 5734).

The ID number of a copied object is different

If you copy an object and paste it into a different enclosing object, the copy is then a different object from the original, and it has a different ID number. For example, if you copy a card and paste it into a different stack, the ID number of the pasted card is different from the ID number of the card you copied. Therefore, you can't assume that you have "moved" the card when you copy it, paste it, and delete the original—a button that took you to the original will probably not take you to the copy. •

Because ID numbers are unique and unchanging for all objects within a stack, HyperCard uses them internally to identify objects (for example, to identify the target of a go command generated with the LinkTo feature in the Button Info dialog box). HyperCard can generally find objects faster if they are identified by ID number. If you ask for the name of an object that has no name (put the name of last card), HyperCard returns its ID number.

The ID of an object is one of its properties. The ID property of an object has three forms that are similar to the three forms of the name and are differentiated by the same adjectives—long, abbreviated, and short. The long ID of an object includes the type of object, its ID number, its enclosing object if necessary, and the full pathname of its stack:

```
card id 2590 of stack "HyperDisk:HyperCard:Stacks:Home"
```

The abbreviated form includes the type of object and its ID number:

card id 2590

The short form includes just the ID number:

2590

All objects except stacks always have ID numbers; stacks never have ID numbers.

Special Object Descriptors

You can use the special descriptor this to refer to the current card, background, or stack—for example:

put the id of this card into whereFound

You can't use this with buttons or fields.

You can refer to the card or background preceding the current one, within the stack, as previous, which can be abbreviated prev. Similarly, you can refer to the card or background following the current one as next—for example:

go to next background

You can refer to the card that was current immediately prior to the current one as recent.

You use me within a script to specify the object containing the currently executing handler. For example, this statement in a field script would put the value of the textHeight property of the field into the variable height:

put the textHeight of me into height


Identifying a Stack

A stack is a HyperCard document. In some cases when you're writing a script or using the Message box, you can refer to a stack by its name alone. To do that, the stack must be in the current folder, in the folder containing the HyperCard application, or in a folder listed in the global variable stacks. (The stacks variable gets its list of folders on startup from the Stacks Search Paths card of

the Home stack. The Stacks Search Paths card is one of three Search Paths cards that contain lists of search paths, or pathways through the folders on your disk, that HyperCard should follow to retrieve a stack, application, or document.) When the stack is located anywhere else, you must let HyperCard know the full pathname by which it can find the stack.

A full pathname is a concatenation of the volume name, directory name or names, and filename, separated by colons. The volume name is the name of the disk or server containing the stack. The directory names are the names of all the folders, if any, that HyperCard has to open to get to the stack. (HyperCard sometimes might have to open several folders because folders may contain other folders to any depth.) The filename is the stack name. Figure 5-2 shows the structure of a pathname.

Figure 5-2 A pathname



The only unambiguous way to refer to a stack in a script or in the Message box is the word stack followed by its name in quotation marks. When you refer to a stack, you can use the full pathname to specify the stack's exact location:

go to stack "myDisk:myFolder:mystack"

You can also type the folder name in the Stack Search Paths card of the Home stack. If HyperCard can't find a stack you request, it displays a dialog box that allows you to click your way through the directories until you reach the stack. HyperCard notes your path and, once you've found the stack, automatically records its folder on the Search Path card in the Home stack.


Ambiguous stack descriptors

HyperCard tries to derive a proper stack name from an ambiguous expression in a place where it expects a stack descriptor, but it cannot always succeed. In that case, HyperCard displays the directory dialog box to allow the user to find the stack file. •

Naming a Stack


You must name a stack when you create it. (For all other objects, names are optional.) You create a stack with the New Stack command in the File menu or with the create stack command. (See Chapter 10, "Commands," for more information about the create stack command.) When you use the New Stack command, a dialog box appears in which you type the name for the new stack. (See Figure 5-3.) You can also select the card size for your stack either by dragging the rectangle on the right side of the dialog box or by selecting one of the preset sizes available from the pop-up menu in the upper-right corner, as shown in Figure 5-4.

Figure 5-3 New Stack dialog box



Identifying a Stack

Figure 5-4 New Stack dialog card-size pop-up menu



Combining Object Descriptors

To refer to objects within a stack, you combine object descriptors using either of the prepositions of and in between an object descriptor and that of its enclosing object. Combined object descriptors proceed left to right from the smaller to the larger:

first field of last card of this background

This syntax lets you refer directly to any object within the current stack—you don't have to go to the card containing a particular field to get the field's contents or put something into it. For example, if the current card were the first in the stack, you could still execute the following command:

put the selection into field "undoHolder" of last card

You cannot refer to an object within another stack. You have to go to the stack before you can address its objects directly.

You can further combine field descriptors with chunk expressions, which are described in Chapter 7, "Expressions."

Referring to Menus and Menu Items

HyperCard menus and menu items have names and numbers, as well as ID numbers.

Menu and Menu Item Names

Menus and menu items all have names. The name of a menu or menu item is one of its properties. You assign a name for a menu when the menu is created with the create command. You assign a name to a menu item when you put the menu item into a menu with the put command.

Menu and menu item names can include any characters, including spaces. When you use a menu or menu item name in a statement, put quotation marks around the name to ensure that HyperCard recognizes it as a literal and doesn't look for a variable by that name, for example, menuItem "User Preferences". When you refer to menus by name, you must precede the menu name with the word menu, for example, menu "Notes". When you refer to existing menu items, you precede the name of the menu item with the word menuItem, for example, menuItem "Power Tools". You must also specify which menu the menu item is in, for example, menuItem "Power Tools" of menu "Utilities". You can use either of or in. There is an exception to these rules: you do not have to precede the name of a menu item with menuItem or specify the menu that a menu item is in when referring to a menu item in a doMenu statement:

doMenu "Power Tools"

Menu and Menu Item Numbers

Menus and menu items always have numbers by which you can refer to them. The menu number refers to the menu's position within the menu bar. Menus are ordered from left to right in the HyperCard menu bar. The menu item number refers to the menu item's position within its enclosing menu. Menu items are ordered from top to bottom.

You can get the name of a menu item by referring to it with its number. For example, typing the following statement into the Message box

```
menuItem 3 of menu "Utilities"
```

puts the name of the third menu item in the Utilities menu into the Message box.

You can also use ordinals when referring to menus and menu items. For example, typing the following statement into the Message box

```
the third menuItem in the fifth menu
```

puts the name of the third menu item in the fifth menu into the Message box.

You cannot get the number of a menu or menu item by referring to it by name. For example, the statement

```
the number of menuItem "Card Info..." of menu "Objects"
```

would result in an error dialog box.

The dashed line used in menus to visually separate menu items that have different functions is also counted as a menu item in the number of menu items. For example, if you have a menu with a dashed line separating the second and third menu choices, the dashed line is referred to as menuItem 3. You always refer to the dashed line by a menu item number because it has no name property. To put a dashed line in an existing menu, use the put command syntax as follows:

```
put "-" after menuItem itemName of menu menuName
```

To get a return-delimited list of all of the menus in the current HyperCard menu bar, use the function the menus. To get a return-delimited list of all the menu items in a menu, use the menu name, number, or ordinal: menu "Power Tools", menu 6, or the sixth menu.

To determine how many menus are in the current HyperCard menu bar, use the function number of menus. To determine how many menu items are in a specified menu, use the function number of menuItems in menu menuName. To determine the name of a menu or menu item, use the name property.

You can use menu commands, functions, and properties with the HyperCard built-in menus with the exceptions noted in the descriptions of the menu commands, functions, and properties.

The following statements use some of the menu commands and properties to create the simple example of a custom (user-defined) menu shown in Figure 5-5.

```
create menu "MyMenu"

put "Item 1" into menu "MyMenu"

put "-" after menuItem "Item 1" of menu "MyMenu"

put "Item 3" after the second menuItem of menu "MyMenu"

put "Item 4" after menuItem "Item 3" of menu "MyMenu"

put "-" after menuItem "Item 4" of menu "MyMenu"

put "Item 6" after the fifth menuItem of menu "MyMenu"


set the enabled of menuItem "Item 4" of menu "MyMenu" to false

-- or disable menuItem 4 of menu "MyMenu"

set the cmdChar of menuItem "Item 6" of menu "MyMenu" to "]"

set the checkMark of menuItem "Item 3" of menu "MyMenu" to true
```

Figure 5-5 A custom menu



Referring to Windows

In addition to referring to a window by name, you can refer to a window by ID number or by a number representing its place in the window layer.

Card windows are referred to as card window (for example, set the location of card window to 45,65). Card window always refers to the card window of the current stack. You can't use the card window syntax to refer to the card window of another stack unless you go to that stack first. You can, however, refer to another visible or hidden stack's window with the syntax window "stackName" (for example, set the location of window "Dizzie" to "45,65").

You refer to the Message Watcher window as Message Watcher (for example, show Message Watcher) or window "Message Watcher" (for example, set the loc of window "Message Watcher" to "65,80").

You refer to the Variable Watcher window as Variable Watcher (for example, set the loc of Variable Watcher to "64,124") or window "Variable Watcher" (for example, set the hBarLoc of window "Variable Watcher" to "65,80").

The Tools palette and Patterns palette are referred to in HyperTalk as tool window and pattern window, or window "tools" and window "patterns", respectively.

The Message box is referred to as message window or message box. Message can be abbreviated msg in any of these forms.

The Scroll window is referred to as scroll window or window "Scroll".

In addition to HyperCard's built-in windows, there are also external windows you create with the picture command. They are referred to by the name you give to the window at the time of its creation—for example,

set the rect of window "MyBestPicture" to "60,90,300,300"

You can also retrieve the ID of any window, including pictures and palettes. The unique IDs of picture windows could be particularly useful for referring to different windows that have two pictures with the same name.

In addition to its name and ID number, you can refer to a window by its number—that is, its position in the front-to-back order of windows. (Keep in mind that a window's number is a read-only property, and that this number changes as other windows are selected, opened, or closed.)

The windows function evaluates to a list of all the windows (listed by name in front-to-back order) that are currently available to HyperCard. The list could include the Message box, Scroll window, Message Watcher window, Variable Watcher window, FatBits window, Patterns palette, Tools palette, the windows of the Home stack and any currently open stacks, and any user-defined external windows.

Chapter Summary

Here is a summary of the material covered in this chapter:

- You refer to a HyperCard object using an object descriptor—its generic name and its specific designation.
- Cards, backgrounds, buttons, fields, and windows always have unique ID numbers that never change, always have object numbers that may change, and may optionally be given names.
- You can use special ordinals—middle, last, and any—to refer to objects by their position within their enclosing object.
- You can refer to the current card, background, or stack with this. You can refer to the card or background preceding the current one with previous, and to the one following the current one with next. You can refer to the card that was current prior to the current one with recent.
- The term me, in a script, refers to the object containing the script.
- The only unambiguous object descriptor for a stack is the word stack followed by the stack's filename within quotation marks.

- You can combine object descriptors to refer directly to any object in the current stack.
- Menus and menu items can be referred to by their name or number.
- Built-in HyperCard windows are referred to by names that are defined in the HyperTalk vocabulary. An external window you create with the picture command is referred to by the name you give it when you create it. Windows can also be referred to by the number of their position in the window layer or their unique ID numbers.

This chapter describes the elements of HyperTalk that contain values. **Values** are the information on which HyperTalk operates. A HyperTalk **expression** is a description of how to get a value.

The **sources of values** in HyperTalk are

- constants
- literals
- functions
- properties
- numbers
- containers

These sources of values are the most basic expressions.

HyperCard does not have data types: values are stored simply as strings of characters. (For mathematical operations, numbers are represented internally in a more efficient format; see the Standard Apple Numerics Environment description in this chapter.)

Constants

A **constant** is a named value that never changes. It's different from a variable in that you can't change it, and it's different from a literal in that its value is not always the string of characters making up the name. For example, the constant <code>empty</code> is the same as the null string (the literal " "), and the constant <code>space</code> is the same as the literal " ". All HyperTalk constants are described in Appendix B, "Constants."

Constants 99

Literals

A **literal** is a text string whose value is the string, exactly as it appears. Literals are denoted by double quotation marks at both ends of the string. (You must use the straight double quotation mark, not the printer's double quotation marks typed with the Option–left bracket and Option–Shift–left bracket keys.) Any character except double quotation mark, return, or "soft" return (generated by pressing Option-Return) can be part of a literal string. A literal can be of any length. For example, "This is a literal string" is a literal.

Unquoted literals are not supported

Do not use unquoted literals in HyperTalk. The value of an unquoted literal is the literal of itself—as though you had entered put "fred" into fred. Always put double quotation marks around a word you want HyperCard to take as a literal. •

Functions

A **function** is a named value that HyperCard calculates when the statement in which the function is used executes. The value of a function varies according to conditions of the system or according to the value of parameters you pass to the function when you use it.

For example, the built-in function named the time returns the current time in place of itself in a HyperTalk statement:

put the time into the message box

If the current time were 5:12 P.M., the above example would put 5:12 PM into the Message box.

You can also define your own functions in scripts using the function handler structure described in Chapter 9, "Control Structures and Keywords."

All built-in HyperTalk functions are described in Chapter 11, "Functions."

Properties

A **property** is a named value representing one of the defining characteristics of an element of the HyperCard environment. Different types of objects and other elements have different properties, according to their purpose. For example, fields share a set of properties, many of which are different from the set shared by buttons.

You get the value of most properties by using the property name as a function in a script or in the Message box. For example, the following statement retrieves the location property (two integers separated by a comma) of button 1, and it puts the value into the Message box:

```
put the location of button 1 into msg
```

This next example returns a value of either true or false for the enabled property of the menu Clues.

```
put the enabled of menu "Clues"
```

You can also change most properties with the set command. All HyperCard properties are described in Chapter 12, "Properties."

Numbers

A **number** in HyperCard is a character string consisting of any combination of the numerals 0 through 9, representing a decimal value. A number can include one period (.) representing the decimal point, but it can have no other punctuation nor a space character. A number can be preceded by a hyphen or minus sign to represent a negative value (HyperCard doesn't recognize a plus sign as part of a number). Numbers that consist only of numerals are integers. Numbers that include a period are real and, when used with mathematical operators, are manipulated with floating-point operations.

Properties 101

Standard Apple Numerics Environment

HyperCard performs mathematical operations with Standard Apple Numerics Environment (SANE) routines, but you don't have to worry about how to represent the values. You always enter numbers into HyperCard containers as numeric strings.

When performing a mathematical operation, HyperCard automatically converts the strings representing the numbers to SANE numeric values. If you put the result of the operation into a variable, it's stored as a SANE numeric value; if you put it into a field or the Message box, HyperCard automatically converts it back to a string with a precision of up to 19 decimal places. The same conversion takes place if you put the variable into a field or the Message box at a later time, or if you use it in a way that implies a string (character 2 of varName). So although SANE values are used internally for handling numbers with speed and precision, you can always think of HyperTalk numbers as strings.

Precision

The precision of the decimal string, resulting from putting a SANE numeric value into a field or the Message box, is controlled by the numberFormat global property (see Chapter 12, "Properties," for a detailed description). For example, the command

set numberFormat to 0.00

would result in a string with at least one digit to the left of the decimal point and exactly two digits to the right of the decimal point.

The numberFormat property does not affect the precision with which mathematical operations are executed, only the precision with which the results are displayed. When you put a number into a field or the Message box to display it, however, HyperCard converts it to a decimal string. So any extra precision it may have had (beyond the numberFormat specification in effect at the time) is lost.

Number Handling

The following example shows how number handling works. These three HyperTalk statements put the constant pi into a variable, set the numberFormat property, and put the value of the variable into the Message box, respectively:

```
put pi into joe
set numberFormat to 0.00
put joe into msg
```

The result shown in the Message box is 3.14159265358979323846. In this case, pi is entered into the variable joe as a string, and it remains a string, so numberFormat has no effect. If, however, you perform a mathematical operation on the variable, HyperCard converts it to a SANE numeric value:

```
put pi into joe -- joe contains a string add 0 to joe -- mathematical operation makes it a number set numberFormat to 0.00 -- affects the format of joe put joe into msg
```

The result shown in the Message box is 3.14. In this case, numberFormat takes effect when joe is converted from a SANE numeric value to a string as it's put into the Message box. The example statements for number handling work only when placed inside a handler. If entered one at a time in the Message box, the result is in the default format, because HyperCard resets numberFormat to its default value during idle time.

Containers

A **container** in HyperCard is a place where you can store a value. Containers include fields, buttons, variables, menus, the current selection, and the Message box. Containers other than fields and buttons can store values of any length, including zero length. Containers other than the Message box can have more than one line in them; each line ends with a return character (which can be the only character in the line).

Containers 103

Fields

A **field** is a HyperCard object for holding and displaying editable text. Fields are interesting objects because they are also containers—a field's value is the text string it contains. Fields can also act as expressions; for example, put field 1 into it puts the value of the expression field 1 into the variable it. Variables are described in the section "Variables" later in this chapter, and expressions are described in Chapter 7, "Expressions."

You can refer to fields directly by name, number, or ID number. (See Chapter 5, "Referring to Objects, Menus, and Windows," for more about how to refer to fields.)

Fields belong to cards or to backgrounds; the text held by a field, however, usually remains with the card (unless the sharedText property is true), even if the field belongs to the background. A field can contain up to 30,000 characters, including spaces, return characters, and other invisible characters. If you put more than that many characters into a field, the extras are ignored.

You can search through text with the find command unless the dontSearch property of the field is true. You can edit it using the I-beam pointer of the Browse tool when the field isn't locked.

About Paint text

You can also put text onto cards and backgrounds as **Paint text**—pictures that look like characters. Paint text can't be edited once it has been fixed onto the card or background (although you can paint over it or erase it as you can any part of a picture). See the *HyperCard Reference Guide* for more information on Paint text. •

Buttons

As mentioned in Chapter 2, "HyperTalk Basics," buttons are action objects or "hot spots" on the screen that can also contain text. Buttons, like fields, are objects that are also containers—a button's value is the text string it contains. Buttons can also act as expressions; for example,

put btn 6 into cd fld 1

puts the value of the expression btn 6 into the card field with the number 1.

Pop-up buttons contain text that they display as menu items. The following code fragment creates a new pop-up button whose menu items are the currently running programs:

```
doMenu "New Button"
set style of last button to popup
put the programs into last button
```

See the programs function in Chapter 11, "Functions," and the style property in Chapter 12, "Properties." Variables are described in the next section, and expressions are described in Chapter 7, "Expressions."

Variables

A **variable** is a named container that has no visible representation other than its name. Its value is a character string of any length. The variable name is a HyperTalk **identifier**. An identifier can be of any length, always begins with an alphabetic character, and can contain any alphanumeric character plus the underscore character (_).

You assign a value to a variable with the put command. You cannot read from a nonexistent variable—you must create it by putting something into it before you use it. The constant empty, the null string, counts as something you can put into a variable. This example puts a numeric value 12 into the variable fudge, adds 5 to that variable, and then puts the result, 17, into the Message box. Enter each line separately in the Message box.

```
put 12 into fudge
add 5 to fudge
put fudge into msg
```

HyperCard assumes that an unquoted word used in an expression is a variable when it can't interpret the word as some other source of value (the string is not a function, constant, property, or other container name). If you haven't put a value into a variable by that name, HyperCard treats it as an unquoted literal.

Containers 105

Scope of Variables

HyperCard has both local and global variables. A **local variable** is valid only during the current invocation of the currently executing handler. You don't need to declare a local variable before you use it—just put something into it. A **global variable** is valid for all handlers. You must declare a variable as global by using the global keyword in each handler before you use the variable:

global useMeEverywhere, useMeToo

HyperTalk assumes a variable to be local unless you specifically use the global keyword.

For more details on the global keyword, see Chapter 9, "Control Structures and Keywords."

Parameter Variables

You create parameter variables when you put their names after the message name in a handler:

on messageName firstParam, secondParam

When the handler is called, these variables are assigned the values, if any, of the items in a comma-separated list of expressions following the message name in the calling statement. Parameter variables are local to their handler. See Chapter 4, "Handling Messages," for an explanation of parameter passing.

The Variable It

The local variable named It is the destination of the commands get, ask, answer, read, and request. For example, get the name of field 1 puts the value of that background field's name into It. Convert puts its results into It if another destination isn't specified.

For information on these commands, see Chapter 10, "Commands."

Menus

When a menu reference does not refer to a menu as a HyperCard element (for example, get enabled of menu "Home"), then it behaves as a container. Like variables, you assign a value (made up of text) to a menu with the put command. The text becomes the menu's menu items. In this manner, a menu evaluates to a list of its menu items; the statement


```
put menu "Edit" into editMenuItems
```

stores a list of the menu items in the Edit menu in the variable editMenuItems.

The Selection

The **selection** is a container that holds the currently selected area of text. You can put values into, before, or after the selection or put the selection (or any chunk of the selection) into another container. Figure 6-1 shows an example that puts a string into the selection to replace the highlighted text.

Figure 6-1 Manipulating the selection



Containers 107

If the phrase I'm the selected text is selected, and your handler issues the statement

put the selection into the Message box

then I'm the selected text appears in the Message box. (Both instances of the word the in the example are optional.)

Found text isn't selected

Text found by the find command is indicated by a box around it—it is not placed into the selection. To get information about text found with the find command, use the functions foundText, foundChunk, foundLine, and foundField, which are described in Chapter 11, "Functions."

You must select some text with the mouse or the click, drag, or select command before you can manipulate the selection container.

You can also get information about a chunk of text or a line in a field that has been clicked with the clickChunk or clickLine function, described in Chapter 11, "Functions."

The Message Box

The **Message box** is a special container. Any HyperTalk expression can be put into the Message box. Typically, you use the Message box to send a HyperTalk message directly to an object or to HyperCard. The Message box is a single-line container, as shown in Figure 6-2. If you put more than one line from a multiple-line container into the Message box (put card field 2 into msg), only the first line is copied into the Message box.

Referring to the Message box

There are several forms you can use when referring to the Message box. The forms are message box, message, and msq. ◆

Figure 6-2 The Message box

```
go to stack "HyperCard wishList"
```

The Message box is the default destination for the put command. You can put a value directly into the Message box without specifying the Message box by using one of these forms of the put command:

```
put property [of element]
put container
put function
```

Property is an expression that yields any HyperCard property, *element* yields the descriptor of a HyperCard element (an object, menu, menu item, or window), *container* yields a container, and *function* yields any HyperCard function.

If you put something into the Message box when it's hidden, HyperCard shows it automatically. You can toggle the Message box between being hidden or shown by pressing Command-M.

The Message box can be specified by just the word message or its abbreviation msg. Optionally, you can follow either of those with either box or window, and you can precede either with the word the.

See the description of the put command in Chapter 10, "Commands," for more information about the values you can put into the Message box.

Chapter Summary

Here is a summary of the material covered in this chapter:

- The most basic expressions in HyperTalk are constants, literals, functions, properties, numbers, and containers.
- HyperTalk's values can always be treated as strings of characters.
- Containers—fields, variables, the selection, and the Message box—are places to store values.

This chapter describes the expressions you use to refer to values. An **expression** is a description of how to get a value. It may be as simple as a single source of a value, or it can be a complex expression built with operators.

This chapter also describes HyperTalk's **operators**, the elements of the language that you use in expressions to manipulate and calculate values, described in Chapter 6, "Values."

Complex Expressions

You can build complex expressions using values and operators. As a complex expression is evaluated, the values of its basic components are manipulated to derive a final value in place of the entire expression. (The original values are not changed in the process.) Complex expressions are evaluated according to rules of precedence, and restrictions apply to the values that can be used, depending on their operators.

Chunk expressions are different

Chunk expressions are a different type of expression: they designate pieces of the strings representing values. Chunk expressions are described later in this chapter. ◆

Factors

A **factor** is a single element of value in an expression. The following constructs are factors:

- a simple source of value
- an expression enclosed in parentheses

- an element with a minus sign in front of it that evaluates to a number
- an expression with the word not in front of it that evaluates to true or false

An expression can be a single source of value, or it can be any two expressions with an operator between them.

The difference between a factor and an expression is important to the syntax of HyperTalk commands and functions. Where a built-in HyperTalk command parameter permits an expression, you can specify as complex an expression as you wish. HyperCard derives the final value before passing the parameter to the command. For example, the add command accepts a complex expression as its first parameter:

```
add 46+12*monthlyRate to total
```

In contrast, when a built-in HyperTalk function requires a factor, HyperCard takes the value of the first factor as the parameter to pass to the function. For example, the sqrt function takes the first factor following its name as its parameter. This is illustrated by the following expression, which you can type into the Message box or use in a statement:

```
the sqrt of 4+12
```

In the example, the sqrt function takes the factor 4 as its parameter, rather than the value of the expression 4+12. So the entire expression evaluates to 14, rather than 4, which would be the value if sqrt accepted an entire expression. (To specify the entire expression 4+12 as the parameter, you can enclose it in parentheses, which turns it into a single factor.)

Two hyphens always indicate a comment

You can put a hyphen in front of a factor to create another factor, and you can put another hyphen in front of that and still have a factor. However, two hyphens in sequence indicate a comment, so you must separate the hyphens with a space or enclose the inner factor in parentheses for HyperCard to recognize the construct as a factor. •

HyperTalk's built-in commands and functions are described in Chapters 10 and 11, respectively.

HyperTalk Operators

Operators are used in complex expressions to derive values from other values. Operators fall into several categories:

- Arithmetic operators work on numbers and result in numbers.
- Comparison operators work on numbers, text, and Boolean values (true or false) and result in Boolean values.
- Logical operators work on Boolean values and result in Boolean values.
- Text operators manipulate text strings and result in text strings.

Table 7-1 is a list of all the operators in HyperTalk.

Table 7-1 HyperTalk operators

Operator	Description	
&	Concatenate: Text string operator that joins the text string yielded by the expression on its left to the text string yielded by the expression on its right.	
&&	Concatenate with space: Text string operator that joins the text string yielded by the expression on its left to the text string yielded by the expression on its right, with a space between them.	
/	Divide: Arithmetic operator that divides the number to its left by the number to its right.	
=	Equal: Comparison operator that results in true if the expression to its left and the expression to its right have the same value. The expressions can be arithmetic, text string, or logical.	
^	Exponent: Arithmetic operator that raises the number to its left to the power of the number to its right.	
>	Greater than: Comparison operator that results in true if the expression to its left has greater value than the one to its right. The expressions can be both arithmetic or both text.	

continued

 Table 7-1
 HyperTalk operators (continued)

Operator	Description
≥	Greater than or equal to: Same as $>=$. The \geq character is obtained on the Macintosh keyboard by pressing Option-period (.).
>=	Greater than or equal to: Same as ≥. Comparison operator that results in true if the expression to its left has greater value than the one to its right or the same value. The expressions can be both arithmetic or both text.
()	Grouping: Expressions within the innermost pair of parentheses are evaluated first. Parentheses don't force a new level of evaluation; they change the sequence in which the current level of evaluation proceeds.
<	Less than: Comparison operator that results in true if the expression to its left has less value than the one to its right. The expressions can be both arithmetic or both text.
≤	Less than or equal to: Same as \leq . The \leq character is obtained on the Macintosh keyboard by pressing Option-comma (,).
<=	Less than or equal to: Same as \leq . Comparison operator that results in true if the expression to its left has less value than the one to its right or the same value. The expressions can be both arithmetic or both text.
_	Minus: Arithmetic operator that makes negative the number to its right or, if it is between two numbers, subtracts the one on the right from the one on the left.
*	Multiply: Arithmetic operator that multiplies two numbers it appears between.
≠	Not equal: Same as <>. The ≠ character is obtained on the Macintosh keyboard by pressing Option–equal sign (=).

continued

 Table 7-1
 HyperTalk operators (continued)

Operator	Description
<>	Not equal: Comparison operator that results in true if the expression to its left and the expression to its right have different values. The expressions can be arithmetic, text, or logical.
+	Plus: Arithmetic operator that adds two numbers it appears between.
and	AND: Logical operator that results in true if both the expression to its left and the expression to its right are true.
contains	Contains: Comparison operator that results in true if the text string yielded by the expression on its right is found in the text string yielded by the expression on its left.
div	Divide and truncate: Arithmetic operator that divides a number to its left by a number to its right, ignoring any remainder, resulting in just the whole part.
is	Is: Same as =.
is a or is an	Is a, is an: Comparison operator that tests for types. Types include number, integer, point, rect, date, empty, and logical.
is in	Is in: Converse of contains; comparison operator that results in true if the text string yielded by the expression on its left is found in the text string yielded by the expression on its right.
is not	Is not: Same as <>.
is not a or is not an	Is not a, is not an: Comparison operator that tests for types. Types include number, integer, point, rect, date, and logical.
is not in	Is not in: Opposite of is in; comparison operator that results in true if the text string yielded by the expression on its left is not found in the text string yielded by the expression on its right.

continued

 Table 7-1
 HyperTalk operators (continued)

Operator	Description
is within	Is within: The is within operator tests whether or not a point lies inside a rectangle; it results in a Boolean value: true or false.
mod	Modulo: Arithmetic operator that divides the number to its left by the number to its right, ignoring the whole part, resulting in just the remainder.
not	NOT: Logical operator that results in true if the expression on its right is false, and false if the expression on its right is true.
or	OR: Logical operator that results in true if either the expression to its left or the expression to its right is true.
there is a or there is an	There is a, there is an: Unary operator that results in true if the item exists. Items include the descriptor of a window, menu, menu item, file, button, field, card, card picture, background, background picture, part, stack, folder, document, file, or program.
	You can use this operator to check for any currently executing System 7–friendly program. The expression
	there is a program programName
	returns true if the program is both System 7–friendly and currently executing. When searching for an application or document, this operator uses the search paths stored in the Home stack. When searching for a file, it does not use the search paths.
there is not a	There is not a, there is not an: Opposite of there is
or there is not an	a; unary operator that results in true if the specified item does not exist. Items include the descriptor of a window, menu, menu item, file, button, field, card, card picture, background, background picture, part, stack, folder, document, file, scripting language, or program. When searching for an application or document, this operator uses the search paths stored in the Home stack. When searching for a file, it does not use the search paths.

Operator Precedence

Parentheses alter the order of expression evaluation. Different operators have different orders of precedence that determine how things get evaluated. The order in which HyperCard performs operations is shown in Table 7-2.

Table 7-2 Operator precedence

Order	Operators	Type of operator
1	()	Grouping
2	-	Minus sign for numbers
	not	Logical negation for Boolean values
	there is a	Boolean test for HyperCard items
	there is an	Boolean test for HyperCard items
	there is not a	Boolean test for HyperCard items
	there is not an	Boolean test for HyperCard items
	within	Boolean test for point within rectangle
3	٨	Exponentiation for numbers
4	*/div mod	Multiplication and division for numbers
5	+ -	Addition and subtraction for numbers
6	& &&	Concatenation of text
7	> < <= >= ≤ ≥	Comparison for numbers or text
	is in contains	Comparison for text
	is not in	Comparison for text
	is a	Comparison for types
	is an	Comparison for types
	is not a	Comparison for types
	is not an	Comparison for types
8	= is is not <> ≠	Comparison for numbers or text
9	and	Logical for Boolean values
10	or	Logical for Boolean values

Operators of equal precedence are evaluated left to right, except for exponentiation, which goes right to left. For example, 2^3^4 means "3 raised to the fourth power, then 2 raised to that power," whereas 1-2-3 means "2 subtracted from 1, then 3 subtracted from that." If you use parentheses, HyperCard evaluates the parenthetical expression first.

Operators and Expression Type

The operator you use must match the values you're using it with: "tom" + "cat" would cause an error, because numeric values are required for addition. However, tom + cat would be acceptable if tom and cat were names of containers with numbers in them, and "tom" & "cat" would be acceptable because the & operator works on text strings (the result of this operation would be the text string tomcat). Text operators work on any value, because any value in HyperTalk can be treated as a text string; they always yield text strings.

Because numeric values are automatically converted to strings when necessary (see "Numbers" in Chapter 6, "Values"), they can be manipulated by both text operators and arithmetic operators. For example, 5 & 78 yields 578, and 5 + 78 yields 83.

Comparison operators try to treat both of their operands as numbers; if they can't both be regarded as numbers, HyperCard treats them as text and does a lexical comparison. A lexical comparison uses the order of the ASCII table (see Appendix D, "Extended ASCII Table"). For letters, it's the same as alphabetical order; for numerals, it's 0–9, but it's different from a numerical comparison because a lexical comparison looks at just one character at a time, rather than the number as a whole. For example, 9 < 10 results in true, because 9 is less than 10 arithmetically. But "9x" < "10x" results in false, because the operands are evaluated lexically and 9 is greater than 1.

Chunk Expressions

You use a chunk expression to specify a particular piece—a **chunk**—of the value of any source of value: constant, literal, function, property, number, or container. Chunk expressions can specify any character, word, item, or line in the source.

Syntax of Chunk Expressions

The form of a chunk expression designates the smallest part of the chunk first, then specifies each larger, enclosing part. You separate each part of the expression with the preposition of or its synonym in. For example, the expression

first character of second word of third line of field 1

specifies a single character in the field.

You modify the specification of the kind of chunk—character, word, item, or line—with the number of the particular one you want. The number can be an ordinal constant preceding the kind (tenth word) or an integer following the kind (line 2). You can also use a numeric constant in place of the integer (line two), or any numeric expression that resolves to an integer.

You can use the special ordinals middle, last, and any to specify a chunk within its enclosing part. HyperCard resolves a special ordinal to a number using the total number of chunks of the specified type within its enclosing part: middle resolves to one more than half the total (rounded down to the nearest integer), last resolves to the total, and any resolves to a random number between 1 and the total. For example,

```
put "Joe" into any word of line 2 of field 1
```

replaces a random word in the line with Joe.

It isn't necessary to specify the enclosing parts of the source in strict hierarchical order. You can designate any smaller part within any larger part:

```
character 35 of field 1
```

And, although you must go left-to-right from smaller to larger, you don't have to specify any smaller part than you want:

```
third item of It
```

Characters

Characters are designated by the chunk name character (or char). Spaces count as characters in any part of a source except words. (Words are delimited by spaces.) Commas count as characters except in items. (Items are delimited by commas.) Return characters count as characters in whole sources and items. (A return character delimits the last word on the line as well as the line itself.)

For example, if field 6 contains the phrase

```
It was the turtle, not I, who spilled the beans. the chunk expression character 25 of field 6 yields a comma (the one after not I).
```

Words

Words are composed of any characters, including punctuation, delimited by spaces and return characters, and are designated by the chunk name word:

```
word 2 of "Where's my cubicle?" yields my.
```

Items

Items are composed of any characters, including punctuation, delimited by commas, and are designated by the chunk name item:

```
item three of "cat's, rat's, bat's, gnat's"
yields " bat's" (including the space character in front).
```

Lines

Lines are composed of any characters, including punctuation, delimited by return characters, and are designated by the chunk name line.

The chunk name line denotes text between the beginning of a container and the first return character, between two return characters, or between the last return character and the end of the container.

It doesn't matter how many display lines it takes to display one container line. For example, a single line in a field might occupy several lines on the display if the text wraps around (which it does if the field isn't wide enough to accommodate the whole line). Figure 7-1 shows two examples of lines in a field: one with text wrap, and one without text wrap.

Figure 7-1 Lines in a field

This is line one in the field.	This is line one in the field. This is line two.
This is line two. And here's line three.	And here's line three.

Ranges

The preposition to in a chunk expression specifies a range of a chunk within the larger chunk:

```
word 1 to 5 of line 2 of field "fred"
```

The numbers given in a range are inclusive. For example:

```
char 2 to 5 of "Hedgehog" yields edge.
```

You specify the range with integers (or with constants or numeric expressions that resolve to integers) following the chunk name, rather than with ordinal numbers preceding the chunk name. That is, you must say char 1 to 3 of "george"; you can't say first to third char of "george".

When the first number in a character range is greater than the second, you get an empty string. For example, char 5 to 3 of "Motorcycle" yields "" or empty. For words, items, and lines, a "reversed" range evaluates to the first chunk of the range. For example, word 2 to 1 of "Motorcycle helmet" yields "helmet".

Figure 7-2 shows some chunk expressions, labeled in various valid forms of chunk expression syntax, in a hypothetical card field 1.

Third word This is one line. of line 1 of Character 2 card field 1 And here is another line of word 4 of Char 4 to 6 line 2 of s entire sentence is of line 3 of card field 1 card field 1 actually one line (line 3) Tenth word of that has wrapped around third line of card field 1 in the field Here's a line with items Item 2 of that are, you know fourth line of card field 1 separated by commas

Figure 7-2 Chunk expressions

Chunks and Containers


Combining a chunk expression with the object descriptor of a field lets you refer directly to any piece of text down to a single character within the current stack:

put char 2 of line 2 of field 1 of last card

Figure 7-3 shows an example that refers to the single character "a".

Figure 7-3 Combining chunks and objects

Third character of second word of third line of first field of fourth card.



You can't specify chunks in another stack

You can't combine a stack name with a chunk expression; you must go to the stack first. ◆

Chunks as Destinations as Well as Sources

Chunk expressions can be used to specify a part of the value in a container wherever a container name is used. So, the chunk can specify the destination of a value—where you're putting it—as well as the source of a value—where you're getting it. For example,

```
put "Mr Steve" into word 3 of field 1
```

replaces only the third word in the field with the value Mr Steve, leaving the rest of the field's former contents intact.

Nonexistent Chunks

If you specify chunks that don't exist as sources of values, you get nothing. For example,

```
put char 5 of "hey" into msg
```

puts empty (or nothing) into the Message box, because the word *hey* contains only three characters.

If you specify a nonexistent chunk as the destination of a put command, the outcome depends on the kind of chunk. If you put a value into a character or a word that doesn't exist in a container, you put just the value. That is, if field 1 is empty, the statement

```
put "hey" into word 5 of field 1
```

puts hey (with no characters before it) into background field 1.

If you put a value into a nonexistent line, however, HyperCard puts in a return character, and if you put a value into a nonexistent item, HyperCard puts in a comma. (In both cases, you put a null chunk delimited by its particular delimiting character.) For example, if field 1 is empty, the statement

```
put "hey" into line 5 of field 1
```

puts four return characters (four null lines) followed by hey into background field 1. Similarly,

```
put "hey" into item 5 of field 2
```

puts four commas (four null items) followed by hey into the first line of background field 2.

Chapter Summary

Here is a summary of the material covered in this chapter:

- Complex expressions are built with values and operators.
- Operators are used to manipulate and calculate values.
- Chunk expressions can specify any chunk—character, word, item, or line—either in a source of value or as the destination of a put command.

This chapter describes the messages HyperCard sends in response to events, such as mouse clicks or Apple event commands, that you or an external process initiate in its environment.

Most system messages are sent by HyperCard to the current card, but those having to do with a specific button or field are sent to that object. The receiving object has the first chance to respond to the message before it goes on to the next encompassing object, as described in Chapter 4, "Handling Messages." The receiving object can respond to the system message with a handler that begins

on messageName

where *messageName* is one of the system messages in the lists in this chapter.

Messages and Commands

Most system messages are informational—they cause no action if passed all the way to HyperCard, although they may be a result of a HyperTalk command executing. For example, HyperCard sends deleteButton to a button while it is executing either a Cut Button or Clear Button menu command. The deleteButton message is a result of a command, not the command itself. Consequently, you can't prevent the deletion of buttons by intercepting the deleteButton message with a handler named deleteButton. All system messages that are a result of a command can be intercepted, but the intercepting handler will have no effect on the action of the command that sends that message.

Other system messages, however, are commands if passed to HyperCard. For example, all menu commands are passed to HyperCard as parameters of the doMenu message. (So you can prevent deletion of buttons by intercepting doMenu. But see the section "Redefining Commands" at the beginning of Chapter 10 before trying it.) All system messages that are HyperTalk commands are noted as such in this chapter and are also listed in Chapter 10, "Commands." If a message that reaches HyperCard is neither a system message nor a command, HyperCard displays a "Can't understand" error dialog box.

Although system messages are usually sent by HyperCard, they can be sent by other objects as well. For example, a handler could invoke a mouseUp handler in another object by executing a statement such as

```
send "mouseUp" to button 1 of card 1
```

The tables in this chapter correspond to the type of object to which the listed system messages are sent initially. If that object has no handler with a name matching the system message, it passes the message on to succeeding objects in the hierarchy. So, for example, a card can have a handler for a message sent initially to a button.

Messages Sent to a Button

The only messages that are sent initially to buttons are those having to do with a specific button. They are of two types: those announcing the button's creation or deletion, and mouse messages.

All of the mouse messages that can be sent to buttons can also be sent to fields. When buttons and fields are layered on top of each other, mouse messages are sent only to the closest one. Background buttons and fields can never overlay those belonging to the card. Both background buttons and card buttons precede the card in the message-passing hierarchy even though the background itself comes after the card.

Table 8-1 shows the system messages HyperCard sends initially to buttons.

 Table 8-1
 Messages sent to a button

Message	Meaning	
deleteButton	Sent to a button that is being deleted just before it disappears.	
mouseDoubleClick	Sent to a button after a second mouse click is released when all of the following occur:	
	■ The second click is within the double-click time interval set in the Mouse control panel.	
	■ The second click is at a location within 4 pixels of the first click.	
	■ The second click is within the same object as the first.	
	When the mouseDoubleClick message is sent, it's the only system message sent as a result of the second click.	
	If someone clicks repeatedly, faster than the double- click speed, each odd-numbered click is treated as a first click and each even-numbered click is treated as a second click.	
mouseDown	Sent to a button when the mouse button is pressed down while the pointer is inside its rectangle. (This message may also be sent to a field or card; see Table 8-2 and Table 8-3.)	
mouseEnter	Sent to a button as soon as the pointer is moved within its rectangle. (This message may also be sent to a field; see Table 8-2.)	
mouseLeave	Sent to a button as soon as the pointer is moved outside its rectangle. (This message may also be sent to a field; see Table 8-2.)	
mouseStillDown	Sent to a button repeatedly while the mouse button is held down and the pointer is inside its rectangle. (This message may also be sent to a field or card; see Table 8-2 and Table 8-3.)	

Table 8-1 Messages sent to a button (continued)

Message	Meaning	
mouseUp	Sent to a button when the mouse button is released while the pointer is inside its rectangle. The pointer must be in the same button rectangle it was in when the mouse button was pressed down for the message to be sent. (This message may also be sent to a field or card; see Table 8-2 and Table 8-3.)	
mouseWithin	Sent to a button repeatedly while the pointer is inside its rectangle. (This message may also be sent to a field; see Table 8-2.)	
newButton	Sent to a button as soon as it has been created; because a button can have no script with which to respond to this message (unless it was created by pasting), the message passes to objects lower in the hierarchy that can respond with handlers such as	
	on newButton set autoHilite of the target to true end newButton	

Messages Sent to a Field

The only messages that are sent initially to fields are those having to do with a specific field. They are of three types: those announcing the field's creation or deletion, those announcing its opening for text entry or closing afterward, and mouse messages.

All of the mouse messages that can be sent to fields can also be sent to buttons. When buttons and fields are layered on top of each other, mouse messages are sent only to the closest one. Background buttons and fields can never overlay those belonging to the card. Both background fields and card fields precede the card in the message-passing hierarchy even though the background itself comes after the card.

Table 8-2 shows the system messages HyperCard sends initially to fields.

Table 8-2Messages sent to a field

Message	Meaning	
closeField	Sent to an unlocked field when it is closed after text editing by clicking outside the field, moving the text insertion point to the next field with the Tab key, pressing the Enter key, clicking a button, going to another card, or quitting HyperCard. The message is not sent unless some text was actually changed.	
deleteField	Sent to a field that is being deleted just before it disappears.	
enterInField	Sent to a field when the Enter key is pressed while there is an insertion point or selection in the field. If enterInField is not intercepted by a handler and the contents of the field have been changed, HyperCard sends the closeField message.	
exitField	Sent to an unlocked field when it is closed without having its text changed.	
mouseDoubleClick	Sent to a locked field after a second mouse click is released when all of the following occur:	
	■ The second click is within the double-click time interval set in the Mouse control panel.	
	■ The second click is at a location within 4 pixels of the first click.	
	■ The second click is within the same object as the first.	
	When the mouseDoubleClick message is sent, it's the only system message sent as a result of the second click.	
	If someone clicks repeatedly, faster than the double- click speed, each odd-numbered click is treated as a first click and each even-numbered click is treated as a second click.	
	and in the	

 Table 8-2
 Messages sent to a field (continued)

Message	Meaning	
mouseDown	Sent to a locked field when the mouse button is pressed down while the pointer is inside it. MouseDown is not sent to a scrolling field when the mouse is clicked while the pointer is in the scroll bar. You can send mouseDown to an unlocked field by holding down the Command key while clicking the mouse in the field. (This message may also be sent to a button or card; see Table 8-1 and Table 8-3.)	
mouseEnter	Sent to a field as soon as the pointer is moved into it. (This message may also be sent to a button; see Table 8-1.)	
mouseLeave	Sent to a field as soon as the pointer is moved outside it. (This message may also be sent to a button; see Table 8-1.)	
mouseStillDown	Sent to a locked field repeatedly while the mouse button is held down and the pointer is inside it. (This message may also be sent to a button or card; see Table 8-1 and Table 8-3.)	
mouseUp	Sent to a locked field when the mouse button is released while the pointer is inside it. The pointer must be in the same field it was in when the mouse button was pressed down for the message to be sent. (This message may also be sent to a button or card; see Table 8-1 and Table 8-3.)	
mouseWithin	Sent to a field repeatedly while the pointer is inside it. (This message may also be sent to a button; see Table 8-1.)	
newField	Sent to a field as soon as it has been created.	
openField	Sent to an unlocked field when it is opened for text editing by clicking the field or moving the text insertion point from the previous field with the Tab key.	

Table 8-2 Messages sent to a field (continued)

Message Meaning returnInField Sent to a field when the Return key is pressed while there is an insertion point or selection in the field. In response to a returnInField message, HyperCard sends a tabkey message to the field if the following conditions are true: ■ The field's autoTab property (described in Chapter 12, "Properties") is true. ■ The ReturnInField message is not intercepted by a handler. ■ The field is not a scrolling field. ■ The insertion point or selection is on the last line. Otherwise, HyperCard inserts a return character into the field. The tabKey message, if it's not intercepted, causes HyperCard to place the insertion point in the next field. tabKey Sent to a field when the Tab key is pressed while the text insertion point is in the field. (This message may also be sent to the current card; see Table 8-3.)

Messages Sent to the Current Card

System messages not sent to buttons or fields are sent initially to the current card, even when they concern the background or the stack.

Mouse messages are sent to the card only when there is no button or field, belonging to either the card or the background, under the pointer.

Table 8-3 shows the system messages HyperCard sends initially to the current card.

Table 8-3 Messages sent to the current card

Message

Meaning

appleEvent class,
id, sender

Sent to the current card when an Apple event is received.

In an appleEvent message, *class* is the general category of the event (aevt, misc), *id* is the actual event received (oapp, odoc, pdoc, clos, quit, dosc, eval), and *sender* is the name of the application or process that sent the event.

Since Apple event commands are usually generated by other processes, you may want to check to make sure that they are not destructive. You can intercept an appleEvent message with an Apple event handler like this one written for the Home stack:

```
on appleEvent class,id,sender
answer "Apple Event Alert!" & return & ¬
"The class is" && class & return & ¬
"The ID is" && id & return & ¬
"The Sender is" && sender ¬
with "Pass" or "Kill"
if It is "pass" then pass appleEvent
end appleEvent
```

If you pass the event on at the end of your handler to HyperCard using the pass keyword, HyperCard executes the event; otherwise, the event is not executed.

arrowKey var

Sent to the current card when an arrow key is pressed (see also the textArrows property in Chapter 12, "Properties"). The value passed into the parameter variable *var* can be left, right, up, or down, depending on which arrow key is pressed. The beginning of a handler for this message could read

```
on arrowKey whichKey
  if whichKey = "left" then go previous card
...
```

(This message is also a HyperTalk command; see Chapter 10, "Commands.")

close

Sent to the current card, just before leaving that card, when you close a stack window with the close window command and when you click the close box of a card window.

 Table 8-3
 Messages sent to the current card (continued)

Message	Meaning	
closeBackground	Sent to the current card, just before leaving that card, when a background is closed by going to another card that has a different background.	
closeCard	Sent to the current card just before leaving that card.	
closePalette paletteWindowName , paletteWindowID	Sent to the current card when a palette that was opened with the palette command is closed.	
closePicture pictureWindowName , pictureWindowID	Sent to the current card when a window that was created with the picture command is closed.	
closeStack	Sent to the current card, just before leaving that card, when a stack is closed by opening another stack.	
commandKeyDown var	Sent to the current card when a combination of the Command key and another key is pressed. The parameter variable <i>var</i> can be any character on the keyboard. The beginning of a handler for this message could read	
	on commandKeyDown whichKey if whichKey = j then doMenu "MyMenu" more statements	
controlKey var	Sent to the current card when a combination of the Control key and another key is pressed. The possible values of the parameter value <i>var</i> and the keys each value corresponds to are shown in Appendix D, "Extended ASCII Table." (See also the controlkey command in Chapter 10, "Commands.") The beginning of a handler for this message could read	
	<pre>on controlKey whichKey if whichKey = 16 then doMenu "Print Card" additional statements</pre>	
deleteBackground	Sent to the current card when a background is deleted just before it disappears.	
deleteCard	Sent to a card that is being deleted just before it disappears.	
	continued	

 Table 8-3
 Messages sent to the current card (continued)

Message	Meaning			
deleteStack	Sent to the current card when a stack is deleted just before it disappears.			
doMenu <i>var1</i> , <i>var2</i>	Sent to the current card when a menu item is selected. The parameter variable <i>var1</i> has the exact name of the menu item selected, including the three periods following menu items that invoke dialog boxes. Uppercase and lowercase don't matter, but you must type the three periods—don't use the Option-semicolon ellipsis character. The second parameter variable, <i>var2</i> , has the exact name of the menu in the menu bar. (This message is also a HyperTalk command, which is listed in Chapter 10, "Commands." An example handler to intercept the doMenu message is shown in the section "Redefining Commands," at the beginning of Chapter 10.)			
enterKey	Sent to the current card when the Enter key is pressed unless the text insertion point is in a field. (This message is also a HyperTalk command; see Chapter 10.)			
functionKey var	Sent to the current card when a function key on the Apple Extended Keyboard is pressed. The parameter variable <i>var</i> can range from 1 to 15. Function keys 1 through 4 are preprogrammed for the Undo, Cut, Copy, and Paste commands, respectively. The beginning of a handler for this message could read			
	on functionKey whichKey if whichKey < 5 then pass functionKey else if whichKey is 5 then doMenu "New Card" else if whichKey is 6 then choose browse tool else if whichKey is 7 then choose button tool			
	You can override the preprogrammed functions of keys 1 through 4 in a functionKey message handler. (This message is also a HyperTalk command; see Chapter 10, "Commands.")			
help	Sent to the current card, just before leaving that card, when Help is chosen from the Go menu (or Command-? is pressed). You can intercept this message if you want to provide your own Help system for your stack. (This message is also a HyperTalk command; see Chapter 10, "Commands.")			

Table 8-3 Messages sent to the current card (continued)

Message Meaning hide menubar Sent to the current card when the menu bar is visible and you press Command–Space bar. (Hide is also a HyperTalk command; the command accepts other parameter variable values besides menubar; see its description in Chapter 10, "Commands.") idle Sent to the current card repeatedly when nothing else is happening and the Browse tool is current. An idle handler can interfere with typing. For example, if you have an idle handler that puts text into a field, it can remove the insertion point from another field while the user is typing. Here is an example of such a handler: on idle put the time into card field "Time" pass idle end idle If this on idle handler were to execute during typing into another field (idle is sent during a typing pause), and if the time had changed, HyperCard would remove the insertion point from the user's field. The user would have to click the field or press the Tab key to replace the insertion point after every pause, which would be annoying and tedious. keyDown var Sent to the current card when a key is pressed. The parameter variable var can be any character on the keyboard. The beginning of a handler for this message could read on keyDown whichKey if whichKey = t then put "That's the key" -- more stuff... The keyDown message is not sent for keys that generate special messages or for programmed function keys. A programmed function key would send a functionKey message and any additional messages that the specified function key is programmed to generate. See also the functionKey message

continued

description.

 Table 8-3
 Messages sent to the current card (continued)

Message	Meaning		
mouseDoubleClick	Sent to a card, after a second mouse click is released, when all of the following occur:		
	■ The second click is within the double-click time interval set in the Mouse control panel.		
	■ The second click is at a location within 4 pixels of the first click.		
	 The second click is within the same object as the first. 		
	When the mouseDoubleClick message is sent, it's the only system message sent as a result of the second click.		
	If someone clicks repeatedly, faster than the double-click speed, each odd-numbered click is treated as a first click and each even-numbered click is treated as a second click.		
mouseDown	Sent to the current card when the mouse button is pressed dow and the pointer is not in a button rectangle or field. (This messa may also be sent to a button or field; see Table 8-1 and Table 8-2		
mouseDownInPicture pictureWindowName, point	Sent to the current card when the mouse button is held down while the pointer is in a window created with the picture command. See also the picture command in Chapter 10, "Commands."		
mouseStillDown	Sent to the current card repeatedly while the mouse button is held down. (This message may also be sent to a button or field; see Table 8-1 and Table 8-2.)		
mouseUp	Sent to the current card when the mouse button is released. (This message may also be sent to a button or field; see Table 8-1 and Table 8-2.)		
mouseUpInPicture pictureWindowName, point	Sent to the current card when the mouse button is released after being down while the pointer is in a window created with the picture command. See also the picture command in Chapter 10, "Commands."		
moveWindow	Sent when you change a card window's location property with HyperTalk, drag or zoom the card window, or change the location of the card window with the show command. See also the location and rectangle properties in Chapter 12, "Properties," and the show command in Chapter 10, "Commands."		

 Table 8-3
 Messages sent to the current card (continued)

Message	Meaning	
newBackground	Sent to the current card as soon as a background has been created.	
newCard	Sent to a card as soon as it has been created.	
newStack	Sent to the current card when a stack is created.	
openBackground	Sent to the current card when a background is first opened by going to a card whose background is different than that of the previous card.	
openCard	Sent to a card when you go to it.	
openPalette paletteWindowName , paletteWindowID	Sent to the current card when a palette is opened with the palette command.	
openPicture pictureWindowName , pictureWindowID	Sent to the current card when a window is created with the picture command.	
openStack	Sent to the current card when a stack is opened by going to a card in a different stack than that of the previous card. In this case the following three messages are sent, in order: openCard, openBackground, and openStack.	
quit	Sent to the current card when you choose Quit HyperCard from the File menu (or press Command-Q) just before HyperCard quits.	
resume	Sent to the current card when HyperCard resumes running after having been suspended.	
resumeStack	Sent to the current card when you return to an already open stack.	
returnKey	Sent to the current card when the Return key is pressed unless the text insertion point is in a field. (This message is also a HyperTalk command; see Chapter 10, "Commands.")	
show menubar	Sent to the current card when the menu bar is hidden and you press Command–Space bar. (Show is also a HyperTalk command; the command accepts other parameter variable values besides menubar; see the description in Chapter 10, "Commands.")	

Table 8-3 Messages sent to the current card (continued)

Message	Meaning		
sizeWindow	Sent to the current card when the card window is resized, such as in the following cases:		
	■ The window is resized from the size box or scroll palette.		
	■ The window is zoomed in or out, thereby changing the window size.		
	 A script sets the one of the rectangle properties (height, width, and so on) of the card window to a new rectangle. 		
	■ A script sets the rect of the card to a new rectangle and the resizing of the card causes resizing of the card window.		
	In all cases except the first, a moveWindow message also may be sent. When both messages are pending, sizeWindow is sent first.		
suspend	Sent to the current card when HyperCard is suspended by launching another application with the open command just before the other application is launched.		
suspendStack	Sent to the current card, just before leaving that card, when you switch to another stack.		
startUp	Sent to the first card displayed when HyperCard is first started.		
tabKey	Sent to the current card when the Tab key is pressed unless the text insertion point is in a field. In that case, tabKey is sent initially to the field; see Table 8-2. (This message is also a HyperTalk command; see Chapter 10, "Commands.")		

Message Order

For some events, HyperCard sends a sequence of system messages. The messages are sent in a specific message order. You can create message handlers that use the message sending order to set properties or perform other actions when opening stacks, creating new backgrounds, creating new cards, deleting cards, backgrounds, or stacks, moving from card to card, and moving from

stack to stack. For example, the startUp system message is always sent when HyperCard first starts up and the first stack is opened, so you can create a handler for the startUp system message that sets properties for the first card before it appears.

You can create handlers for any message that is sent earlier in the message sending order to change the actions that take place before the messages that follow it are acted upon by HyperCard. The HyperCard message sending order that results from some of the actions most frequently performed when creating or modifying stacks is shown in Table 8-4. You can also open the Message Watcher to watch the messages that result from other actions.

Table 8-4 HyperCard message sending order

Action	Resulting message order
Create a new background	<pre>closeCard, closeBackground, newBackground, newCard, openBackground, openCard</pre>
Create a new card	closeCard, newCard, openCard
Create a new stack	<pre>closeCard, closeBackground, closeStack, newStack, newBackground, newCard, openStack, openBackground, openCard</pre>
Cut a card	<pre>closeCard, closeBackground, deleteCard, deleteBackground, openBackground, openCard</pre>
Delete a background	closeCard, closeBackground, deleteCard, deleteBackground
Delete a card	closeCard, closeBackground, deleteCard, deleteBackground, openBackground, openCard
Delete a stack	closeCard, closeBackground, closeStack, deleteStack
Paste a card	<pre>closeCard, closeBackground, newBackground, newCard, openBackground, openCard</pre>
Resume HyperCard	resume, openStack, openBackground, openCard
Start up HyperCard	startUp, openStack, openBackground, openCard

Message Order 139

This chapter describes the nature of control structures and the control structure vocabulary, which is made up of HyperCard keywords.

A **keyword** is a word whose meaning is predefined in HyperTalk. You cannot redefine keywords as variable names. Keywords are not sent as messages when they execute in scripts, nor can they be used in the Message box (except for do, if, and send). Some keywords provide the structure for handlers; others control the flow of execution within handlers.

HyperTalk has two kinds of handlers: message and function handlers, denoted by the initial keywords on and function, respectively. Message and function handlers are defined in the same way (except for the initial keyword), but they differ in how they are invoked and in how they return values.

The syntax for each keyword is given. In the syntax statements, words in italic represent general elements that you replace with a specific instance when you write a statement; brackets ([]) denote optional elements (don't type the brackets).

Keywords in Message Handlers

The on keyword identifies a HyperCard message handler. Message handlers are written to define your own messages, or to modify or redefine what happens in response to any message (including a HyperTalk command). The general syntax of a message handler looks like this:

on messageName [parameterList] statementList end messageName

MessageName is an identifier: a string starting with a letter and containing no spaces or punctuation marks except underscore; parameterList is a series of zero or more parameter variables (separated by commas if more than one); and statementList is one or more HyperTalk statements.

The handler dictates the method by which its object responds to <code>messageName</code>. When a message called <code>messageName</code> is sent to an object, HyperCard checks all of that object's message handlers to see if it has one named <code>messageName</code>. If so, the object responds according to that handler, and the message is sent no further (assuming the script has no pass statement, described later in this chapter). If the object has no handler to match <code>messageName</code>, HyperCard passes the message to the next object in the hierarchy.

You can override HyperTalk

If you name a message handler the same as a built-in command, your name overrides the built-in one if yours is anywhere along the message-passing hierarchy between the object sending the message and HyperCard. ◆

The statements in the handler execute until an end, exit, pass, or return keyword is reached (these keywords are discussed later in this section). A message handler can return a value through the built-in function the result (discussed in Chapter 11, "Functions").

On

on messageName [parameterList]

The on keyword marks the beginning of a message handler and connects the handler with a particular message. *MessageName* is the first word of the message to which the handler responds, and it is the name of the handler.

The optional *parameterList* allows the message handler to receive some values sent along with the message. This list is a series of local variable names, called *parameter variables*, separated by commas. When the message is sent, each source of value following the message name is evaluated; when the handler receives the message, each value is plugged into the parameter variable that appears in the corresponding position following on *messageName*. The first value in the list goes into the first parameter variable, and so on. If no values are sent with the message name, empty goes into each parameter variable.

Chapter 4, "Handling Messages," explains more about parameter passing. See also the param, paramCount, and params functions in Chapter 11, "Functions."

End

end messageName

The end keyword begins the last line of a handler—it is reached when all of the handler's statements have been executed (except for any bypassed conditional blocks). When the end statement is reached, the message that initiated execution of the handler is sent no further unless a pass <code>messageName</code> statement follows the end statement. (Pass is defined later in this section.) If the message that initiated this handler's execution was part of some other handler, control passes back to the other handler.

Exit

exit messageName exit to HyperCard

The exit *messageName* statement ends execution of the handler.

The exit to HyperCard form makes program flow return directly to HyperCard, bypassing any pending handlers that have not finished executing.

Pass

pass messageName

The pass messageName statement ends execution of the handler and sends the entire message that initiated execution of the handler to the next object in the hierarchy. (Ordinarily, a message is sent no further than the object containing the executing handler.)

Return

return expression

The return statement ends execution of the handler and, when it appears within a message handler structure, places the value of *expression* into the HyperTalk function the result.

The value of the result set by the return statement is valid only immediately after it executes; each new statement resets the result. (See the result function in Chapter 11, "Functions," for examples.)

Message Handler Example

The following example shows a handler that originates a message that in turn initiates execution of a second handler. (The second handler could be in the same script as the first or anywhere farther along the object hierarchy.)

```
on mouseUp

heyNow 5,10 -- heyNow is the message name that's sent
end mouseUp

on heyNow timeVar,timeVar2 --Handler name heyNow matches message name
play "boing" tempo 200 "c4e c dq c f eh" -- Happy Birthday
wait timeVar seconds
play stop
play "harpsichord" "ch d e f g a b c5w"
wait timeVar2 seconds
play stop
end heyNow
```

Execution of the first handler is initiated when its object receives a mouseUp message. The mouseUp message could be generated when the user clicks the mouse or types mouseUp in the Message box and presses Return. It could also originate from another handler executing the statement mouseUp or could be sent explicitly to the handler's object with a send command.

When the mouseUp handler executes, it sends its one command statement (heyNow 5,10) as a message, first to its own object. The message name (the first word of the message) matches the handler name (the word following on in the first line of the handler), so the statements in the second handler begin executing. (If the current object had no heyNow message handler, that object would pass the entire message on to the next object in the hierarchy.)

The values of the parameters following heyNow in the first handler are passed into the parameter variables following heyNow in the second handler. So when the second handler is executing, timeVar has the value 5, and timeVar2 has the value 10.

Keywords in Function Handlers

A **function** is a named value that is calculated by HyperCard when a statement in which it's used executes. The function keyword identifies a HyperCard function handler. You can use this structure to define your own functions, which then can be called from any place in a statement where their values are needed. (User-defined functions are called like built-in HyperCard functions except that you must always use parentheses—see "Return," later in this section.)

Like message handlers, function handlers cannot be nested inside each other (or inside message handlers). The general syntax of a function handler looks like this:

function functionName [parameterList]
 statementList
end functionName

FunctionName is an identifier: a string starting with a letter and containing no spaces or punctuation marks except underscore; parameterList is a series of zero or more parameter variables separated by commas; and statementList is one or more HyperTalk statements.

User-defined function handlers use the message-passing hierarchy in the same way as do message handlers. That is, when the function name appears in a statement or in the Message box, HyperCard searches through all of the scripts along the current message-passing hierarchy for a matching function handler. If

a match is found, the function handler executes. If none is found, the function call is passed to HyperCard; if there is no built-in function of that name, HyperCard displays an error dialog box.

If you name a function handler the same as a built-in function, your function is called when you use the function call syntax that uses parentheses. Of course, your function handler must also be in the script of an object lower or equal in the hierarchy than the originator of the function call. You can make calls to built-in functions using the function call syntax with the preceding the function name, which bypasses the message-passing hierarchy and calls HyperCard built-in functions directly.

Program flow runs through the function handler until it encounters an end, exit, pass, or return statement (discussed later in this section). A function handler returns a value directly into the statement in which its name was used.

Function

function functionName [parameterList]

The function keyword marks the beginning of a function handler and connects the handler with a particular function call. *FunctionName* is the function call to which the handler responds, and it is the name of the handler.

The optional *parameterList* allows the function handler to receive some values sent along with the function call. This list is a series of local variable names, called *parameter variables*, separated by commas. When the function call is made, each source of value appearing between parentheses following the function name is evaluated; when the handler begins to execute, each value is plugged into the parameter variable that appears in the corresponding position following function *functionName*, the first value in the list going into the first parameter variable, and so on.

For more details on passing parameters to function handlers, see "Return," later in this section.

End

end functionName

The end statement is the last line of the handler, reached when all of the handler's statements have been executed (except for any bypassed conditional blocks).

When the end statement is reached, control passes back to the handler containing the function call that originated the function handler's execution.

Exit

exit functionName
exit to HyperCard

The exit *functionName* statement ends execution of the handler.

The exit to HyperCard form makes program flow return directly to HyperCard, bypassing any pending handlers that have not finished executing, including the handler containing the function call.

Pass

pass functionName

The pass statement ends execution of the handler and sends the entire function call that initiated execution of the handler to the next object in the hierarchy. (Ordinarily, a function call is sent no further than the object containing the executing handler.)

Return

```
return expression
```

The return statement ends execution of the handler and, when it appears within a function handler structure, dictates the returned value of the function.

The value of *expression* replaces the function in the calling statement.

The function appears in the calling statement in the form *functionName* (*expressionList*):

```
put square(17) into card field 1
```

ExpressionList is a series of zero or more expressions separated by commas whose values are assigned to the parameter variables in the *parameterList* of the function handler. In the above example, the *expressionList* comprises only the number 17.

A user-defined function handler that would respond to the function call example square (17), shown above, is

```
function square x
   return x * x
end square
```

In this example, the function handler has one parameter variable to receive one value passed to it by the calling statement. The value 17 is passed to the function handler, where it is assigned to the parameter variable x; the value of x * x is returned by the return statement, replacing square(17) in the calling statement. So, the effect of the calling statement is to put the value 289 into card field 1.

Parentheses required

User-defined functions are always followed by parentheses (which are empty if there are no parameters to pass). Unlike built-in functions (explained in detail in Chapter 11), user-defined functions can't be called with the form the *function* of. ◆

Function Handler Example

The following function handler determines whether a number passed to it as a parameter is even or odd, returning the constant true if it's even or false if it's odd:

```
function evenNumber numberPassed
  return numberPassed mod 2 is 0
end evenNumber
```

A calling statement that would invoke the evenNumber function handler could be one like the following:

```
if evenNumber(numberVariable) then add 1 to evenNumberCount
```

In the calling statement, numberVariable can be the name of any variable or other source of value (including an actual number). HyperCard evaluates numberVariable before it passes the function call along the hierarchy, and its value is given to the parameter variable numberPassed when the evenNumber function handler is found. The part of the calling statement following then is arbitrary—the point of the example is to show how the function handler receives a value, examines it, and returns another value into the calling statement, based on the result of its execution.

Repeat Structure

The repeat structure causes all of the HyperTalk statements between its first and last lines to execute in a loop until some condition is met or until an exit statement is encountered. The general syntax of a repeat structure looks like this:

```
repeat controlForm
statementList
end repeat
```

ControlForm is one of the forms of the repeat statement described below, and statementList is any number of HyperTalk statements. Repeat structures can be used only within message handlers or function handlers.

Repeat Structure 149

Note

If you want to try the examples in this chapter, be sure to put them within handlers. ◆

Repeat Statements

The repeat keyword begins the first line of a repeat structure. The repeat statement has five forms differentiated by the second word of the statement. Additionally, the repeat with form has two variations.

Repeat Forever

```
repeat [forever]
```

The loop repeats forever, or until an exit statement is encountered (whichever comes first):

```
put 1 into Message box
repeat
   add 1 to Message box
   if Message box contains 6 then exit repeat
end repeat
```

The example ends with 6 in the Message box.

For information on exit repeat, see "Exit Repeat Statement," later in this chapter. For information on if, see "If Structure," later in this chapter.

Repeat For

```
repeat [for] number [times]
```

Number is a source that yields a positive integer specifying how many times the loop is executed:

```
put 1 into Message box
repeat for 5 times
   add 1 to Message box
end repeat
```

The example ends with 6 in the Message box.

Repeat Until

```
repeat until condition
```

Condition is an expression that always evaluates to true or false. The loop is repeated as long as the condition is false. The condition is checked prior to the first and any subsequent executions of the loop:

```
put 1 into Message box
repeat until Message Box contains 6
   add 1 to Message box
end repeat
```

The example ends with 6 in the Message box.

Repeat Structure 151

Repeat While

```
repeat while condition
```

Condition is an expression that evaluates to true or false. The loop is repeated as long as the condition is true. The condition is checked prior to the first and any subsequent executions of the loop:

```
put 1 into Message box
repeat while Message Box < 6
   add 1 to Message box
end repeat</pre>
```

The example ends with 6 in the Message box.

Repeat With

There are two variations of the repeat with form: one that increments a variable and one that decrements a variable.

```
repeat with variable = start to finish
```

Variable is a local or global variable name, and *start* and *finish* are sources of integers. The value of *start* is assigned to *variable* at the beginning of the loop and is incremented by 1 with each pass through the loop. Execution ends when the value of *variable* equals the value of *finish*.

```
repeat with increment = 1 to 6
   put increment into the Message box
end repeat
```

The example ends with 6 in the Message box. (This structure works much like a FOR... NEXT loop in BASIC.)

```
repeat with variable = start down to finish
```

The down to form is the same as the to form above, except that the value of *variable* is decremented by 1 with each pass through the loop. Execution ends when the value of *variable* equals the value of *finish*.

```
repeat with decrement = 6 down to 1
  put decrement into the Message box
end repeat
```

The example ends with 1 in the Message box.

Exit Repeat

```
exit repeat
```

The exit repeat statement sends control to the end of the repeat structure, ending execution of the loop regardless of the state of the controlling conditions specified in the repeat statement.

```
put 1 into the Message box
repeat with increment = 1 to 100
   add increment to the Message box
   if Message box > 20 then
      beep 5
      exit repeat
   end if
end repeat
```

The example ends with 22 in the Message box.

An exit statement can appear anywhere within the structure.

For information on if, see "If Structure," later in this chapter.

Repeat Structure 153

Next Repeat

```
next repeat
```

When a next repeat statement is encountered, control returns immediately to the top of the structure. (Usually, flow doesn't return to the top of the repeat structure until an end statement is encountered.)

```
repeat 20
  put random(9) into tempVar
  if tempVar mod 2 = 0 then next repeat
  put tempVar after field "oddNumbers"
end repeat
```

The example appends only the odd random numbers to the field, skipping any even ones.

A next statement can appear anywhere within the repeat structure.

For information on if, see "If Structure," later in this chapter. For more information about the random function, see Chapter 11, "Functions."

End Repeat

```
end repeat
```

The end repeat statement marks the end of the loop; it's the last line of a repeat control structure. When the controlling conditions specified in the repeat statement have been satisfied or an exit statement is encountered, control goes beyond the end statement:

```
repeat for 5 times
  beep
end repeat
```

If Structure

The if structure tests for the specified condition and, if the condition is true, executes the command statement or series of command statements that follow. The if structure has several forms, described in the following sections.

Note

If you want to try the examples in this section, be sure to put them within handlers. ◆

Single-Statement If Structure

A single-statement if structure has the form shown below:

```
if condition then statement [else statement]
```

A single-statement if structure can also occupy more than one line:

```
if condition
then statement
[else statement]
```

Within the if structure, *condition* is an expression that evaluates to true or false, and *statement* is a single HyperTalk command statement.

In the single-statement if structure, only one command statement can follow either then or else (if present), and the command statement must be on the same line with then or else.

If the condition between if and then is true, HyperCard executes the statement between then and else if else is present, or between then and the end of the line if else is not present following the statement, either on the same line or on the next line.

If Structure 155

If the condition between if and then is false, HyperCard executes the statement between else and the end of the line if else is present, or it ignores the rest of the line if else is not present:

```
if Message box > 10 then beep 5 else beep 15
```

In this example, if the Message box holds a value greater than 10, the Macintosh beeps 5 times; if the value in the Message box is 10 or less, the Macintosh beeps 15 times.

Note

Single-statement if structures can be used in the Message box. ◆

Multiple-Statement If Structure

A multiple-statement if structure accommodates more than one executable statement following then and, optionally, more than one statement following else:

```
if condition then
    statementList
[else
    statementList]
end if
```

You can also end a multiple-statement then clause with a single-line else, in which case no end if statement is needed:

```
if condition then
    statementList
else statement
```

Condition is an expression that evaluates to true or false, and *statementList* is any number of HyperTalk statements.

In the multiple-statement if structure, more than one command statement can follow either then or else (if present), and the first command statement must be on the line following then or else. That is, if you want to have more than one statement in a block following then or else, put a return character after the respective then or else. Such a multiple-statement block must be ended explicitly: a multiple-statement then block can be ended with either end if or else; a multiple-statement else block must be ended with end if.

If the condition between if and then is true, HyperCard executes the statement or statements between then and else if else is present, or between then and end if if else is not present.

If the condition between if and then is false, HyperCard executes the statements between else and end if if else is present, or it ignores what's between then and end if if else is not present:

```
if number of this card is 10 then
  put "We're done!" into msg
  go Home
else
  put "And the next question is:" into msg
  go next card
end if
```

Note

Multiple-statement if structures can be used only within message handlers or function handlers. ◆

Nested If Structures

If structures can be nested; that is, statements following a then or an else can include more if structures. Each nested multiple-line if structure must have its own end if, and an else always goes with the closest preceding if clause.

If Structure 157

The next example could be used as a mouseUp handler within a button.

```
repeat
  ask "Guess a number between 1 and 10:"
  if it is empty then
     exit repeat
  else
     if it is random(10) then
        put "You guessed it!"
     else
        put "Sorry, try again."
     end if
  end if
end repeat
```

In this example, satisfying the if it is empty condition in the first if structure allows the user to exit the loop by selecting the OK button without entering a number in the dialog box that is created with the ask command. Executing this example without the first if structure results in an endless loop, which you can exit by simultaneously clicking the Cancel button and pressing the Command-period keys.

Note

Nested-statement if structures can be used only within message handlers or function handlers. ◆

Do

```
do expression [as scriptingLanguage]
```

The do keyword causes HyperCard to get the value of *expression*; HyperCard then sends that value as a message. (The do keyword in HyperTalk does not work like the do in Pascal does.)

You can use the do *expression* [as *scriptingLanguage*] form to execute scripts in any scripting language supported by an OSA-compliant scripting component, as well as HyperTalk. Here are some examples:

```
do field 1 as AppleScript
do "people.dw.stuff = 1" as UserTalk
```

In versions of HyperCard before HyperCard 2.0, if *expression* was a field with more than one line, only the first line of the field was used by HyperCard and any lines that followed were ignored. HyperCard now evaluates any expression after the do keyword and sends it as a command. For example, if field 3 contains several lines of HyperTalk code and you say do field 3, the entire contents of field 3 are sent to HyperCard. Each line of the container executes just as if it were contained in a handler.

The do keyword can be used in the Message box.

Global

```
global variableList
```

VariableList is one or more HyperCard variable names separated by commas.

The global keyword makes a variable name known and its contents available to any script of any object in HyperCard. The following two lines are individual examples of global statements:

```
global myVar
global pages,sections,chapters
```

The following example handlers show a global variable being used for two handlers to access the same value:

```
on mouseUp
   global myVariable -- load the global here
   put 3 into myVariable
   writeResult
end mouseup
```

If Structure 159

```
on writeResult
  global myVariable -- now we can use the global
  put myVariable -- the value remains 3
end writeResult
```

Changing the value of a global variable in any script changes its value everywhere. The global keyword must be used in each handler in which the global variable is used.

Global variables are not saved in between sessions of HyperCard or when HyperCard is suspended by launching another application with the open command.

Send

```
send expression to program programName [with|without reply] send expression to program ID programID [with|without reply] send expression to this program [with|without reply] send "messageName [parameterList]" [to object]
```

Expression is any valid expression or sequence of commands in the scripting language supported by the target program, programName is the pathname of the application to send the message to, programID is the signature of the application to send the message to, messageName is a string beginning with a letter and containing no spaces or punctuation marks other than underscore, parameterList is one or more expressions (separated by commas if more than one), and object is a HyperCard object descriptor or HyperCard itself. If no object is specified, the message continues along the message-passing hierarchy. (See Chapter 4, "Handling Messages," for information on how the message-passing hierarchy works.)

The send keyword sends a message directly to a particular object, bypassing any handlers in the intervening message-passing hierarchy that might otherwise intercept the message.

```
send "hideIt" to field 3
send "addSums travel,food,hotel" to stack "expenseAccount"
send mouseUp to button "pushMe"
send "doMenu Print Card" to HyperCard
send "make waves" to program "FishingNet:MyHD:HyperCard"
send "build {project}" to program "MPW Shell" without reply
```

You can send a message directly to any object in the current stack or to another stack, but not to a specific object in another stack.

If the object has no message handler for *messageName*, the message is passed along the message-passing hierarchy stemming from the object to which the message was sent. If the object does have a matching handler, the handler executes, but the card to which it belongs does not necessarily open. Messages sent by executing the statements of the object's handler are sent along the receiving object's hierarchy.

The send expression to program form sends a "do script" Apple event from HyperCard to another application running remotely. You can use it to send a script to any program that understands the standard 'dosc' Apple event. By default, HyperCard waits for a reply from the target program before continuing. However, you can specify with the [without reply] option if you don't want to wait for a reply.

If the target program is running on a different Macintosh you must specify the Macintosh name; if it is in a different zone you must specify that also. The form of such a full pathname is *zone:Macintosh:program*.

SCRIPT

The following handler directs a copy of HyperCard 2.2 on a Macintosh computer named "MyMac," in the same zone as the sending computer, to go to the last card of its currently active stack. It then checks the result to make sure that the command executed:

```
on changeRemoteCard

send "go last card" to program "MyMac:HyperCard 2.2"

if the result is not empty -- problems?

then answer "Error during send!"

end changeRemoteCard
```

If Structure 161

The next handler sends a message to a copy of HyperCard running on a Macintosh computer named "Oahu" on a network zone named "Hawaii." The message tells the remote copy of HyperCard to execute the handler "doThisNow," already defined in the remote stack:

```
on doRemoteHandler send "doThisNow" to program "Oahu:Hawaii:HyperCard 2.2" end doRemoteHandler
```

NOTES

When sending Apple events to another program, if HyperCard has not established a link with the target program, the user is presented with a dialog box, through which the link is established. If a link has already been established between HyperCard and the target program, the Apple event is sent without further user interaction.

The following error messages go into the container the result of the source program when the send fails:

Condition	the result contents
Information returned is not recognized by HyperCard as text	Unknown data type
System software prior to version 7.0	Not supported by this version of the system
Target program didn't handle event	Not handled by target program
Target program returned error number in reply, or AESend returned some other error	Got error <errornum> when sending Apple event</errornum>
Target program returned error string in reply	<errorstring></errorstring>
Target program timed out	Timeout
User canceled "Link to program" dialog	Cancel

Chapter 4, "Handling Messages," has more information about how the send command interacts with the message-passing hierarchy.

Parameter expressions are evaluated before they are sent, even though the entire message has quotation marks around it.

The send keyword does not change cards when a message is sent to an object on a card other than the current card, or cause HyperCard to send open or close messages to cards, backgrounds, or stacks. For example, if you are on the second card and send a message to a button on the ninth card in the stack, the ninth card doesn't get an openCard message.

You can use it in the Message box

The do, if, and send keywords, unlike all other keywords, work in the Message box. ◆

If Structure 163

This chapter describes all the commands in HyperTalk, showing their syntax and meaning.

HyperTalk commands are built-in message handlers that reside in HyperCard itself. When you issue a HyperTalk command, it's passed along the message-passing hierarchy as a message to HyperCard. In most cases there's no handler in any script along the way to intercept the message, so HyperCard receives the message and acts on it.

Some commands (such as arrowKey) are system messages as well as commands. This means two things: a system event can generate the message (pressing an arrow key generates the arrowKey message), and HyperCard has a built-in response to the message (arrowKey takes you to another card).

Redefining Commands

You can write a message handler that redefines a built-in command. Redefining commands is especially useful for trapping menu commands you want to modify or that you want to prevent a user from issuing (for example, on doMenu menuItem).

Be wary, however: once a command—or any message—has been intercepted by a handler, it's sent no further along the hierarchy, so your newly defined command replaces HyperCard's built-in one. If, for example, you write a

handler for the doMenu command, be sure to pass the message if you don't want to prevent *every* instance of it from reaching HyperCard:

```
on doMenu menuItem
  if menuItem is "Delete Card" then
    answer "Are you sure?" with "Delete" or "Cancel"
    if It is not "Delete" then exit doMenu
    end if
    pass doMenu
end doMenu
```

If you inadvertently fail to pass doMenu, you may find yourself apparently unable to use any menu command, even to fix the doMenu handler. (In that case, from the Message box, execute the command edit script for the object containing the handler. If the Message box is hidden and blind typing is false, go to the last card of the Home stack and turn blind typing on.)

Syntax Description Notation

The syntax descriptions use the following typographic conventions. Words or phrases in this font are HyperTalk language elements or are those that you type to the computer literally, exactly as shown. Words in *italics* describe general elements, not specific names—you must substitute the actual instances. Brackets ([]) enclose optional elements that may be included if you need them. (Don't type the brackets.) In some cases, optional elements change what the message does; in other cases they are helper words that have no effect except to make the message more readable.

It doesn't matter whether you use uppercase or lowercase letters; names that are formed from two words are shown in lowercase letters with a capital in the middle (likeThis) merely to make them more readable.

The term *yields* indicates a specific kind of value, such as a number or a text string, that must result from evaluation of an expression when a restriction applies (for example, the expression and the destination in an add command must yield numbers). However, any HyperTalk value can be treated as a text string.

Some of the syntax statements and examples in this chapter use the soft return (\neg) character to continue long statements onto the next line. The soft return is used here because of the line length limitations of the page format used in this chapter. You should avoid using soft returns in your scripts so that the statements in your handlers are easier to read.

System 7 Commands

Some commands require system software version 7.0 or later. If you try to run a script with any of these commands in them while running an earlier version of system software, HyperCard sets the HyperTalk function the result to "Not supported by this version of the system."

Command Descriptions

The rest of this chapter describes the commands supported by HyperCard 2.2.

Add

SYNTAX

```
add number to [chunk of] container
```

Number is an expression that yields a number. *Chunk* is an expression that yields a chunk of a container. *Container* is an expression that identifies a container, such as a field, the Message box, the selection, or a variable.

EXAMPLES

```
add 3 to It
add field "Amount" to field "Total"
```

DESCRIPTION

The add command adds the value of *number* to the value of [*chunk* of] *container* and leaves the result in [*chunk* of] *container*. The value in the container when you begin must be a number; it is replaced with the new value.

SCRIPT

The following example handler sums numbers in a field, if each line of the field contains one number, and puts the result into the Message box. The name of the field is passed to the handler as a parameter.

```
on sumField whichField
  put 0 into total
  repeat with count = 1 to the number of lines¬
     in whichField
     add line count of whichField to total
  end repeat
  put total into msg
end sumField
```

Answer

SYNTAX

```
answer question [with reply [or reply2 [or reply3]]]
answer file promptText [of type fileType]
answer program promptText [of type processType]
```

Question and *reply* are expressions that yield text strings. If no reply is specified, HyperCard displays one button containing OK.

PromptText is an expression that yields a string of text that will appear in the dialog box as a prompt, telling the user what action to take. Use a string consisting of the space character, "", if you do not want a prompt to appear. If you are using the answer program form of the answer command and you use the null string, "", for the prompt text parameter, HyperCard displays the default prompt "Choose a program to link to:". (See Figure 10-3.) *PromptText* can be up to 254 characters.

Reply, reply2, and reply3 can be up to 254 characters each.

FileType is one of the following literal file types: stack, text, application, picture, paint, and painting. You can also specify the same file types with the following Macintosh four-letter file-type designators: STAK, TEXT, APPL, PICT, and PNTG.

ProcessType is a System 7–friendly process currently running on your machine or any others on the network.

EXAMPLES

```
answer "Which is the way the world ends?" with ¬
"Bang" or "Whimper"

answer myQuestion with myAnswer or field 7

answer file "Pick a text file:" of type text

answer file "" of type PICT

answer program "Pick a Zone, Macintosh, and Program."
```

DESCRIPTION

The answer command either displays a dialog box with a question and up to three buttons, each representing a different reply, or displays a standard file dialog box, with a list of either all the files of a certain type or a PPC Browser that contains a list of all the System 7–friendly processes currently running on your machine and any others on the network.

When you use the answer *question* form of the answer command, the last reply you specify correlates to the default button in the resulting dialog box. If no reply is specified, HyperCard displays one button containing OK. The dialog box stays on the screen until one of the buttons is clicked. Pressing Return or Enter has the same effect as clicking the default button.

When you use the answer file form of the answer command, HyperCard displays a standard file dialog box containing your prompt and a list of files. You can specify a file type using the *fileType* parameter. When your user selects a file from the file list, its name is placed in the local variable It.

Answer 169

The answer program command displays a dialog box in which the user can choose from all the System 7–friendly programs, or processes, running on the user's Macintosh computer or any other networked Macintosh computers.

When you select a program from the PPC Browser, its program path goes into the local variable It. If you click the Cancel button or press the Command-period keys, the variable It is empty and the result contains Cancel.

SCRIPT

The following example handler produces the dialog boxes in Figure 10-1 (the second one depends on which button you click in the first one):

```
on chooseColor

answer "Which color do you prefer?" with "Red" or¬

"Blue" or "Yellow"

if It is "Red" then answer "You picked Red."

else if It is "Blue" then answer "You picked Blue."

else if It is "Yellow" then answer "You picked Yellow."

end chooseColor
```

Figure 10-1 Answer command dialog boxes



The following example handler displays the standard file dialog box shown in Figure 10-2.

```
on mouseUp

answer file "Print what document?" of type text

if It is not empty then

put It into doc

answer file "Use what application?" of type ¬


application

if It is not empty then print doc with It

end if

end mouseUp
```

Figure 10-2 Answer command display of the standard file dialog box




Execute the following line of code from either a script or the Message box to produce the PPC Browser shown in Figure 10-3.

```
answer program ""
```

Answer 171

Figure 10-3 The PPC Browser produced using the answer program command



NOTES

There is no way for a script to reply to a dialog box by itself, so it's important that a script meant to run unattended not use answer.

The text of the button clicked goes into the local variable It. If no reply is specified, HyperCard displays one button containing OK.

The question can be up to 14 lines or 254 characters.

If you use a container with more than one line for a reply, the middle line is displayed in the button. (Only the center portion shows if the line is too long to fit in the button.) However, all lines go into the local variable It when the button is clicked.

Unless you're using container names, put the question and the replies inside quotation marks if they contain any spaces.

If you do not supply a file type for the answer file form, all file types are displayed in the dialog box. If you try to execute answer program under System 6, the result returns "Not supported by this version of the system".

See also the ask command, later in this chapter.

ArrowKey

SYNTAX

arrowKey direction

Direction is an expression that yields the name of one of the arrow keys: left, right, up, or down.

EXAMPLES

arrowKey left
arrowKey down

DESCRIPTION

The arrowKey command takes you to another card. The effects of the arrowKey command are shown in Table 10-1.

The arrowKey message, which invokes the arrowKey command if it reaches HyperCard, is normally generated by pressing any of the arrow keys on the keyboard. (Which arrow key you press determines the message's parameter value.) You can also send arrowKey from the Message box or execute it as a line in a script.

Table 10-1 Effects of the arrowKey command

Parameter value	Effect
left	Go to previous card in current stack
right	Go to next card in current stack
up	Go forward through recent cards
down	Go back through recent cards

ArrowKey 173

Note

The textArrows property alters the effect of pressing the arrow keys (see "TextArrows" in Chapter 12), but it does not affect the arrowKey command. ◆

See also the arrowKey message in Table 8-3.

SCRIPT

The following example handler works with extended keyboards. It makes function keys 9, 10, 11, and 12 send the arrowKey message with parameters of left, right, up, and down, respectively:

```
on functionKey whichKey -- map function keys to arrow keys if whichKey is 9 then arrowKey left else if whichKey is 10 then arrowKey right else if whichKey is 11 then arrowKey up else if whichKey is 12 then arrowKey down else pass functionKey end functionKey
```

Ask

SYNTAX

```
ask question [with defaultAnswer]
ask password [clear] question [with defaultAnswer]
ask file promptText [with fileName]
```

Question and defaultAnswer are expressions that yield text strings. PromptText is an expression that yields a text string. FileName is an expression that yields a default filename to be displayed in the filename field of the dialog box.

Put the question and the default answer inside quotation marks if they contain any spaces or if they are telephone numbers containing a hyphen (see the example script), unless you're using container names.

EXAMPLES

```
ask "Who needs this kind of grief?" with "Not me." ask field 1 with line 1 of field 2 ask password "Please enter your password:" ask file "Save this file as:" with "MyTextFile" ask file ""
```

DESCRIPTION

The ask command displays a dialog box containing a question with a text box into which the user can type an answer. The optional *defaultAnswer* string specifies an answer that appears initially in the window, highlighted so it can be easily replaced. The dialog box appears with OK and Cancel buttons. The *question* and *defaultAnswer* can have up to 14 lines between them for all text to display properly.

The ask password form causes the answer to be encrypted as a number (which is placed into the local variable It). The encrypted answer can be stored in a field to be compared to a later answer to ask password if, for example, you want the user to be able to protect data he or she enters into the stack. Password protection built into a stack in this manner is separate from that set up by the Protect Stack command in the File menu. The text entered in the password dialog box is hidden from the user. Like the ask form, the ask password form's *question* and *defaultAnswer* can have up to 14 lines between them for all text to display properly.

The ask file form of the ask command displays a standard dialog box for saving files. You can use the optional *fileName* form of the command to place a default filename in the filename text entry field of the dialog box. The *fileName* string should be 23 characters or less in length to fit into the text entry field. The default filename is replaced by the user when the user starts typing. If you do not supply a default filename, the filename text entry field is empty when the dialog box is displayed.

The *promptText* string should be 7 lines or less to fit into the dialog box. If you do not want a prompt, use " ".


Ask 175

SCRIPT

The following example handler produces the dialog box in Figure 10-4:

```
on phone
   ask "Dial what number:" with "555-1212"
   if It is not empty then dial It
end phone
```

Figure 10-4 Ask command dialog box



NOTES

The text typed into the box (the answer to the question, the password, or the filename) goes into the local variable It, either when the OK button is clicked or when Return or Enter is pressed. If the Cancel button is clicked, the dialog box goes away, but the answer is not placed into It. The function the result returns "Cancel".

If you use the ask password clear form of the ask password command, the password is not encrypted when it is typed in the dialog box.

Unless you're using container names, put the question and the default answer inside quotation marks if they contain any spaces (or if, as in the example, they are telephone numbers containing a hyphen—to prevent HyperCard from doing subtraction).

See also the answer command, earlier in this chapter.

Beep

SYNTAX

```
beep [number]
```

Number is an expression that yields an integer.

EXAMPLES

```
beep 5
beep line 3 of field 1
```

DESCRIPTION

The beep command causes the Macintosh speaker to play the system beep sound *number* times. If no *number* is given, the speaker sounds the system beep once.

SCRIPT

The following example handler uses the beep command to alert the user that an answer dialog box, to which the user must reply, is being displayed:

```
on openStack
  beep 2
  answer "Do you need instructions?" with "Yes" or "No"
  if It is "Yes" then go to stack "Instructions"
end openStack
```

Beep 177

Choose

SYNTAX

choose tool toolNumber

ToolName is an expression that yields the name of any one of the tools from the HyperCard Tools palette (shown in Figure 10-5). *ToolNumber* is an expression that yields an integer from 1 to 18.

EXAMPLES


choose browse tool choose tool 11 choose eraser tool

DESCRIPTION

The choose command changes the current tool as though you had chosen it from the Tools palette. Valid tool names and numbers are

```
browse (1)
               oval (14)
brush (7)
               pencil (6)
bucket (13)
               poly[gon] (18)
button (2)
               rect[angle] (11)
curve (15)
               reg[ular] poly[gon] (17)
eraser (8)
               round rect[angle] (12)
field (3)
               select (4)
               spray [can] (10)
lasso (5)
line (9)
               text (16)
```

Figure 10-5 Tools palette



SCRIPT

The following example shows a typical use of the choose command in a handler:

```
on drawBox
reset paint
choose rectangle tool
set lineSize to 2
drag from 50,50 to 150,150
choose browse tool
end drawBox
```

NOTES

You must have the user level set to Painting, Authoring, or Scripting to use the choose command, but the Tools palette need not be visible.

You can get the name of the current tool by using the function the tool in a handler or the Message box.

Setting user levels is described in the *HyperCard Reference* and in the userLevel global property description in Chapter 12, "Properties." The tool function is described in Chapter 11, "Functions."

Choose 179

Click

SYNTAX

```
click at point [with key [,key2[,key3]]]
```

Point is an expression yielding a point: two integers separated by a comma, representing horizontal and vertical pixel offsets (respectively) from the top-left corner of the card. *Key*, *key*2, and *key*3 are expressions that yield one of the following key names, separated by commas: shiftKey, optionKey, or commandKey (or cmdKey).

EXAMPLES

```
click at 100,100
click at the loc of button "Press me" with optionKey
```

DESCRIPTION

The click command causes the same actions as though you had clicked with the pointer at the specified point on the screen: the system messages mouseDown and mouseUp are sent to the objects under the pointer (but the visible pointer is not moved from its current location).

Using a with *key* form produces the same result as clicking the mouse button while holding down the specified key (or keys).

If *point* is within an unlocked field, the insertion point is set: if there is text at or past *point*, the insertion point is set at *point*; if there is text on the same line as *point* but *point* is beyond the end of text, the insertion point is set at the end of text on that line; if there is no text at *point*, the insertion point is set at the start of the line.

You can select a word by double-clicking it (that is, by executing the click command twice in succession at the location of the word). You can select any string of text by using click at the beginning, then using click with shiftKey at the end of the string.

SCRIPT

The following example handler selects and displays a word from a locked field when you click the word (mouseUp is not sent to unlocked fields when you click them):

```
on mouseUp

set lockText of me to false

click at the clickLoc -- simulates double-click

click at the clickLoc

get the selection

put It into the Message box

set lockText of me to true

end mouseUp
```

NOTES

The pixel offset values of *point* are not restricted to the size of the screen but are misinterpreted if greater than 32767.

See also the drag command, later in this chapter.

Close

SYNTAX

close [docPathname [in|with]] appPathname

DocPathname is an expression yielding a text string that is a valid document name. AppPathname is an expression yielding a text string that is a valid application name or desk accessory.

You must provide the full pathname of the document if it cannot be found through the search paths. When running System 7, both parameters, *docPathname* and *appPathname*, can refer to Finder alias files.

Close 181

EXAMPLES

```
close "HD:Applications:TeachText 7.1"
close "TestDoc" with "HD:MyApp 1.0"
```

DESCRIPTION

The close command closes an application, a document opened with another application, or a desk accessory, by sending one of the Apple event messages quit or clos to the other application. The form close [docPathname [in|with]] appPathname sends the close Apple event, and the form close appPathname sends a quit Apple event.

The other application or desk accessory must be on the same Macintosh computer as HyperCard, and that Macintosh computer must be running System 7. Also, the other application must recognize the Apple event quit to close itself and the Apple event clos to close a document. (See also the system message appleEvent described in Chapter 8, "System Messages.")

SCRIPT

The following button handler closes a specific application after the user's intention is confirmed:

```
on mouseUp -- Button handler

answer "Are you sure you want to close"¬
&&"OtherHyperCard?" with "No" or "Yes"

if It is "Yes"

then close "MacHD:OtherHyperCard"

end mouseUp
```

NOTE

The following error messages go into the container the result of the source program when the close command fails:

Condition	the result contents
Closing an application that's not running	No such application
Target program didn't handle event	Not handled by target program
Target program returned error number in reply, or AESend returned some other error	Got error <errornum> when sending Apple event</errornum>
Target program returned error string in reply	<errorstring></errorstring>
Target program timed out	Timeout

Close File

SYNTAX

close file fileName

FileName is an expression that yields a text string that is a valid filename.

EXAMPLES

```
close file myData
close file "myDisk:myFolder:myFile"
```

Close File 183

DESCRIPTION

The close file command closes a disk file previously opened with the open file command to import or export ASCII text. The expression *fileName* must yield a valid Macintosh filename, including pathname if required.

SCRIPT

The following example handler reads any size text file into a global variable named temp:

```
on importText
   global temp
  put "MyFilename" into filename
  open file filename
  read from file filename until end
  put It into temp
  close file filename
end importText
```

NOTES

If the specified file is not open, an error is generated. The error is stored in the HyperCard function the result. Use the close file command to close files explicitly after you use them. HyperCard automatically closes all open files when an exit to HyperCard statement is executed, when you press Command-period, or when you quit HyperCard.

You must provide the full pathname of the file if it's not at the same directory level as HyperCard. (See "Identifying a Stack" in Chapter 5 for an explanation of pathnames.)

See also the open file, read, and write commands, later in this chapter, and the result function in Chapter 11, "Functions."

Close Printing

SYNTAX

close printing

DESCRIPTION

The close printing command ends a print job previously begun with the open printing command or the open report printing command. Nothing is actually printed until the close printing command is executed.

SCRIPT

The following example handler executes a printing job. It prints a specified number of cards, beginning on a specified card:

```
on printRange low,high
  push card
  open printing
  go to card low
  print (high-low) + 1 cards
  close printing
  pop card
end printRange
```

NOTE

See also the open printing, open report printing, print, and print card commands, later in this chapter.

Close Printing 185

Close Window

SYNTAX

close window window

Window is an expression that identifies a stack window or picture window.

DESCRIPTION

The close window command closes the specified stack. The close window command works on stack windows only if more than one stack is open and the stack is active (or frontmost). The close window command also works on picture windows, external windows, and stacks that are hidden. When the specified window is closed, a close system message is also sent by HyperCard.

EXAMPLE

close window "Planets"

NOTE

You cannot use the close window command on HyperCard's built-in palettes; use the hide command instead.

See also the go command in this chapter and the close system message described in Chapter 8, "System Messages."

CommandKeyDown

SYNTAX

commandKeyDown char

Char is an expression yielding a character (spaces count as characters).

EXAMPLE

```
commandKeyDown "H" -- go Home
commandKeyDown "V" -- paste
commandKeyDown "5" -- doMyCommand
```

DESCRIPTION

The commandKeyDown command passes a character, *char*, which represents a key pressed in combination with the Command key. HyperCard has various built-in responses to the commandKeyDown command, depending on the character passed with it.

You can use the commandKeyDown command to take advantage of the built-in meanings for Command-key combinations in HyperCard. For example, commandKeyDown "P" is the same as pressing the Command key and "P" key together or selecting Print Card from the File menu.

You also can override HyperTalk Command-key combinations. If you name a message handler the same as a built-in command, your name overrides the built-in one if yours is anywhere along the message-passing hierarchy between the object sending the message and HyperCard.

In the case of keys other than those built into HyperCard, nothing happens when a given Command-key combination is pressed or a commandKeyDown command is executed unless you have a handler for that Command-key combination in the script of the current card or in a script somewhere in the message-passing hierarchy between the current card and HyperCard.

SCRIPT

The following example handler in a stack script in the current message-passing hierarchy opens the Navigator palette at the coordinates 20,30 when it intercepts the commandKeyDown system message and the parameter "Y". The handler works either if the Command-Y key combination is pressed or if you type the command commandKeyDown "Y" in the Message box.

```
on commandKeyDown whichKey
  if whichKey = "Y" then
    palette "navigator","20,30"
    exit commandKeyDown
  end if
  pass commandKeyDown
end commandKeyDown
```

NOTES

CommandKeyDown is also a system message sent to the current card when the Command key is pressed in combination with another key. See Table 8-3 for more information.

See also the keyDown and controlKey commands in this chapter, and the commandKey function in Chapter 11, "Functions."

ControlKey

SYNTAX

controlKey keyNumber

KeyNumber is an expression that yields an integer between 1 and 127. The values 97 through 126 do not correspond to any key.

EXAMPLE

controlKey 26

DESCRIPTION

The controlKey command passes a numeric value, *keyNumber*, which represents a key pressed in combination with the Control key.

NOTES

ControlKey is also a system message sent to the current card when the Control key is pressed in combination with another key. The acceptable values for the *keyNumber* parameter are shown in Table 10-2.

There are no built-in meanings for Control-key combinations in HyperCard. Nothing happens when a given Control-key combination is pressed or a controlKey command is executed unless you have a handler for that Control-key combination in the script of the current card or in a script somewhere in the message-passing hierarchy between the current card and HyperCard.

See also the controlKey system message in Table 8-3.

Table 10-2 ControlKey message parameter values

Parameter value	Keys	Parameter value	Keys
1	a, Home	12	l, Page Down
2	b	13	m, Return
3	c, Enter	14	n
4	d, End	15	0
5	e, Help	16	p, all function keys
6	f	17	q
7	g	18	r
8	h, Delete	19	S
9	i, Tab	20	t
10	j	21	u
11	k, Page Up	22	V

continued

ControlKey 189

 Table 10-2
 ControlKey message parameter values (continued)

Parameter value	Keys	Parameter value	Keys
23	W	47	Slash (/)
24	x	48	0
25	у	49	1
26	z	50	2
27	Esc, Clear, left bracket ([)	51	3
28	Backslash (\), Left Arrow	52	4
29	Right bracket (]), Right Arrow	53	5
30	Up Arrow	54	6
31	Hyphen (-), Down Arrow	55	7
39	Single quotation mark (')	56	8
42	Asterisk (*)	57	9
43	Plus (+)	59	Semicolon (;)
44	Comma (,)	61	Equal (=)
45	Minus (–)	96	Tilde (~)
46	Period (.)	127	Forward delete

SCRIPT

The following example handler in a stack script in the current message-passing hierarchy prints the current card when it intercepts the controlKey system message and the parameter 16. The handler works either if the Control-P key

combination is pressed or if you type the command controlKey 16 in the Message box.

```
on controlKey whichKey
  if whichKey = 16 then
      doMenu "Print Card"
      exit controlKey
  end if
  pass controlKey
end controlKey
```

Convert

SYNTAX

```
convert [chunk of] container|literal [[from format][and format]]
     to format [and format]
```

Container is an expression that identifies a container, and *format* is an expression that yields a time or date format. The optional [and *format*] specification is used when both a date and time are included. Valid formats and their meanings are as follows:

abbreviated dabbrev date abbr date		The date in text form with abbreviated day of week: Tue, October 17, 1989.
abbreviated t abbrev time abbr time	cime	Same form as short: 5:15 PM.
dateItems		A comma-separated list of numbers representing (in order) year, month, day, hour, minute, second, and day of week.
long date		The date in text form: Tuesday, October 17, 1989.

Convert 191

CHAPTER 10

Commands

long time	The time in colon-separated form including

seconds: 5:15:15 PM.

seconds Seconds since midnight, January 1, 1904.

continued

short date The date in slash-separated numeric form:

10/17/89. The date separators may be different in

countries other than the United States.

short time The time in colon-separated form without seconds:

5:15 PM.

EXAMPLES

This line of code puts the content of the first line of the second card field into the internationally invariant format dateItems:

convert line 1 of card field 2 from date to dateItems

If line 1 of card field 2 contains the date April 9, 1993, then HyperCard puts this into card field 2: 1993, 4, 9, 0, 0, 0, 6. Other examples using the convert command are

convert card field "Date and Time" from date and time to ¬ dateItems

convert timeVariable to seconds

convert myVar from seconds to long date

convert line 1 of second cd field to long date and ¬ short time

DESCRIPTION

The convert command gets a date or time and converts it from a particular format, if you choose to specify one, to a particular format. This command works with any date format supported by an installed script.

The first form of the convert command gets the date or time from a container and places the converted date or time in that container. When you use a literal as input to the convert command, the resulting date or time is stored in the HyperTalk variable It.

If you know precisely what format the input is in, you can choose to specify a format to convert from. If the input can't be parsed as specified, HyperTalk sets the result to "Invalid date".

Note that if you try to convert an invalid date, for example, a date that has the wrong number for the day, like Wednesday, May 6, 1993, when it should be Thursday, May 6, 1993, HyperTalk sets the result to "Invalid date".

IMPORTANT

A script that needs to perform calculations on dates and times should first convert to one of HyperTalk's invariant formats for dates and times—seconds and dateItems. This avoids problems that may occur when someone trys to run your stack on a machine where the format of the date has been localized (to Swedish format, for instance) or customized (to display military time, for instance) by changing resources in the System file. To make sure your scripts and stacks are localizable, you should also be careful to save dates and times in either seconds or dateItems format. These formats are the only ones that the commands convert and sort are guaranteed to recognize on any system.

SCRIPT

Here's an example that shows how to get tomorrow's date in the short format (this works no matter what format the date is set to by system resources):

```
on mouseUp

get the date -- the current date in short format

convert it to dateItems -- year, month, day, hour,

-- minute, second, day of week

add 1 to item 3 of it -- make it tomorrow

convert it to short date

end mouseUp
```

Convert 193

The following example handler counts the seconds elapsed while a command in the Message box executes:

```
on mouseUp
  put the long time into startTime
  convert startTime to seconds
  if msg is not empty then do msg
  put the long time into endTime
  convert endTime to seconds
  answer "That took" && endTime - startTime && "seconds."
end mouseUp
```

Create Menu

SYNTAX

create menu menuName

MenuName is an expression that yields the name of a new menu to be added to the menu bar.

EXAMPLES

```
create menu "Home"
create menu "Vacation locations"
```

DESCRIPTION

You use the create command to add a new menu to the HyperCard menu bar. After the new menu is created, it remains in the menu bar until it is deleted with the delete command, or you use the reset menubar command, or you quit HyperCard. If you want a set of menus to remain in the menu bar while a certain stack is open, create your menus in that stack's openStack system message handler. You can delete or disable your menus when you close your stack or open another stack by using the delete or disable command in closeStack or suspendStack system message handlers. See Chapter 8, "System Messages," for more information about system messages.

You can put menu items into the new menu with the put command, described later in this chapter. You can also specify a menu message to be sent when a menu item is chosen.

NOTES

See also the checkMark, commandChar, enabled, markChar, menuMessage, name, and textStyle properties in Chapter 12, "Properties."

See also the delete, disable, enable, and put commands in this chapter.

Create Stack

SYNTAX

create stack stackName [with background] [in a new window]

StackName is an expression that yields the name you want to assign to the new stack. Background is an expression that yields the descriptor of a background you want to use in the new stack. The background must be one in the current stack.

EXAMPLES

```
create stack "Ghosts" with this background
create stack "Mystery" with bkgnd 3
```

DESCRIPTION

The create command creates a new stack with the specified name and optionally with a specified background of the current stack.

If you do not specify a background, the stack is created with a blank background. If you use the form create stack *stackName* in a new window, the stack is created, appears in another window, and becomes the current stack. If you do not use the form in a new window, the current stack is closed.

Create Stack 195

NOTES

The create stack command no longer allows *stackName* to begin with the period character.

To create a stack with a background in a stack other than the current stack, you must go to the stack with the background you want to use before using the create stack command.

If the create stack command generates an error, it is stored in the HyperCard function the result.

The new stack is created with the same card size as the current stack. You can change the card size by resetting the rectangle property of the card window or by clicking the Resize button in the Stack Info dialog box, and then dragging the lower-right corner of the representation of the card to the size you want.

See also the result function in Chapter 11, "Functions," and the rectangle property in Chapter 12, "Properties."

Debug Checkpoint

SYNTAX

debug checkpoint

EXAMPLE

debug checkpoint

DESCRIPTION

The debug checkpoint command sets a checkpoint in a HyperTalk handler. When HyperCard encounters this message in a handler, it enters the debugger: it pauses execution of the handler and opens the script editor window, putting a box around the line where the checkpoint is set.

Once you are in the debugger, you can step or trace through the remaining lines of the script. You can step by pressing Command-S or choosing Step from the Debugger menu. You can step into by pressing Command-I or choosing

Step Into from the Debugger menu. You can trace by choosing Trace from the Debugger menu. You can trace into by pressing Command-T or choosing Trace Into from the Debugger menu. With each step, the next line of HyperTalk in the current handler is selected and executed.

NOTES

In combination, checkpoints and stepping can be used to examine, diagnose, and modify the behavior of sophisticated HyperTalk handlers.

See also Chapter 3, "The Scripting Environment," for more information about the debugger environment.

Delete

SYNTAX

```
delete chunk of container
delete menu
delete menuItem of menu
delete part
```

Chunk is a chunk expression referring to some text in a specified container, and container specifies the container. Menu is an expression that yields a menu descriptor. MenuItem is an expression that yields a menu item descriptor. Part is an expression yielding a button or field descriptor.

EXAMPLES

```
delete line 1 of field 1
delete char 1 to 5 of line 4 of field "Charlie" ¬
    of second card
delete menuItem "Paths..." of menu "Home"
delete menu "Windows"
delete second menuItem of menu 6
delete button 1
```

Delete 197

```
delete last button
delete card field "Temp Data"
delete field id 1234
```

DESCRIPTION

The delete command removes

- text from a container in the current stack
- a menu item
- a menu
- a part (button or field) from the current card

Note that this command lets you delete menus from the standard HyperCard menu bar, including the Tools, Patterns, Font, and Apple menus; but you can't delete menu items within those menus. If you delete those menus, the menu items in those menus can still be activated with the doMenu command or with their Command-key equivalents.

SCRIPT

The following example handler finds and deletes a name from a list with one name per line:

```
on zapaName

put "Maller" & return & "Calhoun" & return & "Winkler"¬

into list

ask "Delete which name from the list?" with empty

repeat with count = the number of lines in list¬

down to 1

if It is in line count of list then ¬

delete line count of list

end repeat

end zapaName
```

NOTES

Using the delete command to delete a chunk is not the same as using put empty into with the same chunk of text specified. For example, if you delete a line in a field with a statement like

```
delete line 4 of field 7
```

you delete the return character as well as the text; what was previously the fifth line becomes the fourth. The following statement leaves the return character in line 4:

```
put empty into line 4 of field 7
```

Even if you delete all of the text in a field, the field remains defined on the card or background, unlike selecting the field and choosing Cut Field or Clear Field from the Edit menu.

When you delete text in a field on a card other than the current one, the current card does not change. If you delete the text in a background field that has the sharedText property set to true, the text in that background field is deleted on every card with that background field.

Because deleting parts causes a deleteButton or deleteField message to be sent, you can delete only parts on the current card. In other words, delete button 1 of next card doesn't work; however, you do not get an error message when you try to do this.

In the case of the HyperCard standard menu items, the doMenu command works even when the item is deleted with the delete command. For example, if the File menu is deleted and the following handler is executed, HyperCard exits to the Finder:

```
on mouseDown

delete menuItem "Quit HyperCard" from menu "File"

doMenu "Quit HyperCard"

end mouseDown
```

Command-key equivalents, however, do not work for menu items that have been deleted, with one exception: Command-Q still works after the Quit HyperCard menu item is deleted.

Delete 199

Chapter 5, "Referring to Objects, Menus, and Windows," describes how to designate menus and menu items. Chunk expressions are described in Chapter 7, "Expressions." See also the create menu, disable, enable, and put commands in this chapter.

Dial

SYNTAX

```
dial number [with modem [modemCommands]]
```

Number is an expression that yields a string with numbers in it, and *modemCommands* are commands for your modem.

EXAMPLES

```
dial steve -- if steve is a variable containing a number dial "415-555-1212" dial "493-996-1010" with modem "ATS0=0S7=1DT" dial "493-973-6000" with modem
```

DESCRIPTION

The dial command, without the with modem option, generates the touchtone sounds for the digits in *number* through the Macintosh speaker. Holding the telephone handset up to the speaker works on some telephones; for others you need a device that feeds the Macintosh audio output to the telephone.

If you use the with modem option, the dial command sets up telephone calls using the Apple Modem 300/1200, the Apple Personal Modem, or any Hayes-compatible modem attached to the Macintosh serial port. The *modemCommands* parameters are those described in the manual for your modem. Their default value is "ATS0=0DT".

If *number* yields a string with numbers including a hyphen (as in 555-1212), enclose it within quotation marks to prevent HyperCard from doing subtraction with the hyphen before passing the number to the dial command (which ignores characters other than numbers). Similarly, enclose the *modemCommands* parameter within quotation marks.

NOTES

You can press Command-period to exit the dial command during the ten-second wait imposed when dialing with a modem.

A one-second delay occurs between opening the modem port and first using it.

Disable

SYNTAX

```
disable menuItem of menu
disable button
```

Menu is an expression that yields a menu descriptor. *MenuItem* is an expression the yields a menu item descriptor. *Button* is an expression that yields a button descriptor.

EXAMPLES

```
disable background button 5
disable menu "Home"
disable menu 5
disable menuItem "Get Back" of menu "Direction"
disable the fourth menuItem of sixth menu
```

DESCRIPTION

The disable command disables a menu, menu item, or button. When any of these objects is disabled, it is gray and inactive. The disable command also sets the enabled property to false. You should be aware that when you create a menu item, it is automatically enabled unless you use the disable command to change it.

If you try to use the disable command on a menu item, menu, or button that does not exist, HyperCard displays an error dialog box with the text, "No such menu" (or menu item or button) unless the lockErrorDialogs property is set to true.

Disable 201

Except for Command-Q, Command-key equivalents do not work on menu items that have been deleted or disabled.

NOTE

See also the commandChar, enabled, markChar, and menuMessage and button properties in Chapter 12, "Properties," and the create menu, enable, and put commands in this chapter.

Divide

SYNTAX

divide [chunk of] container by number

Chunk is an expression that yields a chunk expression. *Container* is a container that holds a numeric value, and *number* is any expression that yields a numeric value.

EXAMPLES

```
divide field "total" by 3
divide fahrenheit by celsius -- if fahrenheit and
   -- celsius are variables
divide line 3 of field 4 by 10
```

DESCRIPTION

The divide command divides the value of [chunk of] container by the value of number and puts the result into [chunk of] container.

SCRIPT

The following example handler figures the percentage represented by a fraction of two numbers specified as parameters:

```
on percent var1,var2
  divide var1 by var2
  put trunc(var1 * 100) & "%"
end percent
```

NOTES

The value previously in the container must be a number; it is replaced with the new value.

Division by 0 puts the result INF into *container*. (INF is the SANE value for infinity.) Division is carried out to a precision of up to 19 decimal places. The value for the amount of precision is set with the numberFormat property.

See also the numberFormat global property in Chapter 12, "Properties," and the discussion of numbers in Chapter 6, "Values."

DoMenu

SYNTAX

ItemName is an expression that yields the name of a menu command. *MenuName* is an expression that yields the name of a menu. *ModifierKey* is one or more comma-delimited combinations of optionKey, commandKey, and shiftKey.

EXAMPLES

```
doMenu "open stack..."
doMenu "Copy Card"
doMenu "Open Stack..." with shiftKey
```

DoMenu 203

DESCRIPTION

The doMenu command performs the menu command specified by *itemName* as though you had chosen the command directly from the appropriate HyperCard menu. In conjunction with the doMenu command, you can choose to suppress a dialog box by using the without dialog option.

You may also use an optional modifier key to apply to your menu item choice. For instance, if someone chooses the Open Stack menu item while holding down the Shift key, the Open Stack dialog box appears with the New Window checkbox already checked. This HyperTalk command line does the same thing:

doMenu "Open Stack..." with shiftKey

Note

If you write your own doMenu handler to intercept menu commands, you can examine param(6) to find out if a modifier key parameter was specified. ◆

There are several caveats to be aware of when using or intercepting the doMenu command:

- Both the specified menu item and the menu in which it resides must be available at the current user level (as described in the *HyperCard Reference Guide*).
- If there are periods following the menu item, you must include them in *menuItem* (you can't use the ellipsis character in their place). For example, "Open Stack..." is a HyperCard menu item with three periods.
- Some menu commands change with conditions (for example, Paste Card can change to Paste Button, depending on the contents of the Clipboard).
- If you write a handler to intercept the doMenu system message that is sent to the current card when a menu item is selected, be sure to pass the message after examining the new menu item. (See the example.) Otherwise, you may find yourself apparently unable to use any menu command, fix the doMenu handler, or quit HyperCard. (In that case, from the Message box, execute the command edit script for the object containing the handler. If the Message box is hidden and blind typing is false, go to the last card of the Home stack and turn blind typing on.)

SCRIPT

The following example handler checks for a doMenu message with the Quit HyperCard menu item and puts up a dialog box when the Quit HyperCard menu item is selected:

```
on doMenu menuChoice
  if menuChoice is "Quit HyperCard"
  then
    answer "Are you sure you want to Quit" ¬
    with "OK" or "Cancel"
    if it is "Cancel"
    then
       exit doMenu
    else
       pass doMenu
    end if
else
    pass doMenu
    end if
end doMenu
```

Drag

SYNTAX

```
drag from point1 to point2 [with key [,key2[,key3]]]
```

Point1 and point2 are expressions, each of which yields a point: two integers separated by a comma, representing horizontal and vertical pixel offsets (respectively) from the top left of the Macintosh screen. Key, key2, and key3 are one of the following key names, separated by commas: shiftKey, optionKey, or commandKey (or cmdKey).

Drag 205

EXAMPLES

```
drag from 100,100 to 200,200 drag from the loc of button 1 to the mouseLoc with ¬ commandKey,shiftKey
```

DESCRIPTION

The drag command performs the same action as though you had dragged manually, except that in order to select text in a field using the drag command, you must use with shiftKey. In all other cases, using the with key form produces the same result as dragging while holding down the specified key.

SCRIPT

The following example handler draws random-sized ovals filled with random patterns on a new card:

```
on mouseUp

doMenu "New Card" -- so we don't draw on current card
choose oval tool
set filled to true
repeat until the mouseClick
set pattern to random(30)
drag from random(319),random(199) to ¬
random(319),random(199)
end repeat
choose browse tool
doMenu "Delete Card" -- get rid of the card we just made
go previous card -- take us back where we started from
end mouseUp
```

NOTES

You can use drag with any tool selected, but it has no effect with some Paint tools.

The location of the actual pointer doesn't change from where it was before the command was issued.

See also the click command earlier in this chapter, and the dragSpeed property in Chapter 12, "Properties."

Edit Script

SYNTAX

edit [the] script of object

Object is an expression that yields a descriptor of an object: a stack, card, background, field, or button.

EXAMPLES

edit script of button 1
edit script of this stack

DESCRIPTION

The edit script command opens the script of the specified object with the HyperCard script editor as though you had clicked the Script button in the object's Info dialog box.

SCRIPT

The following example handler enables you to edit the script of any button or field merely by positioning the pointer over it and pressing the Option key:

on mouseWithin

if the optionKey is down then edit script of the target end mouseWithin

NOTE

Refer to Chapter 3, "The Scripting Environment," for an explanation of how the script editor works.

Edit Script 207

Enable

SYNTAX

```
enable button
enable menu
enable menuItem of menu
```

Button is an expression that yields a card or background button descriptor. *Menu* is an expression that yields a menu descriptor. *MenuItem* is an expression that yields a menu item descriptor.

EXAMPLES

```
enable menu "Home"
enable menu 5
enable menuItem "Get Back" of menu "Direction"
enable the fourth menuItem of sixth menu
enable background button id 3
enable btn "PanAm"
```

DESCRIPTION

The enable command makes the specified menu, menu item, or button active by setting its enabled property to true and making its text and outline appear solid rather than dimmed.

If you enable a menu, menu item, or button that does not exist, HyperCard displays an error dialog box with the text "No such menu" (or menu item or button) unless the lockErrorDialogs property is set to true.

NOTES

See also the commandChar, enabled, markChar, and menuMessage and button properties in Chapter 12, "Properties," and the create menu, disable, and put commands in this chapter.

Command keys do not work on menu items that have been deleted or disabled.

EnterInField

SYNTAX

enterInField

DESCRIPTION

The enterInField command closes a field that is open for text editing.

NOTES

The enterInField system message, which invokes the enterInField command if it reaches HyperCard, is normally sent by pressing the Enter key on the keyboard, but you can also execute it as a line in a script.

Closing a field with enterInField sends the closeField system message; if no text was changed, the exitField system message is sent.

See also the enterKey and exitField system messages in Chapter 8, "System Messages."

EnterKey

SYNTAX

enterKey

DESCRIPTION

The enterKey command sends a statement typed into the Message box to the current card or, if a field is open for text editing, closes the field.

EnterInField 209

NOTES

The enterKey system message, which invokes the enterKey command if it reaches HyperCard, is normally sent by pressing the Enter key on the keyboard, but you can also execute it as a line in a script.

Closing a field with enterKey sends the closeField system message; if no text was changed, the exitField system message is sent.

See also the enterKey and exitField system messages in Chapter 8, "System Messages."

Export Paint

SYNTAX

export paint to file fileName

FileName is an expression that yields any valid Macintosh filename.

EXAMPLE

export paint to file "TreeFrogs"

DESCRIPTION

The export paint command creates a Macintosh paint file containing the image of the current card and saves it with the specified filename. If you are working in the background, only the graphics, buttons, and fields visible in the background are exported. If you are not working in the background, export paint exports both the card and background graphics plus all the visible card and background buttons and fields.

NOTES

If an error is generated while using the export paint command, the error is stored in the HyperCard function the result.

The export paint command only works when a Paint tool is chosen. If you use export paint while using the browse, button, or field tool, an error message is put into the result.

See also the import paint command in this chapter and the result function in Chapter 11.

Find

SYNTAX

find [international] text [in field] [of marked cards] find chars [international] text [in field] [of marked cards] find string [international] text [in field] [of marked cards] find whole [international] text [in field] [of marked cards] find word [international] text [in field] [of marked cards]

Text is an expression that yields a series of one or more text strings separated by spaces, and *field* is an expression that yields a card field or background field descriptor.

EXAMPLES

```
find "money" in field "Charity"
find chars "Wild" in field 1
find word msg in second field
find word international "æble" in field 5
```

DESCRIPTION

The find command searches through all the card and background fields (visible or not) in the stack for the text strings yielded by *text*. The search begins on the current card and continues through the last card, the first card, and on to the card previous to the current card. The of marked cards option searches only marked cards.

Find 211

You can use the international option with the find command to enable searching that recognizes international characters like æ and ø as unique from a and o. This is important in languages such as Danish, where such characters are distinguished.

Note

If you write a handler to override the find command, you can examine param(1) to determine whether the international option was specified. ◆

Choosing Find from the Go menu (or pressing Command-F) puts the find command in the Message box with the text insertion point after it between double quotation marks.

SCRIPT

The following example handler queries the user for search criteria, then executes the find command:

```
on doMenu var

global findString

if var is "Find..." then

ask "Find what string:" with findString

if It is not empty then

put It into findString

answer "Match" && findString && "how:" ¬

with "Chars" or "Word" or "All"

if It is "Chars" then find chars findString

else if It is "Word" then find word findString

else find findString

end if

else pass doMenu

end doMenu
```

NOTES

The find command executes faster if you use as many three-character combinations as possible in the search string. That is, three characters are faster than one, six are faster than three, nine are faster than six, and so on.

The find form finds the match only at the beginnings of words. The find chars form finds the match anywhere within words. The find word form matches only complete words.

The find whole form (also invoked by pressing Command-Shift-F) lets you search for a specific word or phrase, including spaces. For HyperCard to find a match, all the characters must be in the same field, and they must be in the same order as they appear in the string derived from *text*.

When you use find without whole, HyperCard finds a card that contains every word in the string derived from *text*, but the words can appear in different order or in different fields. That is, with find whole, interword spaces are part of the search string; without whole the spaces delimit separate search strings. With every form of find, you can limit the search to a specific background field.

The following example finds a card with a field that has the phrase *Apple Computer* in it; it won't find *Apple Computers* or *This apple is a computer*. (The find command without whole would find a match in all three cases.)

find whole "Apple Computer"

Find whole won't find partial-word matches, and it pays no attention to case or diacritical marks: *apple Compüter* and *aPPle cOmputer* are seen as the same. (If the international option is specified, however, diacritical marks are recognized.)

The find string form lets you search for a contiguous string of characters, including spaces, regardless of word boundaries. (Find whole searches for characters at the beginnings of words.) For HyperCard to find a match, all the characters must be in the same field, and they must be in the same order as in the string derived from *text*. For strings without spaces, find string works the same as find chars.

Find 213

In the following example, HyperCard finds the string in *Apple computers* but not in *computers, not apples*. (The find command without string would not find a match in either case.)

```
find string "ple Computer"
```

If the match is on a different card, it becomes the current card; if a match isn't found, the current card doesn't change. If you enter the find command from the Message box and a match isn't found, HyperCard sounds a beep. If it finds a match, HyperCard puts a box around the word containing the found string if the field containing the string is visible. If a match is found in a hidden field, the field's card becomes the current card, but the field remains hidden.

As the find command evaluates the expression passed to it, it places the resulting values internally between quotation marks as a single parameter string. The following examples show text expressions on the left and the resulting parameter string on the right:

If more than one search string (separated from each other by spaces) is included in the parameter string, all of them must be on a single card or its background for a successful search. However, they can be in any order on the card, and only the first is shown with a box around it.

The text in shared background fields and in backgrounds, cards, and fields with the dontSearch property set to true is ignored by the find command.

Press Command-F to display the parameter string from the most recently executed find command in the Message box.

An unsuccessful search sets HyperTalk's function the result to not found. After a successful search, the result is empty. (See the result function in Chapter 11, "Functions.")

For more information about retrieving text, see the foundChunk, foundField, foundLine, and foundText functions in Chapter 11, "Functions."

FunctionKey

SYNTAX

functionKey keyNumber

KeyNumber is an expression that yields an integer between 1 and 15.

EXAMPLES

```
functionKey 1
functionKey 15
```

DESCRIPTION

The functionKey command has built-in Undo, Cut, Copy, and Paste functions for *keyNumber* values 1 through 4, respectively. Any other value of *keyNumber* has no built-in effect.

SCRIPT

The following example handler uses the functionKey command to implement the message undo as a command:

```
on undo
```

functionKey 1 -- preprogrammed as undo in HyperCard
end undo

NOTES

The functionKey message, which invokes the functionKey command if it reaches HyperCard, is normally generated by pressing one of the 15 function keys on the Apple Extended Keyboard. But you can also send it from the Message box or execute it as a line in a script.

You can program function keys 5 through 15, or reprogram keys 1 through 4, by writing an on functionKey handler in the script of any object in the hierarchy between the current card and HyperCard. The following

FunctionKey 215

functionKey handler opens the print report dialog box when function key 9 is pressed.

```
on functionKey whichKey
  if whichKey = 9 then
     doMenu "Print Report..."
     exit functionKey
  end if
  pass functionKey
end functionKey
```

See also the functionKey system message in Chapter 8, "System Messages."

Get

SYNTAX

get expression

Expression yields any value.

EXAMPLES

```
get the long name of field 1
get the location of button "newButton"
get 2+3 -- puts 5 into It
get the date
```

DESCRIPTION

The get command puts the value of any expression into the local variable It. That is, get *expression* is the same as put *expression* into It.

SCRIPT

The following example handler saves the current user level, sets the user level to 5, then restores the saved level:

```
on doMything

get userLevel -- get the current userLevel

put It into savedLevel -- save userLevel before

-- changing it

set userLevel to 5 -- set userLevel for my

-- button or script

-- (put my script here)

-- restore userLevel when leaving

set userLevel to savedLevel

end doMything
```

Go

SYNTAX

```
go [to] [stack] stackName [in a new window] [without dialog]
go [to] background [of [stack] stackName [in a new window]]¬
    [without dialog]
go [to] card [of background] [of [stack] stackName¬
    [in a new window]] [without dialog]
go back
go forth
go [to] ordinal
go [to] position
```

StackName is an expression that yields a valid stack name. Card is an expression that yields a valid card descriptor. Background is an expression that yields a valid background descriptor. Ordinal is an expression that yields an ordinal constant. Position is an expression that yields a special object descriptor.

Go 217

EXAMPLES

```
go card 23
go to stack "ArtIdeas"
go bkgnd field 1 -- if bkgnd field 1 contains a stack name
go "home"
go mid card of stack "clip art"
go next
go to first card of second background of "home"
go card 2 of stack "VacationSpots" in a new window
go stack "VacationSpots" in a new window without dialog
go card 4 of stack "VacationSpots" without dialog
go "hd:bigFolder:innerFolder:myStack" -- full pathname
```

DESCRIPTION

The go command takes you to the specified destination. If you name a stack without specifying a card, you go to the first card in the specified stack. If you don't name a stack, you go to the specified card in the current stack. If you go to a background, you go to the next card with that background (not the first card). If the current card has the specified background, you won't move. Go forth and go back move you forward and backward among the recent cards. You can specify a visual effect to be used on opening the card by issuing the visual effect command before you use the go command.

If the destination is in a stack other than the current one and you use the in a new window form of the go command, the destination stack is opened in addition to any existing stacks. If you do not specify the in a new window form, the current stack is closed before the specified stack is opened. If only one stack is open and you do not specify the in a new window form of the go command, the current stack closes and the specified stack appears without a close box.

If you use the without dialog form of the go command and the destination can't be found, you do not get a standard dialog box for opening files. Instead, the result is set to "No such stack" or "No such card". If the destination is a marked card within a stack that has no marked cards, you won't move.

CHAPTER 10

Commands

SCRIPT

The following example handler queries the user for a destination, then executes a go command with a visual effect:

```
on mouseUp
   ask "Where to?" with "This card"
   if It is empty then put "this card" into It
   put It into goWhere
   visual effect fade to black
   go to goWhere
end mouseUp
```

Help

SYNTAX

help

DESCRIPTION

The help command takes you to the first card of the stack named HyperCard Help.

NOTE

See also the \mbox{help} system message in Chapter 8.

Help 219

Hide

SYNTAX

hide background picture
hide card picture
hide groups
hide menuBar
hide object
hide picture of background
hide picture of card
hide titlebar
hide window stackName
hide window windowName

Object yields one of the following:

a valid button descriptor in the current stack
a valid field descriptor in the current stack
message [box] or message [window] or window "message"
pattern window or window "patterns" (the Patterns palette)
tool window or window "tools" (the Tools palette)
window "navigator" (the Navigator palette)
message watcher or window "message watcher"
variable watcher or window "variable watcher"
card window

Card yields the descriptor of a card in the current stack. Background yields the descriptor of a background in the current stack. WindowName is the name of a window created with the picture command. StackName is the name of an open stack.

CHAPTER 10

Commands

EXAMPLES

hide message
hide bkgnd button "goHome"
hide field id 1
hide window "Planets"
hide card window

DESCRIPTION

The hide command removes the specified object from view. Its effect is the same as setting the visible property of the specified object to false or clicking a window's close box (except for external windows and stack windows).

The hide picture form of the hide command removes from view the graphic bitmap on the card or background, and the show picture form of the show command displays it.

The hide groups form of the hide command removes the gray 2-pixel underline made visible below group style text by the show groups form of the show command. The hide groups command affects all group style text in all fields globally.

SCRIPT

The following example handler hides a field or button when the user puts the pointer over the button or field:

on mouseWithin

hide the target
end mouseWithin

NOTES

Message can be abbreviated msg. Background can be abbreviated bkgnd. Button can be abbreviated btn. Card can be abbreviated cd.

Hide menuBar is also sent as a system message when the menu bar is hidden.

Hide 221

If the screen is locked, hide menuBar has no effect. See the lock and unlock commands later in this chapter, and the lockScreen property in Chapter 12, "Properties."

The hide command does not affect the location property of an object or window. You can't use the with the object name. For example, the following statement results in the error message "Can't understand arguments of command hide":

hide the window "navigator"

Hidden fields aren't in the tab order. (They are skipped when you move the text insertion cursor from one visible field to the next by pressing the Tab key.) The find command does search through them, however, and you can put values into them and put their values elsewhere.

Hidden card and background pictures are not displayed when a Browse, Button, or Field tool is chosen, but if you attempt to use a Paint tool manually, a dialog box appears asking if you want to make the picture visible; clicking OK displays the picture. (You can draw on hidden pictures from a script.) Whether or not you are working in the background determines whether your actions pertain to the card or background picture.

If there is another card window behind the current stack's card window and you hide the current stack's card window, the card window behind it becomes the current card window.

If you use either the hide card window or hide window *stackName* form of the hide command to hide the current card or specified stack, the cards in that stack won't be visible again until you set the card window or stack window's visible property to true, use the show card window or show window *stackName* command, or close the stack and reopen it.

You can move hidden windows without changing their visible state with the location property, which is described in Chapter 12, "Properties."

See also the picture and show commands, later in this chapter, and the visible property in Chapter 12, "Properties."

Import Paint

SYNTAX

import paint from file fileName

FileName is an expression that yields a valid Macintosh filename.

DESCRIPTION

The import paint command reads in the specified paint file and makes it the current selection. The import paint command allows you to put digitized images and other pictures created with Macintosh paint programs onto backgrounds or cards.

You can use the export paint and import paint commands together to enhance graphics created with HyperCard. For example, you could export a card image to a file and open it in your favorite paint application. You could then paste in your own pictures and make changes to the file containing the HyperCard card art with your paint program. Once you complete the art work, import the finished paint file to the original card or new card or background.

NOTES

If an error is generated while using the import paint command, the error is stored in the HyperCard function the result.

The import paint command only works when a Paint tool is chosen. If you use import paint while using the Browse, Button, or Field tools, an error message is put into the result.

Imported pictures are clipped to the size of the current card. The maximum area of an imported paint file that can be displayed is 576 pixels by 720 pixels.

See also the export paint command in this chapter and the result function in Chapter 11, "Functions."

Import Paint 223

KeyDown

SYNTAX

keyDown char

Char is an expression yielding a character (spaces count as characters).

EXAMPLE

keyDown "h"

DESCRIPTION

The keyDown command passes a character, *char*, which represents any character on the keyboard. The keyDown command causes HyperCard to enter the character passed with the command at the insertion point in a field, if one is open for text editing, or, otherwise, in the Message box.

NOTES

keyDown is also a system message sent to the current card when the user presses a character key. When the keyDown message reaches HyperCard, it invokes the keyDown command.

See also the commandKeyDown and controlKey commands in this chapter.

Lock

SYNTAX

lock screen error dialogs messages recent

EXAMPLES

lock screen
lock error dialogs
lock messages
lock recent

DESCRIPTION

The lock command can be used for four different unrelated purposes. Using the lock command, you can

- prevent HyperCard from updating the screen by setting the lockScreen global property to true
- prevent HyperCard from displaying error dialogs in response to an error in an executing script by setting the lockErrorDialogs property to true
- prevent HyperCard from sending automatic open, close, suspend, and resume system messages by setting the lockMessages property to true
- prevent HyperCard from recording miniature representations of each card to the Recent card by setting the lockRecent global property to true

NOTE

See also the unlock command in this chapter and the lockErrorDialogs, lockRecent, lockMessages, and lockScreen properties in Chapter 12, "Properties."

Lock 225

Mark

SYNTAX

```
mark card
mark cards where condition
mark all cards
mark cards by finding [international] text [in field]
mark cards by finding chars [international] text [in field]
mark cards by finding string [international] text [in field]
mark cards by finding whole [international] text [in field]
mark cards by finding word [international] text [in field]
```

Card is an expression that yields a card descriptor. Condition is an expression that evaluates to true or false. Text is any text. Field is an expression that yields a field descriptor.

EXAMPLES

```
mark [the] next card
mark cards where "We be shaking" is in field 2
mark all cards
mark cards by finding whole chicken in field 1
mark cards where the short name of this bkgnd is "Clients"
mark cards where the number of buttons > 0
```

DESCRIPTION

The mark command sets the marked property for the specified card or cards to true. Cards can also be marked with the Card Marked option in the Card Info dialog box. By default, cards are unmarked.

The by finding form of the mark command uses chars, word, whole, and string to define the search criteria the same way the find command does. See the description of the find command for information about how to use these forms.

You can use the international option with the find command to enable searching that recongnizes international characters like æ and ø as unique from a and o. This is important in languages such as Danish, where such characters are distinguished.

The mark command can be used with the unmark command in searches where you want to find and mark cards containing particular information while excluding other unnecessary information.

For example, say you want to mark and print all cards with information about "San Francisco" but not "earthquake." You might have a script that uses the following statements:

```
unmark all cards mark cards where "San Francisco" is in field 1 unmark cards where "earthquake" is in field 1
```

You could then show, print, or display the number of cards containing that combination of search criteria.

```
show marked cards
print marked cards
put the number of marked cards into word 3 of field 2
```

NOTES

See also the marked property in Chapter 12, "Properties," and the unmark command, later in this chapter.

You can't mark cards in a read-only stack, even if the userModify property is set to true. See the userModify property in Chapter 12, "Properties."

Mark 227

Multiply

SYNTAX

multiply [chunk of] container by number

Chunk is an expression that yields a chunk expression. *Container* is a container holding a numeric value, and *number* is an expression that yields a numeric value.

EXAMPLES

```
multiply Subtotal by Tax
multiply field 1 by field 3
multiply line 3 of card field 2 by 25
multiply It by 2 -- puts result into It,
-- replacing the old value
```

DESCRIPTION

The multiply command multiplies the value in [chunk of] container by the value of number and puts the result in [chunk of] container.

SCRIPT

The following example handler adds 6 percent to the value of items in a list:

```
on taxMe
  put "12.45,15.00,150.00,76.95,10.00,14.95" into taxables
  repeat with count = 1 to the number of items in taxables
    multiply item count of taxables by 1.06
  end repeat -- the new values are stored in taxables
end taxMe
```

NOTES

The value previously in the container must be a number; it is replaced with the new value.

The result is calculated to a precision of up to 19 decimal places and, if put into a field or the Message box, is displayed according to the numberFormat global property.

See also the numberFormat global property in Chapter 12, "Properties," and the discussion of numbers in Chapter 6, "Values."

Open

SYNTAX

```
open [fileName with] application
```

Application is the name of any application, and *fileName* is the name of any document on your Macintosh computer. Either one can be an expression that yields such a name.

EXAMPLES

```
open "Apps:BigApp"
open "Letter" with "Apps:MacWrite"
open Field 3
open FavoriteApp
```

DESCRIPTION

The open command launches the named application. A specific document may be opened with its own creator or a compatible application by using the open *filename* with *application* form of the open command.

Open 229

SCRIPT

The following example handler queries the user for a document and application before executing the open command:

```
on mouseUp

ask "Open what document?" with empty

if It is not empty then

put It into doc

ask "Use what application?" with empty

if It is not empty then open doc with It

end if

end mouseUp
```

The open command can also bring HyperCard itself to the front—when it is running under system software version 7.0 or later. When you need to make HyperCard the frontmost process, use command lines like these in your own script:

```
get the long name of HyperCard -- get pathname of HyperCard open it
```

This is useful if, for instance, you want to transfer data from another application to HyperCard via the Clipboard. Neither MultiFinder nor the System 7 Process Manager allows access to the Clipboard when an application is in the background. So, if you want to automate a copy and paste between some other application and HyperCard, you must also automate switching between applications.

NOTES

If the document or application you specify isn't at the top level of the file hierarchy (the "disk" level), then the path to it must be specified on the appropriate Search Path card of the Home stack. Alternatively, you can specify the full pathname with the open command:

```
open "MyHardDisk:Apps:Apples"
```

Note that handlers that override the open command may use the function the params to determine the parameters of the original command.

If HyperCard can't find the requested document or application, it displays the dialog box for locating files to the user. Error messages go into the container the result of the source program when the open command fails.

When running single Finder in System 6 and you quit the application, you go to the card you were on in HyperCard when you executed the open command. However, any global variables you had previously declared are now gone, and any portions of handlers that remained unfinished when you executed the open command do not finish.

Open File

SYNTAX

open file fileName

FileName is the name of any file accessible to your Macintosh computer, or an expression that yields such a name.

EXAMPLES

```
open file "textOnly" open file field 1
```

DESCRIPTION

The open file command opens the named file for reading or writing. Usually, the file is an ASCII text file opened in preparation for importing or exporting text. If the specified file doesn't exist, HyperCard creates it.

Open File 231

SCRIPT

The following example handler opens a given file, reads a line of data from it, then closes the file:

```
on openCard
  open file "myUpdate"
  read from file "myUpdate" until return
  put It into card field 1
   close file "myUpdate"
end openCard
```

NOTES

If the specified file is already open, an error is generated. The error is stored in the HyperCard function the result. The result is empty if the command is successful. Use the close file command to close files explicitly after you use them. HyperCard automatically closes all open files when an exit to HyperCard statement is executed, when you press Command-period, or when you quit HyperCard.

You must provide the full pathname of the file if it's not at the same directory level as HyperCard. (See "Identifying a Stack" in Chapter 5, "Referring to Objects, Menus, and Windows," for an explanation of pathnames.)

See also the read, write, and close file commands in this chapter and the result function in Chapter 11, "Functions."

Open Printing

SYNTAX

```
open printing [with dialog]
```

DESCRIPTION

The open printing command starts a print job to be ended later by a close printing command.

The settings specified in the Print Stack dialog box are used unless with dialog is specified, in which case the dialog box is displayed and new settings can be chosen.

SCRIPT

The following example handler prints a selection of cards:

```
on printSelection
  put "1,3,8,15,21" into myCards
  open printing with dialog
  repeat with count = 1 to the number of items in myCards
     go card item count of myCards
     print this card
  end repeat
  close printing -- print the cards
end printSelection
```

NOTES

Printing cards with open printing is similar to printing with the Print Stack command in the File menu, except that Print Stack prints all cards in the stack, while open printing prints only the ones you specify with the print card command, described later in this chapter.

You must use some form of the print command and then the close printing command to print and then close a print job begun with open printing. Don't use the print *fileName* with application command while a print job is active.

See also the close printing, open report printing, print, and print card commands in this chapter.

Open Printing 233

Open Report Printing

SYNTAX

```
open report printing [with template templateName] open report printing [with dialog]
```

TemplateName is an expression that yields the name of a previously defined print template.

EXAMPLES

```
open report printing with template "fieldsOnly" open report printing with dialog
```

DESCRIPTION

The open report printing command prepares a report printing job. The print report job is sent to the printer and closed with a close printing command.

SCRIPT

The following script sets the report template and prints the marked cards in the current stack:

```
on PrintLabels

open report printing with template mailing labels

-- choose the "mailing labels" template

print marked cards -- specify which cards to print

close printing -- generate the report & print

end PrintLabels
```

NOTES

Settings previously specified in the Print Report dialog box are used unless the with dialog form is used, in which case the Print Report dialog box is displayed and new settings can be chosen.

If you do not specify a print report template with the with template templateName form or do not use the with dialog form, the settings from the last print report template accessed in the Print Report dialog box are used for the current print job. If no print report template has been used previously for printing and you neither specify a print report template nor use the with dialog form, nothing is printed.

Printing cards with open report printing is similar to printing with the Print Report command in the File menu, except that you can specify the report template to use in the script without using the Print Report dialog box.

You must use some form of the print command and the close printing command to send the job to the printer and then close a print job begun with open report printing. If you start another print job without closing the previous one, HyperCard notifies you that it will close the previous print job before starting the new one. Don't use the print fileName with application command while a print job is active.

When you choose Cancel after opening the Print Report dialog box with open report printing, the function the result is set to Cancel.

See also the close printing, open printing, print, and print card commands in this chapter.

Palette

SYNTAX

palette paletteName[, point]

PaletteName is an expression that yields the name of the palette you wish to invoke. Point is an expression that yields two comma-separated integers that represent the horizontal and vertical coordinates at which the palette should appear. Point is the offset from the upper-left corner of the current card window to the upper-left corner of the palette minus the title bar. Point needs to be in quotation marks or passed in a container.

Palette 235

EXAMPLES

```
palette "Navigator", "50,100"
palette "GeneralPalette", "150,80"
```

DESCRIPTION

The palette command displays the specified custom XCMD palette or the HyperCard palette called Navigator. If you do not specify a *point* parameter, the palette appears at the default location of 10,20 inside the current card coordinate system if it's the first time it's been displayed. After the first time, it appears at its last location if you don't specify a *point* parameter. *Point* is reset to the default location at the beginning of each HyperCard session.

The palette command and associated palette properties have no effect on the Tools palette or Patterns palette.

NOTES

If you specify a palette that is already visible, the palette command moves the palette to the location specified by the *point* parameter.

You can set the location property of a palette window after the palette is displayed with the palette command:

```
set the loc of window "Navigator" to "65,80"
```

You can close a palette that is displayed by using the close command:

```
close window "Navigator"
```

After a palette has been displayed with the palette command, you can hide and show a palette by using the hide and show commands or setting the visible property. The hide and show commands have no effect if the palette hasn't been displayed yet by the palette command. Here are some examples of statements that hide or show palettes:

```
hide window "Navigator" set the visible of window "Navigator" to true show window "GeneralPalette"
```

There is a group of properties that apply only to HyperCard XCMD palettes. The palette properties are buttonCount, commands, hilitedButton, and properties.

You can use the buttonCount property to determine the total number of buttons in a palette.

Commands returns a return-delimited list of the commands or messages associated with the palette's buttons. The commands are listed according to the number of the button they are associated with, that is, first the command associated with button number 1, then the command associated with button number 2, and so forth.

The HilitedButton property determines or sets the number of the currently highlighted button of the specified palette. Setting HilitedButton does not cause the message associated with the button to be sent. For example, the statement

```
set the hilitedButton of window "Navigator" to 3
```

does not send the doMenu "Help" message associated with button 3 of the Navigator palette.

In the case of action palettes, such as Navigator, the value of the hilitedButton property is always -1.

The properties palette property returns a comma-separated list of the names of the properties that apply to the specified palette.

HyperCard palettes consist of two resources: one of type 'PLTE' and one of type 'PICT'. The 'PLTE' resource contains the functional code for the palette, and the 'PICT' resource supplies the palette image. The two resources must have the same name and resource ID number. Because the palette image is a 'PICT' resource, palettes can be in color.

See also the hide and show commands in this chapter.

Palette 237

Picture

SYNTAX

picture [fileName,sourceType,windowStyle,visible,depth,floatingLayer]

FileName is the name of a file or resource of type 'PICT' or 'PNTG' on your Macintosh computer or an expression that yields such a name.

SourceType is resource, file, or clipboard. (The default source type is file.)

WindowStyle is the style of window in which the picture is displayed. The window styles are plain, rect, zoom, roundRect, dialog, document, shadow, and windoid. (The default window type is zoom.)

Visible is a Boolean value: true for visible, false for invisible. This parameter allows you to create an invisible window and set its properties before displaying it with a show command. See the description for more information about the picture window properties.

Depth is the bit depth of the offscreen buffer that the picture command creates. Bit-depth values between 0 and 32 inclusive are supported. The picture command allocates an offscreen buffer of the bit depth you specify (rounded down to a power of 2) or the bit depth of the picture file, whichever is smaller. This allows you to display picture files with a deeper bit depth in less memory, but at the cost of lower resolution. If the value is 0, the picture command doesn't create an offscreen buffer; instead, the 'PICT' file is drawn directly into the window. A value of 0 for depth makes scrolling and zooming slower and prevents dithering from working. If available system memory is extremely low and the bit depth is set to 0, the file is spooled to the display, but picture properties do not work. It does, however, allow you to display pictures in less memory and animated 'PICT' files and format-1 'PICT' files with color.

Floating Layer is a true or false value that signals whether the new picture is in the floating layer, whose elements always appear above elements in the document layer (where cards and scripts reside), or in the document layer, which is always behind minimized and palettes. If you don't specify this parameter, HyperCard selects a layer appropriate to the window style—the floating layer for windoid, shadow, and rect styles; the document layer for plain, zoom, roundRect, dialog, and document styles.

EXAMPLES

```
picture "Clowns",resource,plain,false,0
picture "MyPICT",file,rect
picture "Picnic",clipboard,roundRect
```

DESCRIPTION

The picture command displays color or gray-scale pictures in an external window. The pictures can come from the Clipboard, from PICT or MacPaint files, or from 'PICT' resources in the current stack or any stack in the message-passing hierarchy.

The picture command works best if HyperCard's application memory size in the Get Info dialog box is set to 2 megabytes or more. If the picture cannot be displayed because of insufficient memory, an error describing the condition is returned in the result function.

There is a set of properties that apply to windows created with the picture command. They are rect, globalRect, globalLoc, scroll, zoom, scale, and dithering. The properties are in addition to the standard HyperTalk properties location and visible, which also apply to windows created with the picture command.

The rect and globalRect properties are set just like the rectangle property for other HyperCard windows. The rect property applies to the rectangle of the window created with the picture command in coordinates local to the current card window. The globalRect property applies to the rectangle of the window created with the picture command in global screen coordinates. See the rectangle property in Chapter 12, "Properties."

The rect or globalRect property is specified as four comma-separated integers representing the bounding window rectangle. The first two integers represent the top-left corner position of the window on the screen, and the second two integers represent the bottom-right corner of the window. Four literals can also be used to set the rect and globalRect properties. They are cardScreen (or card), largestScreen (or largest), deepestScreen (or deepest), and mainScreen (or main). These literals display the picture window centered on the same screen as the card window, on the screen with the largest area, on the screen with the greatest bit depth, and the main screen, respectively.

Picture 239

Here are examples that set the rect and globalRect properties:

```
set the rect of window "Clowns" to "120,225,300,480" set the globalRect of window "Clowns" to "largest"
```

The loc (also called location) property applies to the location of the window created with the picture command in coordinates local to the current card window. The globalLoc property applies to the location of the window created with the picture command in global screen coordinates. For more information on the loc (location) and globalLoc properties, see Chapter 12, "Properties."

The loc or globalLoc property specifies a point in the screen's coordinate system where the top-left corner of the window is to be displayed. The point is specified as two integers that represent the horizontal and vertical offsets, respectively. Four literals can also be used to set the loc and globalLoc properties. They are cardScreen (or card), largestScreen (or largest), deepestScreen (or deepest), and mainScreen (or main). These literals display the picture window centered on the same screen as the card window, on the screen with the largest area, on the screen with the greatest bit depth, and the main screen, respectively. Here are examples that set the loc and globalLoc properties:

```
set the loc of window "Flowers" to "65,100" set the globalLoc of window "Clowns" to "card"
```

The scroll property for windows created with the picture command is like the scroll property for cards in card windows. See the scroll property in Chapter 12, "Properties." Scroll is specified as two comma-separated integers representing the horizontal and vertical offsets, in the picture's coordinate system, to be displayed at the top-left corner of the window. Here is an example that sets the scroll property for a window:

```
set the scroll of window "Water" to "45,60"
```

The dithering property is a Boolean value: true for dithering, false for no dithering. (The default for the dithering property is false.) Here is an example that sets the dithering property for a window:

```
set the dithering of window "Garlic" to true
```

The scale property scales a picture in a window created with the picture command. The value for scale is an integer between -5 and 5, inclusive. Negative integers scale down the picture, and positive integers scale up the picture. Scaling is done using 2 raised to the scale power. For example, if the scale is -2, the picture is scaled to 25 percent. The default value for scale is 0. Here is an example that sets the scale property for a picture in a window:

set the scale of window "Summer fun" to 4

The zoom property applies to windows created with a window style that supports a zoom box. It zooms a window in or out. The possible values for zoom are in and out. Here is an example that sets the zoom property for a window:

set the zoom of window "Alligators" to out

NOTES

If you do not provide a valid name for the *fileName* parameter, a standard dialog box for opening files is displayed from which you can choose a 'PICT' or 'PNTG' file. The one exception to this is when you specify clipboard for the *sourceType* parameter. In that case any name can be used. If you cancel the standard file dialog box, HyperCard sets the result to cancel.

If the *sourceType* parameter is a resource and the filename specified in the *fileName* parameter can't be found, the picture command converts the *fileName* parameter to a number and looks for a 'PICT' resource with the specified number as its ID.

If you do not set the rect or globalRect property, HyperCard displays the picture in a window that is the same size, or as close to the same size as possible, as the original picture.

If you do not set the scroll property, the picture is displayed with its 0,0 coordinate at the top-left corner of the external window.

The new 32-bit Color QuickDraw is fully supported. You can display 16-, 24-, and 32-bit images with the picture command. The dithering property is ignored if 32-bit Color QuickDraw isn't installed in the System Folder.

Picture 241

The rect and shadow window types are created behind all the HyperCard windows. This allows you to create picture windows that appear to pop up above the card window.

You can close windows created with the picture command by clicking the close box or with the close command as follows:

```
close window "fileName"
```

FileName is the filename specified in the *fileName* parameter for the picture command. It is also the name displayed in the title bar of the window.

If an error occurs when creating a window, the picture command sets the result to an error message that begins with "Couldn't display picture".

If the picture file is displayed successfully, the result is empty.

When you click a window created with the picture command, two system messages are sent. When the mouse button is down, a mouseDownInPicture message is sent. When the mouse button is released, a mouseUpInPicture message is sent. Each message is sent with two parameters: the name of the window and the point within the picture's default (not scaled) local coordinates at which the mouse button was clicked. You can place handlers for these messages anywhere in the message-passing hierarchy or in the stack script of the stack that invokes the picture command. You can use these messages to simulate button actions, card flipping, or anything else that you would use mouseUp and mouseDown system messages for.

The following handler checks for a mouseDownInPicture message sent by a window created by the picture command and puts its name and the location where the mouse button was clicked into the Message box:

```
on mouseDownInPicture wName,cLoc

put "You clicked window" &&quote& wName &quote&& ¬

"at location" && cLoc

end mouseDownInPicture
```

See also the close command in this chapter, and the system messages mouseUpInWindow, mouseDownInWindow, openPicture, and closePicture in Chapter 8, "System Messages."

Play

SYNTAX

```
play sound [tempo tempo] [notes]
play stop
```

Sound is an expression that yields the name of a digitized sound (boing, flute, and harpsichord are included with HyperCard). Tempo is an expression that yields the speed at which the sound plays, and notes is an expression that yields a list of one or more notes representing the pitch at which the sound plays and the duration of the notes. Digitized sounds are of the Macintosh sound resource formats 1 and 2, which are described in Inside Macintosh: Sound.

EXAMPLES

```
play "boing" tempo 200 "c4e c dq c f eh" -- Happy Birthday play "harpsichord" "ch d e f g a b c5w"
```

DESCRIPTION

The play command makes the Macintosh computer play notes through its speaker (or through the audio jack if it's plugged in). You can write a song by specifying a series of notes after the play command. The play stop form stops the current sound immediately; otherwise, it plays until it's done and stops by itself. In most cases, HyperCard continues to execute handlers and perform other actions while a sound plays. In the event of a low-memory situation, such as when playing a large sound while a large Home stack or several other stacks are in use and HyperCard is set to the default memory allocations, HyperCard may suspend other actions until the sound is finished playing. Increasing HyperCard's memory allocation should alleviate this problem.

Digitized sounds are of the Macintosh sound resource formats 1 and 2, which are described in *Inside Macintosh: Sound*. The resources must exist in a stack in the hierarchy or in HyperCard application. If the sound can't be found or can't be loaded into memory, the result gets set to "Couldn't load sound". If the sound isn't played because the volume is set to 0 (in the Sound control

Play 243

panel), HyperCard is running in the background, or an XCMD is using HyperCard's sound channel, the result gets "Sound is off".

SCRIPT

The following example handler goes to each card in a stack and synchronizes playing the specified notes with each card change:

```
on tour

repeat the number of cards

play "harpsichord" tempo 200 "ce4 fe ae c5q ae4 cq5"

go next card

wait until the sound is "done"

end repeat

end tour
```

NOTES

Tempo is a number specifying the speed at which the group of notes is played (100 is a medium tempo; higher numbers are faster). The sound and tempo are specified once for each play command.

The notes are specified in the following form:

noteName accidental octave duration

NoteName is the name of the note played (A through G); *accidental* is # or b, specifying sharp or flat, respectively; *octave* is a number specifying the pitch of the scale (4 is the "middle C" scale); and *duration* specifies the relative time value of the note played:

W	whole note	s	16th note
h	half note	t	32nd note
q	quarter note	х	64th note
е	eighth note		

You can use a period (.) or numeral 3 following *duration* to specify a dotted or triplet note, respectively.

Octave and duration may be changed for each note played; if they are not changed, subsequent notes are in the same octave and have the same duration as the previous note.

The 254-character limit on note strings that existed in earlier versions of HyperCard no longer applies.

See also the sound function in Chapter 11, "Functions."

Pop Card

SYNTAX

pop card [preposition [chunk of] container]

Preposition is into, before, or after; *chunk* is a chunk expression, and *container* is an expression that identifies a container.

EXAMPLE

pop card into field 3 of card WhereIbeen

DESCRIPTION

The pop card command retrieves the identification (full ID and stack pathname) of a card previously saved with the push card command. If you don't provide a destination for the identification, you go directly to the card whose address is popped.

Pop Card 245

SCRIPT

The following example handler pushes whatever card you're on, goes to another stack, gets the value of a field property, then returns to the original card:

```
on getTheFont
  global myStack,theFont
  push card
  go myStack
  put textFont of field 1 into theFont
  pop card -- goes to the card formerly pushed
end getTheFont
```

NOTES

After the card has been popped, its identification is removed from the memory stack—it can't be popped again. If a container is given, however, the card's identification is put into the container, but you don't go anywhere.

See also the push command, later in this chapter.

Print

SYNTAX

```
print fileName with application
print field
print expression
print button
```

FileName is an expression that yields the name of any document on your Macintosh computer, and *application* is an expression that yields the name of the application to which it belongs (or with which it is compatible). *Field* is an expression that yields any field descriptor. *Expression* is an arbitrary expression or container.

EXAMPLES

```
print "memo" with "MacWrite"
print field 1 with field "Program"
print "HD:MY DOCS:letter" with "HD:Applications:MacWrite"
print bkgnd field 1
```

DESCRIPTION

The print command prints the specified file, field, or expression.

The print *fileName* with *application* form of the print command suspends HyperCard, launches the named application, opens the named document, prints the document, then resumes running HyperCard. The specified application must support printing.

The print *field* form of the print command prints the specified field using the current font, size, style, and line height of that field.

The print *expression* form prints any arbitrary HyperTalk expression. Expressions are printed using global print properties, such as printTextFont.

SCRIPT

The following example handler queries the user for the name of a document to print and an application with which to print it:

```
on mouseUp
   ask "Print what document?" with empty
   if It is not empty then
      put It into doc
      ask "Use what application?" with empty
      if It is not empty then print doc with It
   end if
end mouseUp
```

Print 247

NOTES

If the document or application you specify isn't at the top level of the file hierarchy (the "disk" level), then the path to it must be specified on the appropriate Search Path card of the Home stack. Alternatively, you can specify the full pathname with the print command.

Error messages go into the container the result of the source program when the print command fails.

Don't use the print command while a print job started with the open printing command is active.

See also the print card command described in this chapter.

Print Card

SYNTAX

```
print card [from point1 to point2]
print marked cards
print all cards
print number cards
```

Card is an expression that yields a card descriptor or the word card, which refers to the current card.

Point1 is an expression that yields two comma-separated numbers representing the upper-left corner of a rectangular region you want to print on the specified card. *Point2* is an expression that yields two comma-separated numbers representing the lower-right corner of a rectangular region you want to print on the specified card. *Number* is an expression that yields an integer or the word all.

EXAMPLES

```
print card from 0,123 to 345,512
print last card
print card id 3011
print all cards
```

```
print marked cards
print howMany cards -- howMany contains an integer
print card
```

DESCRIPTION

The print card command makes HyperCard print the specified card. It differs from the Print Card command (Command-P) in the File menu in that the File menu command prints at full size, while print card prints at the size specified in the Print Stack dialog box. The print number cards form prints the number of cards specified by number, beginning with the current card. The print marked cards form prints a group of marked cards. The print card form makes HyperCard go to the specified card, print it, and return to the current card.

SCRIPT

The following example handler queries the user for a number of cards to print whenever Print Card is chosen from the File menu:

```
on doMenu var

if var is "print card" then

ask "Print how many cards?" with one
open printing

if It is a number then print It cards
close printing
else pass doMenu -- make sure other menu choices
-- continue to work
end doMenu
```

NOTES

You don't need to use the open printing command before using the print card command. If nothing is printing, the print card command prints the specified card or cards immediately; if an open printing command is in effect, no cards are printed until a page is full (depending on how many cards per page are specified in the printing dialog box) or the close printing command is given.

Print Card 249

Chapter 5, "Referring to Objects, Menus, and Windows," defines card descriptors. See also the marked property in Chapter 12, "Properties," and the close printing, mark, open printing, and open report printing commands described earlier in this chapter.

Push

SYNTAX

```
push card
push card [of stack stackName]
push background [of stack stackName]
push stack
```

Card is an expression that yields the descriptor of any card. *StackName* is the name of an open stack.

EXAMPLES

```
push recent card
push first card
push card
```

DESCRIPTION

The push command saves the identification of the specified card or stack in a LIFO (last-in, first-out) memory stack (an area of memory, not a HyperCard stack).

SCRIPT

The following example handler saves the current card, goes to a random card, then returns to the original card:

```
on nonSense
  push card -- save current card
  go any card
  pop card -- restore current card
end nonSense
```

NOTES

The card identification can be retrieved later with the pop card command (usually so that you can go directly back to the pushed card). The card identification that's saved is the full card ID and stack pathname. HyperCard holds the IDs of up to 20 cards.

Card descriptors are described in Chapter 5, "Referring to Objects, Menus, and Windows."

See also the pop card command, earlier in this chapter.

Put

SYNTAX

```
put expression [preposition [chunk of] container]
put itemName preposition [menuItem of] menu ¬
  [with menuMsg message]
```

Expression is an expression that yields a text string or number; *preposition* is into, before, or after; *chunk* is a chunk expression; and *container* is an expression that identifies a container.

ItemName is an expression that yields a single menu item name or a list of comma-separated or return-delimited names to be added to the specified menu. MenuItem is an expression that yields the word menuItem followed by either the name or number (integer or ordinal number) of a standard HyperCard menu item or a user-defined menu item in the specified menu. Menu is an expression that yields the word menu followed by either the name or number (integer or ordinal number) of a standard HyperCard menu or a user-defined menu in the menu bar. Message is an expression that yields a single message or a list of comma-separated or return-delimited menu messages to be sent when a specified menu item is chosen. The menu messages in the list correspond one to one for each menu item.

Put 251

EXAMPLES

```
put "Hello" into field 1
put "go " before field "WhereTo"
put empty into It
put It -- puts contents of It into Msg
put "Tom" into first word of field "Name"
put "." after first character of last word of field 3
put fld 2 + fld 3 into fld 4 -- adds numbers in fields
put the date into varName
put "Paths" after menuItem "Preferences" of menu "Home"
put "Paths" after first menuItem of menu "Home"
put "Paths" after first menuItem of menu "Home" with ¬
menuMsg "go card 4"
put "Vanilla, Chocolate, Strawberry" into menu ¬
"Flavors" with menuMsg "put Yummy, put Tastie, put ¬
BerryGood"
```

DESCRIPTION

The first form of the put command causes HyperCard to evaluate *expression* and copy the result into *container*. You use the second form of the put command to add menu items to an existing menu. Optionally, you can specify a message to be sent when the menu item it belongs to is chosen.

User-defined items with the same name as standard HyperCard menu items inherit the standard behavior of the HyperCard menu item. For example, if you put an item called Background into a menu called Special, choosing it has the same effect as the standard Background menu item from the Edit menu unless you assign a custom menu message or intercept the doMenu message.

HyperCard does not automatically check, uncheck, enable, or disable user-defined menu items as it does for its own standard menu items. It is your responsibility to make sure user-defined menu items act according to the standard Macintosh user interface. See the commands and properties listed in the notes section for more information about controlling the behavior of menu items.

SCRIPT

The following example handler initializes three global variables when the stack it's in is opened:

```
on openStack
global var1,var2,var3
put 0 into var1
put empty into var2
put empty into var3
end openStack
```

NOTES

If you don't specify the destination container, the value is copied into the Message box. (HyperCard shows the Message box if it's hidden.) If you specify a container that HyperCard doesn't recognize, it creates a new local variable of that name and puts the value into the variable.

For the put *expression* form, using into replaces the contents of the container, before places the source value at the beginning of the previous contents, and after appends the source value to the end of the previous contents.

You can use the put command to put text into buttons. The lines of the text of a pop-up button become the menu items of the pop-up menu that appears when the user clicks the button. Here's an example:

```
set style of button 1 to popup
put menu font into button 1
```

If *expression* is a container holding an arithmetic expression, the expression is not evaluated but is copied literally into the destination. Use the value function with the container name to have HyperCard evaluate its contents.

You can delete the contents of a container by putting the constant empty or "" into it (but this doesn't delete the container). You can specify a chunk expression to insert, replace, or delete a portion of the contents.

Always use the form put *itemName* before | after *menuItem* of menu to add a menu item to a menu that already has menu items in it. If you use the form put *menuItem* into menu, you replace the contents of the menu, deleting any other menu items already in the menu.

Put 253

Because menus are like containers, you can get a list of the current menu items in a menu by using the term menu as an expression. For example, the following statement puts a return-delimited list of all the menu items in the Home menu into card field "MenuItemList":

```
put menu "Home" into card field "MenuItemList"
```

You can get a specified menu item name with a statement like

```
put menuItem 3 of menu "Home"
```

The maximum number of menu items in a menu is 64.

See also the checkMark, commandChar, enabled, menuMessage, name, and textStyle properties in Chapter 12, "Properties." See also the create menu, delete, disable, and enable commands in this chapter.

Read

SYNTAX

```
read from file fileName [at [-]start]

for numberOfChars | until char | constant
```

FileName is an expression yielding the name of any file on your Macintosh; *start* is an integer expression identifying the position in the file where reading starts: a positive number indicates the character offset from the beginning of the file, and a negative number indicates the character offset from the end of the file.

NumberOfChars is an integer expression for the total number of characters to be read.

Char is an expression identifying the last ASCII character to be read (upperand lowercase *are* distinguished).

Constant is one of the following: end, eof, formFeed, quote, return, space, or tab.

EXAMPLES

DESCRIPTION

The read command reads from the specified file, which must be opened already with the open file command, into the local variable It. Reading starts either at the position specified or, if no start is specified, from the character following the last point read with a previously executed read command. Reading continues until the specified character or constant is reached or until the specified number of characters has been read.

SCRIPT

The following example handler opens a file, reads to the end of the file while placing its contents into a global variable, and closes the file:

```
on mouseUp
global fileName, textHolder
open file fileName
read from file fileName until eof
put It into textHolder
close file fileName
end mouseUp
```

NOTE

If you specify more than one character with the read until form, HyperCard stops reading when it finds the first character in the file.

Read 255

Tab characters

HyperCard reads tab characters from a file into It. When text containing tabs is put into a field, the tabs are displayed as spaces. The tabs are not removed when the text is altered; however, if null characters (ASCII 0) are read in, HyperCard changes them to spaces (ASCII 32).

Use the close file command to close files explicitly after you use them. HyperCard automatically closes all open files when an exit to HyperCard statement is executed, when you press Command-period, or when you quit HyperCard.

You must provide the full pathname of the file if it's not at the same directory level as HyperCard. (See "Identifying a Stack" in Chapter 5 for an explanation of pathnames.)

If an error is generated while using the read command, an error dialog appears. See also the close file, open file, and write commands in this chapter, and the result function in Chapter 11, "Functions."

Reply

SYNTAX

```
reply expression [with keyword aeKeyword] reply error expression
```

Expression yields a HyperTalk statement. *AeKeyword* is an Apple event keyword.

EXAMPLES

```
reply "Hello there, nice to hear from you" reply error "Error in the remote stack"
```

DESCRIPTION

You use the reply command to answer an incoming Apple event. If you don't specify a keyword for the reply parameter, then the parameter becomes the direct parameter of the reply.

You can use the form reply *expression* only to reply to a send command from another running copy of HyperCard. This form sets the result in the sending program to *expression*, where *expression* is any string or container.

You use the reply error *expression* form to reply to any Apple event. This form signals an error to the sending program.

SCRIPT

The following script handles Apple events of class 'WILD' and type 'defn' by searching for a string in a background field named "Glossary Entry" and returning the contents of a background field named "Definition."

```
on appleEvent eventClass, eventID, sender
if eventClass is "WILD" and eventID is "defn"
request appleEvent data
find it in field "Glossary Entry"
if the result is empty -- find is successful
then reply field "Definition"
else reply error "Not found"
else pass appleEvent
end appleEvent
```

NOTES

The reply command sets the result to No current Apple event when there is no current Apple event to handle.

Reply 257

Request

SYNTAX

```
request expression from program

request expression of from program id programID

request expression of from this program

request appleEvent data with keyword aeKeyword

request appleEvent data class id sender return id sender id
```

Expression is an expression that can be evaluated by the target program. Program yields a valid program pathname in this form: zone:targetComputer: targetProgram, where zone is a set of Macintosh computers on a local network, targetComputer is the name of the target computer, and targetProgram is the name of the target program. ProgramID is an application's signature (4-character string). AeKeyword is an Apple event keyword.

EXAMPLES

```
request "the number of cards" from ¬
   program "KZone:PMac:HyperCard"
request "the name of this stack" of program "HyperCard"
request "{target}" from program "MPW Shell"
```

DESCRIPTION

The request command sends an "evaluate expression" Apple event from HyperCard to another application running remotely or on the same machine. You can use this command to send an expression to any program that understands the standard 'eval' Apple event. If the target program is another copy of HyperCard, the expression you use as your request can be a built-in HyperTalk function or property (such as the time or the long name of this stack) or a user-defined function call (such as day()). When the target program executes the statement, the result of the request (the value of the expression) goes into the local variable It.

The request appleEvent data with keyword form puts the parameter or attribute with the specified keyword into the local variable It. For example,

you can obtain a parameter of keyword errs, the standard Apple event keyword for an error string, as follows:

```
request appleEvent data with keyword "errs"
put it into errorString
```

If there is no attribute or parameter with the keyword you specify, HyperCard sets the result to Not found.

If you don't supply a keyword, HyperCard assumes you're requesting the direct object of the Apple event, which is defined by the Apple event manager as the parameter with keyword "----". The other request appleEvent forms support special cases for important attributes of Apple events.

SCRIPT

The following handler shows how the request command can get information from another HyperCard program:

```
on getStackName -- Card handler in source stack request "the long name of this stack" ¬ from program HildaPath if the result is empty then answer It else answer the result end getStackName
```

NOTES

The parameter *zone* can be omitted from the program pathname when the target computer is in the same zone as the source computer.

The signature of an application program is a four-character field stored in its signature resource, which the application assigns to the creator field of its documents. For example, HyperCard's signature is 'WILD'.

When the reply to the 'eval' Apple event sent by HyperCard doesn't contain a direct parameter, the request command puts empty into the local variable It. If the Apple event server encounters an error when evaluating the expression and returns an error message in the reply event, the request command

Request 259

puts that message into the result. The following error messages go into the result when the request command fails:

Condition	the result contents			
Error while handling a 'misc' 'eval' event	Can't take the value of that expression			
Information returned is not recognized by HyperCard as text	Unknown data type			
No attribute or parameter with the specified keyword	Not found			
System software prior to version 7.0	Not supported by this version of the system			
Target program didn't handle event	Not handled by target program			
Target program returned error number in reply, or AESend returned some other error	Got error <errornum> when sending Apple event</errornum>			
Target program returned error string in reply	<errorstring></errorstring>			
Target program timed out	Timeout			
User canceled "Link to program" dialog	Cancel			
See also the send keyword.				

Reset Menubar

SYNTAX

reset menubar

DESCRIPTION

The reset menubar command reinstates the default HyperCard menus and removes any custom menus created with the create command and custom menu items put into standard HyperCard menus with the put command.

NOTES

If you are creating a stack to be used by others, use this command with some restraint, because it removes all custom menus and menu items, not just those you created for your stack.

When your stack is closed, remove any custom menus or menu items you created by deleting them. Use a closeStack, suspend, or suspendStack system message handler to remove your custom menus when your stack is closed or is no longer the current stack, and an openStack, resume, or resumeStack system message handler to reinstate your custom menus when your stack is opened or resumed.

See also the create menu and put commands, earlier in this chapter, and Chapter 8, "System Messages."

Reset Paint

SYNTAX

reset paint

DESCRIPTION

The reset paint command reinstates the default values of all the painting properties. The painting properties and their default values are

brush	8	pattern	12
centered	false	polySides	4
filled	false	textAlign	left
grid	false	textFont	geneva
lineSize	1	textHeight	16
multiple	false	textSize	12
multiSpace	1	textStyle	plain

Reset Paint 261

CHAPTER 10

Commands

NOTE

The painting properties are described in Chapter 12, "Properties."

Reset Printing

SYNTAX

reset printing

DESCRIPTION

The reset printing command reinstates the default values of all the printing properties. The printing properties and their default values are

printMargins 0,0,0,0
printTextAlign left
printTextFont Geneva
printTextHeight 13
printTextSize 10
printTextStyle Plain

NOTE

The printing properties are described in Chapter 12, "Properties."

ReturnInField

SYNTAX

returnInField

DESCRIPTION

The returnInField command enters a return character into a field that is open for text editing.

NOTES

The returnInField message, which invokes the returnInField command if it reaches HyperCard, is normally generated by pressing the Return key on the keyboard, but you can also send it from the Message box or execute it as a line in a script.

See also the returnInField system message in Table 8-3.

ReturnKey

SYNTAX

returnKey

DESCRIPTION

The returnKey command sends a statement typed into the Message box to the current card.

NOTES

The returnKey message, which invokes the returnKey command if it reaches HyperCard, is normally generated by pressing the Return key on the keyboard, but you can also send it from the Message box or execute it as a line in a script.

See also the returnKey system message in Table 8-3.

ReturnKey 263

Save

SYNTAX

```
save stack stackName as [stack] fileName
save [this] stack as [stack] fileName
```

StackName is an expression that yields a valid stack name. *FileName* is an expression that yields a valid Macintosh filename.

EXAMPLE

```
save stack "Pottery" as "NewPottery"
```

DESCRIPTION

The save command saves a copy of the specified stack with the given filename. The stack is saved without a dialog box. Both *stackName* and *fileName* must be enclosed in quotation marks.

NOTE

If the save command produces an error, the error is stored in the HyperCard function the result.

Select

SYNTAX

```
select object
select [preposition] chunk of field
select [preposition] text of field
select line number [to number] of field
select line number of button
select empty
```

Object is an expression that yields the descriptor of a button or field, or me, or target; preposition is before or after; chunk is a chunk expression; field is the descriptor of a field; number is an expression that evaluates to an integer; and button is the descriptor of a pop-up button.

(Button and field descriptors and the special descriptor me are explained in Chapter 5, "Referring to Objects, Menus, and Windows." The special descriptor target is explained in Chapter 4, "Handling Messages.")

EXAMPLES

```
select button 1
select before char 1 of field 2
select after text of field 2
select char 1 to 5 of card field "name"
select line 1 to 2 of field 1
select line 4 of button "My Pop-up"
```

DESCRIPTION

The select command creates a selection or highlights lines in a list field or pop-up button. The select *object* form chooses the appropriate tool and selects the object specified as though you had chosen the tool and clicked the object manually with the mouse. The forms specifying a field select text in the specified field and open the field for editing, unless the field is a list field. Before and after can be used to place the insertion point relative to the specified text or chunk of text. Using a chunk expression without a preposition selects the entire chunk, highlighting the characters in the chunk.

If the specified field is a list field (that is, its autoSelect and lockText properties are both true), you can use the select line form to select one or more whole lines, which then appear highlighted. You can also specify a pop-up button with the select line form to select one line from its contents, which then appears within the button rectangle.

The select empty form deselects highlighted text or removes the insertion point from a non-list field. It does not affect highlighted text in a list field or pop-up button.

Select 265

NOTES

For button families, the selectedButton function returns the descriptor of the button that is currently highlighted—selected by the user from the choices the button family represents. To set the selectedButton in a family from a script, set its hilite property to true.

You can select only the parts on the current card, so using select button 1 of next card won't work. You do not get an error message when you try to do this.

See also the selectedButton, selectedChunk, selectedField, selectedLine, and selectedText functions in Chapter 11, "Functions."

Set

SYNTAX

set [the] property [of element] to value

Property is a characteristic of a HyperCard object, menu, menu item, window, or chunk of a field. *Element* is an expression that yields the descriptor of an object, menu, menu item, window, or chunk of a field. *Value* is an expression that yields a valid setting for the particular property.

EXAMPLES

```
set name of field 1 to "Soccer"

set location of button "newButton" to the mouseLoc

set the visible of field 1 to "false" -- hide the field

set userLevel to 5 -- scripting

set the cmdChar of menuItem "Home Cards" of ¬

menu "Home" to 5

set loc of window "ask" to 10,10

set the textStyle of word 1 to 2 of field "Name" to bold
```

DESCRIPTION

The set command changes the state of a specified property. If the element to which the property belongs is not specified, the property must be a global property.

Some properties cannot be changed with the set command. These exceptions are pointed out in the property descriptions in Chapter 12, "Properties."

SCRIPT

The following example handler automatically draws a circle on the current card:

```
on mouseUp
    choose oval tool
    set linesize to 2
    set centered to true
    set dragspeed to 75 -- speed of expansion
    drag from 155,70 to 285,200
    choose browse tool
end mouseUp
```

NOTES

The properties of objects depend on the type of object. Generally, they are the characteristics shown in the Info dialog boxes under the Objects menu. All of the HyperCard properties are described in detail in Chapter 12, "Properties."

Among the commands that set properties are: disable, enable, hide, mark, reset menubar, reset printing, show, and unmark, which are described in this chapter.

Set 267

Show

SYNTAX

```
show background picture
show card picture
show groups
show menuBar
show object [at point]
show picture of background
show picture of card
show titlebar
show window stackName [at point]
show window windowName [at point]
```

Object yields one of the following objects:

a valid button descriptor in the current stack
a valid field descriptor in the current stack
message [box] or message [window] or window "message"
pattern window or window "patterns" (the Patterns palette)
tool window or window "tools" (the Tools palette)
window "navigator" (the Navigator palette)
message watcher or window "message watcher"
variable watcher or window "variable watcher"
card window

Point is an expression yielding two integers separated by commas representing the horizontal and vertical pixel offsets, respectively, on the screen. *Card* yields the descriptor of a card in the current stack. *Background* yields the descriptor of a background in the current stack. *WindowName* is the name of a window created with the picture command or a custom external window. *StackName* is the name of an open stack.

EXAMPLES

```
show msg at 50,300
show tool window
show field "Names" at 1,1
show groups
show Message Watcher
```

DESCRIPTION

The show command displays a specified window or object at a specified location on the screen. If positioning offsets aren't given, the window or object is displayed at its previous location.

The picture form of the show command displays a graphic bitmap on the card or background that has been hidden with the hide command. The show groups form of the show command makes a gray 2-pixel underline below group-style text. The show groups command affects all group-style text in all fields globally.

The show titlebar form of the show command shows the stack window title bar, if it was hidden. If it wasn't hidden, it has no effect.

SCRIPT

The following example handler displays the Tools palette, the Patterns palette, and the Message box at their default locations when HyperCard first starts running:

```
on startUp
show tool window
show pattern window
show msg
end startUp
```

NOTES

The show command sets the visible and, optionally, location properties of the window or object.

Show 269

If the menu bar is hidden and the screen is locked, show menubar has no effect. See the lock and unlock commands in this chapter and the lockScreen property in Chapter 12, "Properties."

On Macintosh Plus and Macintosh SE screens, visible horizontal offsets range from 0 to 511, and visible vertical offsets range from 0 to 341. Members of the modular Macintosh family have variable visible offsets depending on the monitor currently in use.

Message can be abbreviated msg. Background can be abbreviated bkgnd or bg. Button can be abbreviated btn. Field can be abbreviated fld. Card can be abbreviated cd.

For buttons and fields of the current card, *point* specifies the distance from the top-left corner of the card window to the center of the button or field.

Card window refers to the current card window; for it and all stack windows, point specifies the distance from the top-left corner of the screen to the top-left corner of the card window, disregarding the title bar at the top of the window. For the other windows, point specifies the distance from the top-left corner of the card window to the top-left corner of the other window, disregarding the drag bar at the top of the window.

The default location for the Message Watcher window is the lower-left corner of the screen. The default location for the Variable Watcher is the lower-right corner of the screen.

The menu bar always shows at the top of the screen.

You can use the show and hide commands with the Navigator window only after it has been invoked with the palette command.

Valid window names for the show command are any of the windows returned by the windows function.

When you change a card window's location property with the show card window at *location* form, the system message moveWindow is sent. The moveWindow message is also sent when you drag the window to a new location or zoom it in or out with the zoom box, causing the location property to change.

See also the hide, palette, and set commands in this chapter; the show system message in Table 8-3; the windows function in Chapter 11, "Functions"; and the location and visible properties in Chapter 12, "Properties."

Show Cards

SYNTAX

```
show [number] cards
show all cards
show marked cards
```

Number is an expression yielding an integer.

EXAMPLES

```
show all cards
show ten cards
show 26 cards
show marked cards
show howMany cards -- howMany contains an integer
show cards
```

DESCRIPTION

The show cards command displays the specified cards in the current stack in turn, beginning with the next card or, for the show marked cards form, the first marked card. If no parameter is used, show cards displays all cards in the stack continuously.

SCRIPT

The following example handler "prewarms" the stack when you open it, so that going to cards in the stack subsequently will be faster, by caching the cards in RAM:

```
on openStack
   set lockScreen to true
   show all cards
   set lockScreen to false
end openStack
```

Show Cards 271

NOTES

The show all cards form shows all cards in the stack. HyperCard doesn't send the openCard system message when a card is displayed by show cards, nor do visual effects occur. After the cards are shown, the last one shown (where you began in the case of show all cards) is the current card.

See also the marked property in Chapter 12, "Properties."

Sort

SYNTAX

```
sort [sortDirection] [sortStyle] by sortKey
sort [this] stack [sortDirection] [sortStyle] by sortKey
sort [marked] cards [of this stack] [sortDirection] ¬
    [sortStyle] by sortKey
sort background [sortDirection] [sortStyle] by sortKey
sort [marked] cards of background [sortDirection] ¬
    [sortStyle] by sortKey
sort [lines|items of] container [sortDirection] ¬
    [sortStyle] [by sortKey]
```

Container is a field expression, variable, or the variable each.

SortDirection can be either ascending or descending; the default value is ascending.

SortStyle can be text, numeric, dateTime, or international; the default is text.

SortKey is any expression.

Background is an expression that yields a background descriptor.

EXAMPLES

```
sort lines of field 1 by last word of each sort items of field 5 descending numeric by word 2 of each sort numeric by second word of field 1 sort descending text by last word of field "Names" sort cards of this stack by field "Names" sort marked cards descending numeric by bg field 2 sort marked cards of background "Notes" by bg field 2 sort this background by field 1 sort lines of field 3 ascending sort items of field 3 dateTime sort field 3 sort it numeric
```

DESCRIPTION

The sort command can sort and order

- the lines or items in a container; if you do not specify lines or items when sorting a container, the default is lines (if you choose items, remember that HyperCard recognizes an item by its comma delimiter)
- all the cards or marked cards in a single background or a stack

You can customize the sort command by

- setting sortDirection to ascending or descending; it is ascending by default
- setting sortStyle to text, numeric, dateTime, or international; the default is text
- setting *sortKey* to any expression; for example, you could sort the lines in a field by the last word in each line by setting *sortKey* to

the last word of each

Sort 273

SCRIPT

The following example handler shuffles the cards in a stack randomly when the user goes to it from another stack:

```
on openStack
   sort numeric by random(the number of cards)
end openStack
```

NOTE

The international sort style assures correct sorting of non-English text containing diacritical marks and special characters, according to the international resources in your System file, your version of HyperCard, the Home stack, and the current stack.

The dateTime style sorts the stack using one of the forms of date or time (shown with the convert command, in this chapter), with earliest placed first in the ascending direction. The dateTime style also works correctly with non-English forms of date and time that have been modified by international resources in the System file.

See also the marked property in Chapter 12, "Properties," and the mark command in this chapter.

Start Using

SYNTAX

start using stack stackName

StackName is an expression that yields a stack name.

EXAMPLE

start using stack "HD80:myStack"

DESCRIPTION

The start using command inserts the specified stack between the current stack and the Home stack in the message-passing hierarchy. Each successive stack that is added to the message-passing hierarchy is inserted just after the current stack. If a stack that is already in use is "used" again, its previous place in the message-passing hierarchy changes to the place just after the current stack.

The start using command allows you to use the stack script and resources of any other HyperCard stack, not just the Home stack. Once the start using statement is executed, the handlers in the script of the specified stack and the XCMDs and other resources in its resource fork are available for use.

SCRIPT

To change the message-passing hierarchy when opening a stack, simply place a start using statement in the openStack handler:

```
on openStack
    start using stack "myStack:ScriptStack"
end openStack
```

To remove the stack from the hierarchy when closing a stack, place a stop using statement in the closeStack handler:

```
on closeStack
   stop using stack "myStack:ScriptStack"
end closeStack
```

NOTE

See also the description of the message-passing hierarchy in Chapter 4, "Handling Messages," and the next command, stop using.

Start Using 275

Stop Using

SYNTAX

stop using stack stackName

StackName is an expression that yields a stack name.

EXAMPLE

stop using stack "HD80:myStack"

DESCRIPTION

The stop using command removes the specified stack from the messagepassing hierarchy.

SCRIPT

To remove the stack from the message-passing hierarchy when closing a stack, place a stop using statement in the closeStack handler.

```
on closeStack
   stop using stack "myStack:ScriptStack"
end closeStack
```

NOTE

See also the description of the message-passing hierarchy in Chapter 4, "Handling Messages," and the previous command, start using.

Subtract

SYNTAX

subtract number from [chunk of] container

Number is an expression that yields a number. *Chunk* is an expression that yields a chunk of a container. *Container* is an expression that identifies a container, such as a field, the Message box, the selection, or a variable.

EXAMPLES

```
subtract 2 from It
subtract field 1 from field 2
```

DESCRIPTION

The subtract command subtracts the value of *number* from the value of [chunk of] container, leaving the result in [chunk of] container. The value previously in container must be a number; it is replaced with the new value.

TabKey

SYNTAX

tabKey

DESCRIPTION

The tabKey command opens the first unlocked field on the current background or card (placing the text insertion point in the field) and selecting its entire contents. If a field is already open, tabKey closes it and opens the next field, selecting its contents.

Subtract 277

CHAPTER 10

Commands

SCRIPT

The following example handler sets the insertion point in the first field so that the user can type something when the card is opened:

```
on openCard tabKey end openCard
```

NOTES

The tabKey system message, which invokes the tabKey command if it reaches HyperCard, is normally generated by pressing the Tab key on the keyboard. But you can also send it from the Message box or execute it as a line in a script.

The tabKey command opens fields in the following order: from the lowest number to the highest, through the background fields first, then through the card fields.

See also the tabKey system message in Table 8-3.

Type

SYNTAX

```
type text [with commandKey]
```

Text is an expression that yields a text string.

CommandKey can be abbreviated cmdKey.

EXAMPLES

```
type "Now is the time for all good persons."
type "p" with commandKey -- print card
```

DESCRIPTION

The type command enters the value of *text* at the text insertion point, as though you had typed it manually. If the with commandKey form is used, no text appears at the insertion point; rather, the action defined for the Command-key combination is carried out.

SCRIPT

The following example handler chooses the Browse tool, clicks the center of the specified field, and types a literal string:

```
on autoType
   choose browse tool
   click at the loc of field "whereToType"
   type "Automatic writing apppears before your eyes..."
end autoType
```

NOTES

The text insertion point is placed by clicking an unlocked field with the Browse tool or by sending the tabKey message. Manipulating the text insertion point is described in the *HyperCard Reference*.

Paint text can be typed at the text insertion point on a card or background with the Paint Text tool selected.

Unlock

SYNTAX

```
unlock screen with [visual [effect]] effectName [speed]¬
    [to image]
unlock messages|error dialogs|recent
```

EffectName is an expression that yields any of the effect names described under the visual command later in this chapter. Speed is one of the following: fast, very fast, slow, slowly, very slow, or very slowly. Image is one of the following: black, card, gray, grey, inverse, or white.

Unlock 279

EXAMPLES

unlock screen with dissolve to black unlock error dialogs unlock recent

DESCRIPTION

The unlock command can be used for four different unrelated purposes. Using the unlock command, you can reset HyperCard to

- update the screen by setting the lockScreen global property to false. In addition, you can specify a single visual transition to occur when the screen is updated by using the visual effect option.
- send system messages such as openCard, closeCard, and so on, by setting the lockMessages property to false.
- display error dialogs in response to errors in executing scripts by setting the lockErrorDialogs property to false.
- record miniature representations of each card on the Recent card by setting the lockRecent global property to false.

NOTE

Visual effects can't be compounded using unlock screen, as they can be using the visual command.

See also the visual and lock commands in this chapter and the lockErrorDialogs, lockMessages, lockRecent, and lockScreen properties in Chapter 12, "Properties."

Unmark

SYNTAX

```
unmark card
unmark cards where condition
unmark all cards
unmark cards by finding [international] text [in field]
unmark cards by finding chars [international] text [in field]
unmark cards by finding string [international] text [in field]
unmark cards by finding whole [international] text [in field]
unmark cards by finding word [international] text [in field]
```

Card is an expression that yields a card descriptor. Condition is an expression that yields the criteria on which you want to base the unmarking of cards. Text is an expression that yields any text. Field is an expression that yields a field descriptor.

EXAMPLES

```
unmark the next card
unmark cards where "We be shaking" is in field 2
unmark all cards
unmark card by finding word "fire" in bkgnd field 3
```

DESCRIPTION

The unmark command sets the marked property for the specified card or cards to false. The marked property of a card can also be changed with the Card Marked option in the Card Info dialog box. By default, the marked property of a card is false.

The by finding form of the mark command uses chars, word, whole, and string to define the search criteria the same way the find command does. See the description of the find command for information about how to use these forms.

Unmark 281

CHAPTER 10

Commands

The unmark command can be used with the mark command in searches where you want to find and mark cards containing particular information while excluding other unnecessary information. See the description and script example used for the mark command, which is described earlier in this chapter.

NOTE

See also the marked property in Chapter 12, "Properties," and the mark command, earlier in this chapter.

Visual

SYNTAX

```
visual [effect] effectName [speed] [to image]
```

EffectName is one of the following:

```
barn door close | open
                          scroll up | down
checkerboard
                          shrink to top | center | bottom
dissolve
                          stretch from top | center | bottom
iris close | open
                          venetian blinds
plain
                          wipe left | right
push left | right
                          wipe up | down
push up | down
                          zoom close | open
scroll left | right
                          zoom in | out
```

Speed is one of the following:

```
fast very fast
slow[ly] very slow[ly]
```

Image is one of the following:

```
black inverse card white gray
```

EXAMPLES

```
visual effect barn door open visual dissolve slowly to white
```

DESCRIPTION

The visual command specifies a visual transition for HyperCard to use the next time it opens a card, as the current card is closed. The default plain visual effect causes all of the current image to be replaced immediately by the image of the next card. If you use the to *image* form, the visual effect occurs as a transition from the current card to a completely white, gray, or black screen image, to the inverted image of the next card, or to the image of the next card; to card is the default.

SCRIPT

The following example handler stacks two visual effects, which occur in succession, so that the transition appears as a fade to black, then to the next card:

```
on fadeOut
  visual effect dissolve to black
  visual effect dissolve to card
  go next card
end fadeOut
```

Visual 283

NOTES

Visual effects don't happen when you use the arrow keys or the show cards command to change cards; they occur only when go is executed, so they must be set up in a handler that also contains a go command. If a go command is not executed, visual effects set up in the handler are canceled when the handler finishes executing.

You can stack up several visual effects that will occur one after the other when you go to the next card.

See also the unlock command, earlier in this chapter.

Wait

SYNTAX

```
wait [for] time [seconds|ticks]
wait while | until condition
```

Time is an expression that yields an integer, and *condition* is an expression that yields true or false.

EXAMPLES

```
wait 60 seconds wait until the mouse is down
```

DESCRIPTION

The wait command causes HyperCard to pause before executing the rest of the handler, either for a specific length of time, until a specified condition becomes true, or while a specified condition remains true.

If seconds is not specified for *time*, HyperCard uses ticks (1/40 second).

SCRIPT

The following example handler allows time to view each card:

```
on slideshow
repeat the number of cards
visual effect dissolve slowly
go next card
wait 2 seconds
end repeat
end slideshow
```

Write

SYNTAX

write text to file fileName [at [-]start|end|eof]

Text is an expression that yields text. *FileName* is an expression that yields a filename.

Start is an integer expression identifying the position in the file where reading starts. A positive number indicates the character offset from the beginning of the file; a negative number specifies a character offset from the end of the file.

EXAMPLES

```
write field "address" to file "myDisk:myFile"
write "first line" & return & "second line" to file ¬
    "twoliner"

write someStuff to file "myFile" at -15
```

Write 285

DESCRIPTION

The write command causes HyperCard to copy the specified text to the specified disk file.

You can choose to specify the starting point at which to write the text. A negative number indicates the starting point to be a number of characters from the end of the file. If you specify either of the constants end and eof as the place to start, HyperCard appends the new text to the end of the file.

If you don't specify a starting point, the first write command executed after opening a file replaces the previous contents of a file. HyperCard does not ask if you want to write over the existing file.

For the write command to work, you must have already opened the file with the open file command, and you should close it, when writing is completed, with the close file command.

SCRIPT

The following example handler opens a file specified in a global variable, writes the entire contents of the specified field to the file starting at character 5, then closes the file:

```
on writeFile
  global filename
  open file filename
  write background field 1 to file filename
  close file filename
end writeFile
```

NOTES

If a file is open for writing and you write to a file at a certain offset or a specified position, like eof or end, then HyperCard will not replace the file with the new text.

HyperCard replaces the previous contents of a file when it is opened and then written to sequentially, using write commands that do not specify the offset at which to write into the file. If any one of them does specify the offset, the file will contain all of the newly written data but will also include any of the preexisting text that was not specifically overwritten.

You must provide the full pathname of the file if it's not at the same directory level as HyperCard. (See "Identifying a Stack" in Chapter 5 for an explanation of pathnames.)

If the file is locked or its disk is full, HyperCard displays an error dialog box and closes the file. HyperCard automatically closes all open files when an exit to HyperCard statement is executed, when you press Commandperiod, or when you quit HyperCard.

See also the close file, open file, and read commands in this chapter.

Write 287

This chapter describes HyperTalk's built-in functions.

A **function** is a named value that is calculated by HyperCard when the statement it is in executes. The value of a function changes according to conditions of the system or according to values of parameters that you pass to the function when you use it. When HyperCard reads a function name in a line of HyperTalk, it places the function's current value—its result—in that location before completing other actions.

Function Calls

To make a function call, that is, to use it in a HyperTalk statement, you must either use the word the before the function name or append parentheses after it. If a single parameter is passed to a function, the parameter can be enclosed in the parentheses or can follow the word of. (When of is used in this way to indicate the function call, the word the preceding the function name is optional.) If more than one parameter is passed to a function, all parameters must be enclosed in the parentheses and separated from each other by commas. Here are some examples of function calls:

```
put the time into msg
put time() into background field "Time"
put the length of myVariable into card field "howLong"
put average(total_1,total_2,total_3) into Projection
get the clickChunk
```

You can define your own functions in HyperTalk using the function handler structure described in Chapter 9.

Function Calls 289

User-defined functions override built-in ones with the same name

If you define your own function having the same name as a built-in one, yours overrides the built-in one if the function call is made with the parentheses syntax (unless the function call is made farther along the hierarchy than the handler's script). •

You can call the built-in functions of HyperCard directly and bypass any user-defined functions by using the word the before the function name. You can also use of, rather than using the parentheses syntax; however, functions having more than one parameter always require parentheses.

Syntax Description Notation

The syntax descriptions use the following typographic conventions. Words or phrases in this font are HyperTalk language elements or are those that you type to the computer literally, exactly as shown. Words in *italics* describe general elements, not specific names—you must substitute the actual instances. Brackets ([]) enclose optional elements that may be included if you need them. (Don't type the brackets.)

It doesn't matter whether you use uppercase or lowercase letters; names that are formed from two words are shown in lowercase letters with a capital in the middle (likeThis) merely to make them more readable.

The terms *factor* and *expression* are defined in Chapter 7, "Expressions." Briefly, a factor can be a constant, literal, function, property, number, or container, and an expression can be a single factor or a complex expression built with factors and operators. Also, a factor can be an expression within parentheses.

The term *yields* indicates a specific kind of value, such as a number or a text string, that must result from evaluation of an expression when a restriction applies (for example, the factor or expression used with the abs function must yield a number). However, any HyperTalk value can be treated as a text string.

Function Descriptions

The rest of this chapter describes the functions supported by HyperCard 2.2.

Abs

SYNTAX

the abs of factor
abs(expression)

Factor and expression yield numbers.

EXAMPLE

put abs(a-b) into field "theOffset"

DESCRIPTION

The abs function returns the absolute value (makes the sign positive) of the number passed to it.

Annuity

SYNTAX

annuity(rate, periods)

Rate and *periods* are expressions that yield numbers.

CHAPTER 11

Functions

EXAMPLES

```
put myPayment*annuity(.015,12) into presentValue
put myPayment*annuity(.015,12)*compound(.015,12)¬
   into futureValue
```

DESCRIPTION

The annuity function is used to compute the present or future value of an ordinary annuity. *Rate* is the interest rate per period, and *periods* is the number of periods over which the value is calculated. The formula for annuity is

```
annuity(rate, periods) = (1-(1+rate)-periods)/rate
```

The annuity function is more accurate than computing the formula above using basic arithmetic operations and exponentiation, especially when *rate* is small.

NOTE

See also the compound function, later in this chapter.

Atan

SYNTAX

the atan of *factor* atan(*expression*)

Factor and expression yield numbers.

EXAMPLE

put atan(1.0) into field "arcTan" -- yields 0.785398

DESCRIPTION

The atan function returns the trigonometric arc tangent (inverse tangent) of the number passed to it: that is, the angle whose tangent is equal to the given value. The result is expressed in radians.

Radians can be converted to degrees by multiplying by 180 and dividing the result by the value of the constant pi.

SCRIPT

The following example handler converts a value in radians to degrees and puts the result into the Message box:

```
on radiansToDegrees var
  put round((atan(var)*180)/pi) into msg
end radiansToDegrees
```

Average

SYNTAX

```
average(list)
```

List is a sequence of comma-separated expressions that yield numbers, or it is a single container that contains such a sequence.

EXAMPLE

```
put average(1,2,3) into field "avg"
```

DESCRIPTION

The average function returns the average of the numbers passed to it.

Average 293

SCRIPT

The following example handler displays the average of a list of numbers contained in one line of a field:

```
on avgSupplyPrice
  put "12.95,10.50,14.75,15.00,9.95" into line 3 of¬
  field "suppliers"
  answer "Average widget cost:" && average (line 3 of¬
  field "suppliers")
end avgSupplyPrice
```

CharToNum

SYNTAX

```
the charToNum of factor charToNum(expression)
```

Factor and expression yield a character.

EXAMPLE

```
put the charToNum of "a" into It -- yields 97
```

DESCRIPTION

The chartonum function returns an unsigned integer representing the ASCII equivalent value of the character passed to it.

NOTES

If more than one character is passed, charToNum returns the ASCII value of the first character. If *factor* is a literal, it must appear within quotation marks.

See also the numToChar function, later in this chapter.

ClickChunk

SYNTAX

```
the clickChunk
clickChunk()
```

EXAMPLES

```
put the clickChunk into card field "ExpressMyClick"
get the clickChunk
```

DESCRIPTION

The clickChunk function returns a chunk expression referring to the text clicked in a field and is typically something like char 1 to 3 of bkgnd field 3.

ClickChunk refers to the single word clicked, with the definition of a word being any characters delimited by white space (commas, tabs, spaces, returns, and so on). If the location clicked has the style group, then the largest contiguous run of text that has the group style is returned, thus allowing ranges or phrases rather than just single words to be referred to. Group is a possible value of the textStyle property.

SCRIPT

Because chunks of text also have properties, you could use the clickChunk function to examine the textstyle property of a chunk of text in a field and then take the appropriate action based on that style of text. For example, you might have an application that provides definitions for any boldface words when one of the words is clicked.

The following handler placed in a script of a locked field examines the style of a chunk of text clicked in that field and, if that text is boldface, calls up another field containing definitions:

```
on mouseUp
  if the textStyle of the clickChunk is bold
  then show card field "definitions"
end mouseUp
```

ClickChunk 295

CHAPTER 11

Functions

NOTE

See also the clickLine, clickLoc, and clickText functions in this chapter and the textStyle property in Chapter 12, "Properties."

ClickH

SYNTAX

the clickH
clickH()

EXAMPLE

put the clickH into card field "horizontalOffset"

DESCRIPTION

The clickH function returns an integer that represents the number of horizontal pixels from the left side of the card window to the place where the mouse was last clicked.

NOTE

See also the clickV function in this chapter.

ClickLine

SYNTAX

the clickLine
clickLine()

CHAPTER 11

Functions

EXAMPLES

put the clickLine into card field "MyClick"
get the clickLine

DESCRIPTION

The clickLine function returns the specification of the line (based on actual return characters, not display lines) that was clicked. A typical result is line 5 of card field 2. One sentence or line of text may not fit in the width of a field and have to wrap onto subsequent lines on the display. It may appear as though more than one line is in the field, but if the lines are not delimited with return characters, clickLine returns an expression like line 1 of card field 5 when a user clicks the text in that field. If you want clickLine to return a unique line number for each line that is displayed within a field, be sure to end each line in the field with a return character.

NOTE

See also the clickChunk, clickLoc, and clickText functions in this chapter.

ClickLoc

SYNTAX

the clickLoc clickLoc()

EXAMPLE

put the clickLoc into card field "mostRecentClick"

DESCRIPTION

The clickLoc function returns the point on the screen where the user most recently clicked before the handler started executing. The location is determined at the time the message is first sent—the mouse could be elsewhere by

ClickLoc 297

the time the message is received. The location point is returned as two integers separated by a comma, representing horizontal and vertical pixel offsets from the top-left corner of the card.

SCRIPT

The following example handler, when it is in the script of a locked field, selects a word in the field when the user clicks the word:

```
on mouseUp
   set locktext of me to false -- unlock the locked field
   -- next two lines double-click the location
   click at the clickLoc
   click at the clickLoc
   put "You clicked the word:" && the selection
   set lockText of me to true -- must lock it again
end mouseUp
```

ClickText

SYNTAX

```
the clickText
clickText()
```

EXAMPLES

```
put the clickText into card field "ExpressMyClick"
get the clickText
```

DESCRIPTION

ClickText returns the text of a single word clicked, with the definition of a word being any characters delimited by white space (commas, tabs, spaces, returns, and so on). If the location clicked has the style group, then the largest

contiguous run of text that has the group style is returned, thus allowing ranges or phrases rather than just single words to be referred to and analyzed. Group is a possible value of the textStyle property.

SCRIPT

The clickText function can be used to implement glossary lookup or provide other hypertext-type functions with something like the following handler, which should be placed in the script of the field being clicked:

```
on mouseUp
  get the clickText -- must be done before leaving card
  lock screen
  go stack "Glossary"
  find it in field "Words" -- is it a glossary entry?
  if the result = "Not found" then go back
  else unlock screen with dissolve -- display glossary
  -- entry
end mouseUp
```

NOTE

See also the clickChunk, clickLoc, and clickLine functions in this chapter and the textStyle property in Chapter 12, "Properties."

ClickV

SYNTAX

```
the clickV clickV()
```

EXAMPLE

```
put the clickV into card field "verticalOffset"
```

ClickV 299

DESCRIPTION

The clickV function returns an integer that represents the number of vertical pixels from the top of the card window to the place where the mouse was last clicked.

NOTE

See also the clickH function in this chapter.

CommandKey

SYNTAX

the commandKey
commandKey()

EXAMPLE

if the commandKey is up then put "Wow" into msg box

DESCRIPTION

The commandKey function returns the constant up if the Command key is not pressed or down if it is pressed.

NOTES

The commandKey function name can be abbreviated cmdKey.

See also the optionKey and shiftKey functions, later in this chapter.

Compound

SYNTAX

```
compound(rate, periods)
```

Rate and *periods* are expressions that yield numbers.

EXAMPLES

```
put futureValue/compound(.10,12) into presentValue
put presentValue*compound(.10,12) into futureValue
```

DESCRIPTION

The compound function is used to compute the present or future value of a compound interest–bearing account. *Rate* represents the interest rate per period, and *periods* is the number of periods over which the value is calculated. The formula for compound is

```
compound(rate, periods) = (1 + rate)periods
```

The compound function is more accurate than computing the formula expression above using standard arithmetic operations and exponentiation, especially when *rate* is small.

SCRIPT

The following example handler calculates the value in one year of an account earning $7\frac{1}{2}$ percent interest compounded monthly:

```
on calcInterest
   ask "Enter the beginning balance:" with empty
   set numberFormat to ".00" -- dollars and cents format
   put "Value in 1 year $" & it * compound(.075/12,12)
end calcInterest
```

Compound 301

Functions

NOTE

See also the annuity function, earlier in this chapter.

Cos

SYNTAX

the cos of factor cos(expression)

Factor and expression yield numbers.

EXAMPLE

put the cos of 2 -- puts -.416147 into the Message box

DESCRIPTION

The cos function returns the cosine of the angle that is passed to it. The angle must be expressed in radians.

NOTE

Radians can be converted to degrees by multiplying by 180 and dividing the result by the value of the constant pi.

Date

SYNTAX

the [adjective] date
date()

Adjective is long, short, or abbreviated (or abbrev or abbr); the default adjective is short.

EXAMPLE

put last word of the long date into background field "Year"

DESCRIPTION

The date function returns a string representing the current date set in your Macintosh. There are three forms of the date function. Here are examples of the format used by each:

```
the short date 7/20/93
the long date Tuesday, October 7, 1989
the abbrev date Tue, Oct 20, 1992
```

SCRIPT

The following example handler puts the current date into a field when another field (whose script contains the handler) is changed:

```
on closeField
  put the long date into field "lastUpdate"
end closeField
```

NOTES

The format of the date is initially specified by the international resources in the System file. These resources can and are altered for the purpose of customization or localization, so that a French system, for example, can display dates using French names for months and days of the week in the standard French formats.

Therefore, though the date function always returns the same basic data—the current date—the format of the data is not fixed. This issue is important for anyone who wants to build Stackware that works anywhere without modification.

You cannot assume that the long date always returns a date in this format: <day of week>, <month> <day>, <year>. If your stack is used on a Swedish system, a script that assumes that item 1 of the long date is the day of the week will not work since the Swedish format is not delimited by commas and has this format: <day of week> < day> <month> <year>.

Date 303

Make sure you convert and store all dates in the invariant dateItem format before doing calculations to prevent problems that are due to different local date formats. (See the convert command in Chapter 10.)

Destination

SYNTAX

```
the destination
destination()
```

EXAMPLE

```
on closeStack
  global stacksInMySuite
  if the destination is in stacksInMySuite then
        -- don't cleanup
  else
        -- cleanup: remove stack in use, restore menubar
  end if
  pass closeStack
end closeStack
```

DESCRIPTION

Returns the name of the destination stack when HyperCard is in the process of going to another stack. The destination is available to handlers for closeCard, closeBackground, closeStack, and suspendStack. If HyperCard is not going to another stack, this function returns the pathname of the current stack.

DiskSpace

SYNTAX

```
the diskSpace
diskSpace()
```

EXAMPLE

```
if the diskSpace < 100000 then answer ¬
"Your disk is getting full."
```

DESCRIPTION

The diskSpace function returns an integer representing the number of bytes of free space on the disk that contains the current stack.

SCRIPT

The following function handler is used by the second handler (for the writeFile message) to ensure that there is enough space on a disk to write to a file on that disk:

```
function thereIsRoom size
   return (the diskSpace > size)
end thereIsRoom

on writeFile
   global var -- the text to be saved
   put "MyFilename" into fileName
   if thereIsRoom(length of var) then
        open file fileName
        write var to file fileName
        close file fileName
   else answer "Can't write that file; the disk is full."
end writeFile
```

DiskSpace 305

Exp

SYNTAX

the exp of factor
exp(expression)

Factor and expression yield numbers.

EXAMPLE

put the exp of 2 -- puts 7.389056 into the Message box

DESCRIPTION

The exp function returns the mathematical exponential of its argument (the constant e, which equals 2.7182818, raised to the power specified by the argument).

Exp1

SYNTAX

the expl of factor expl(expression)

Factor and expression yield numbers.

EXAMPLE

put the expl of 2 -- puts 6.389056 into the Message box

Functions

DESCRIPTION

The exp1 function returns 1 less than the mathematical exponential of its argument (1 less than the result of the constant e raised to the power specified by the argument). That is, it computes

```
exp(number) - 1
```

Exp2

SYNTAX

```
the exp2 of factor exp2(expression)
```

Factor and expression yield numbers.

EXAMPLE

put the exp2 of 16 -- puts 65536 into the Message box

DESCRIPTION

The exp2 function returns the value of 2 raised to the power specified by the argument.

FoundChunk

SYNTAX

the foundChunk foundChunk()

Exp2 307

Functions

EXAMPLE

put the foundChunk

DESCRIPTION

The foundChunk function returns a chunk expression describing the location of the text found in a field with the find command. For example, if field 1 contained *Now is the time*, the commands (placed inside a handler)

```
find "Now"
put the foundChunk
```

would put char 1 to 3 of bkgnd field 1 into the Message box.

NOTE

See also the find command in Chapter 10.

FoundField

SYNTAX

the foundField
foundField()

EXAMPLE

put the foundField

DESCRIPTION

The foundField function returns the descriptor of the field in which the text was found with the find command. The result is in a form such as card field 1.

SCRIPT

The following handler uses foundField to put the field descriptor of a field containing the specified word in the Message box:

```
on getField theWord
lock screen
push card
find theWord
if the result is "not found" then
put "It's not here"
else
put the number of this card into cardNum
put "Your word was found in" && the foundField && ¬
"of card number" && cardNum
end if
pop card
unlock screen
end getField
```

To make the script work, put it in the stack or background script, then enter getField followed by the word you want to find in the Message box.

FoundLine

SYNTAX

```
the foundLine
foundLine()
```

EXAMPLE

put the foundLine

FoundLine 309

DESCRIPTION

The foundLine function returns a chunk expression describing the line in which the beginning of the text was found with the find command. The result is in a form such as line 1 of card field 2.

FoundText

SYNTAX

the foundText
foundText()

EXAMPLE

put the foundText

DESCRIPTION

The foundText function returns the characters that are enclosed in the box after the find command has executed successfully; for example, the commands

```
find "Hyper"
put the foundText
```

would put HyperCard in the Message box if it were the word containing the matching string.

HeapSpace

SYNTAX

the heapSpace

Functions

EXAMPLE

put the heapSpace into card field "Heap O'Fun"

DESCRIPTION

The heapSpace function returns an integer representing the remaining number of bytes of heap space currently available to HyperCard. The amount of heap space determines performance-related issues, such as whether the user can use the Paint tools, or whether HyperCard can open a stack in a new window.

SCRIPT

The following handler ensures that there is enough memory available for HyperCard to open a palette:

```
on openPalette
  get the heapSpace
  if it is < 100 then
      answer "Not enough memory to open this palette."
  end if
end openPalette</pre>
```

Length

SYNTAX

```
the length of factor length(expression)
```

Factor and expression yield text strings.

Length 311

Functions

EXAMPLES

```
put length("tail") into It -- yields 4
if the length of word n of field 5 > 25
then add 1 to fogIndex
```

DESCRIPTION

The length function returns the number of characters (including spaces, tabs, and return characters) in the text string passed to it.

NOTE

If *expression* is a literal, it must appear within quotation marks. The length function is identical in effect to the following form of the number function:

the number of characters in factor

Ln

SYNTAX

```
the ln of factor ln(expression)
```

Factor and expression yield numbers.

EXAMPLE

put the ln of 10 -- puts 2.302585 into Message box

DESCRIPTION

The ln function returns the base-*e* (natural) logarithm of the number passed to it.

Functions

Ln1

SYNTAX

the ln1 of factor ln1(expression)

Factor and expression yield numbers.

EXAMPLE

put the ln1 of 10 -- puts 2.397895 into Message box

DESCRIPTION

The lnl function returns the base-*e* (natural) logarithm of the sum of 1 plus the number passed to it. That is, it computes

ln(1 + number)

If *number* is small, ln1 of *number* is more accurate than ln(1+number).

Log2

SYNTAX

the log2 of factor log2(expression)

Factor and expression yield numbers.

EXAMPLE

put the log2 of 10 -- puts 3.321928 into the Message box

DESCRIPTION

The log2 function returns the base-2 logarithm of the number passed to it.

Ln1 313

Max

SYNTAX

```
\max(list)
```

List is a sequence of comma-separated expressions that yield numbers, or it is a single container that contains such a sequence.

EXAMPLE

```
put max(5,10,7.3) -- puts 10 into the Message box
```

DESCRIPTION

The max function returns the highest-value number from a list of numbers passed to it. If the source of the list is a container with more than one line in it, only the first line is used.

SCRIPT

The following example handler displays the highest number in a list contained in a variable:

```
on highStock

put "12.50,10,7.95,14.76,13.70" into stockPrices

answer "The highest price for the month is:" ¬

&& max(stockPrices)

end highStock
```

Menus

SYNTAX

the menus menus()

EXAMPLES

```
put the menus into card field 2
put menus() into MyVar -- MyVar is a variable
```

DESCRIPTION

The menus function returns a return-delimited list of all the menus currently in the HyperCard menu bar, including the Apple menu and any custom menus. In System 7, the list includes system menus.

NOTE

See also the create menu command in Chapter 10.

Min

SYNTAX

min(list)

List is a sequence of comma-separated expressions that yield numbers, or it is a single container that contains such a sequence.

EXAMPLE

put min(5,10,7.3) -- puts 5 into the Message box

Menus 315

DESCRIPTION

The min function returns the lowest-value number from a list of numbers passed to it. If the source of the list is a container with more than one line in it, only the first line is used.

SCRIPT

The following example handler displays the lowest number in a list contained in a variable:

```
on lowStock

put "12.50,10,7.95,14.76,13.70" into stockPrices

put "The lowest price for the month is:" ¬

&& min(stockPrices)

end lowStock
```

Mouse

SYNTAX

the mouse
mouse()

EXAMPLE

if the mouse is up then put "Press the mouse button"

DESCRIPTION

The mouse function returns the constant up if the mouse button is not pressed, down if it is pressed.

SCRIPT

The following example handler determines whether the user has single-clicked or double-clicked the button whose script contains the handler:

```
on mouseUp
  put the ticks into start
  repeat until the ticks-start > 4 -- click speed
    if the mouse is "down" then
       go last card -- put your double-click action here
       exit mouseUp
    end if
  end repeat
  go next card -- put your single-click action here
end mouseUp
```

MouseClick

SYNTAX

```
the mouseClick
mouseClick()
```

EXAMPLE

if the mouseClick then put the mouseLoc

DESCRIPTION

The mouseClick function determines if the mouse button is clicked. If no click is sensed, the mouseClick immediately returns the constant false. The mouseClick function returns the constant true when the mouse button is clicked. The mouseClick function does not return true more than one time for a given mouse click.

MouseClick 317

SCRIPT

The following example handler demonstrates operation of the mouseClick function by informing the user whether or not it sensed a click during its execution:

```
on mouseUp

put "Click or don't click..."

wait 5 seconds

if the mouseClick then

put "You clicked."

else

put "You didn't click."

end if

end mouseUp
```

MouseH

SYNTAX

the mouseH mouseH()

EXAMPLE

if the mouseH > 319 then put "Stop"

DESCRIPTION

The mouseH function returns an integer representing the number of horizontal pixels from the left side of the card to the current location of the pointer.

MouseLoc

SYNTAX

the mouseLoc
mouseLoc()

EXAMPLE

show button "everReady" at the mouseLoc

DESCRIPTION

The mouseLoc function returns the point on the screen where the pointer is currently located. This point is returned as two integers separated by a comma, representing horizontal and vertical pixel offsets from the top-left corner of the card.

SCRIPT

The following example handler, in a button script, allows the user to drag the button around the screen:

```
on mouseDown
  repeat until the mouse is up
    set the loc of me to the mouseLoc
  end repeat
end mouseDown
```

MouseLoc 319

MouseV

SYNTAX

the mouseV mouseV()

EXAMPLE

if the mouseV > 199 then put "Stop"

DESCRIPTION

The mouseV function returns an integer representing the number of vertical pixels from the top of the card to the current location of the pointer.

Number

SYNTAX

```
[the] number of objects
[the] number of chunks in expression
[the] number of backgrounds [in this stack]
[the] number of cards in background
[the] number of cards [in this stack]
[the] number of marked cards
[the] number of menus
[the] number of menuItems of menu
[the] number of [card|background] parts
[the] number of windows
```

Objects is [background] buttons, [card] fields, backgrounds, cards, or parts. Chunks is characters (or chars), words, items, or lines, and expression yields a container or text string. Background is an expression that yields the descriptor of a background in the current stack. Menu is an expression that yields a menu descriptor.

EXAMPLES

put the number of buttons into It
put number of items of line 1 of field 2 into listSize
put the number of chars in msg into line 3 of field 2
if number of chars in myVar > 10 then put "Big" into msg
get the number of cards of bkgnd 3

DESCRIPTION

The number function returns the number of buttons, fields, or parts on the current card or on its background, the number of backgrounds or cards in the current stack, the number of chunks of a specified kind in a designated container or text string, the number of cards that are associated with a specified background, the number of marked cards in the current stack, the number of menus in the menu bar, the number of menu items in a specified menu, or the number of windows currently available to HyperCard.

SCRIPT

The following example handler uses the number function to delete all the card fields on a card, regardless of how many there are:

```
on deleteFields
   repeat with whichField = the number of card fields ¬
   down to 1
        -- you must count down like this, not up
        delete card field whichField
   end repeat
end deleteFields
```

NOTES

If backgrounds is not specified with buttons, the number of card buttons is returned; if card is not specified with fields, the number of background fields is returned; if backgrounds is not specified with parts, the number of card parts is returned. If the number function is used with a chunk name, it returns the number of chunks of that kind within the designated container or other factor yielding a text string.

Number 321

The factor can be a chunk expression, so you can get the number of chunks of one kind within another chunk:

```
the number of chars in first word of field 1
```

You can also use the syntax that uses parentheses with the number function—for example:

```
number(cards)
number(menus)
number(bkgnds)
number(fields)
```

Backgrounds can be specified with the abbreviation bkgnds or bgs.

See also the number and marked properties in Chapter 12, and Chapter 5, "Referring to Objects, Menus, and Windows."

NumToChar

SYNTAX

```
the numToChar of factor numToChar(expression)
```

Factor and expression yield positive integers.

EXAMPLE

```
put numToChar(67) into word 4 of line 9 of field \neg "ASCII Chart" -- yields C
```

DESCRIPTION

The numToChar function returns the character whose ASCII equivalent value is that of the integer passed to it.

SCRIPT

The following example handler turns all of the lowercase letters in a field into uppercase letters:

```
on upperCase

put card field 4 into temp

-- variables are faster than fields

repeat with count = 1 to the length of temp

get character count of temp

if charToNum of It > 96 and ¬

charToNum of It < 123 then

put numToChar(charToNum(It)-32) into ¬

character count of temp

end if

end repeat

put temp into card field 4

end upperCase
```

NOTE

See also the charToNum function, earlier in this chapter.

Offset

SYNTAX

```
offset(string1,string2)
```

String1 and string2 are both expressions yielding text strings.

EXAMPLES

```
put offset("hay",field 1) into the Message box
offset("a","abc") -- typed in msg, returns 1
```

Offset 323

DESCRIPTION

The offset function returns the number of characters from the beginning of the *string2* string to the character at which *string1* begins. If *string1* doesn't appear within *string2*, 0 is returned.

SCRIPT

The following function handler finds every occurrence of a string within a container, and it replaces every occurrence with a second string:

```
function searchAndReplace container,original,replacement
  put length of original - 1 into theEnd
  repeat until original is not in container
  -- loop until all are replaced
    put offset(original,container) into start
    -- set start to location of original
    put replacement into char start to ¬
        start + theEnd of container
  end repeat
  return container
end searchAndReplace
```

NOTE

The parameters passed to the offset function can both be arithmetic or logical (as well as text) expressions; after evaluation, the results are treated as strings.

OptionKey

SYNTAX

```
the optionKey optionKey()
```

Functions

EXAMPLE

if the optionKey is down then choose button tool

DESCRIPTION

The optionKey function returns the constant up if the Option key is not pressed, down if it is pressed.

NOTE

See also the commandKey and shiftKey functions in this chapter.

Param

SYNTAX

the param of factor param(expression)

Factor and expression yield integers.

EXAMPLE

```
if param(1) is empty then answer¬
"The first parameter is null."
```

DESCRIPTION

The param function returns a parameter value from the parameter list passed to the currently executing handler. The parameter returned is the nth parameter, where n is the integer derived from factor or expression. The value of param(0) is the message name.

Param 325

SCRIPT

The following example handler sums the numeric arguments passed to it, regardless of how many there are:

```
on addUp -- adds a variable number of arguments
  put 0 into total
  repeat with i = 1 to the paramCount
     add param(i) to total
  end repeat
  put total
end addUp
```

NOTE

See also the paramCount and params functions, in this chapter, and the discussion of parameter passing in Chapter 4, "Handling Messages."

ParamCount

SYNTAX

```
the paramCount
paramCount()
```

EXAMPLE

```
if the paramCount < 3 then ¬
put "I need at least three arguments."
```

DESCRIPTION

The paramCount function returns the number of parameters passed to the currently executing handler.

SCRIPT

The following example handler draws an oval differently depending on the number of parameters passed to it:

```
on drawOval
  if the paramCount is 2 then set lineSize to param(2)
  choose oval tool
  drag from 30,30 to 30 + param(1),30 + param(1)
  choose browse tool
  reset paint
end drawOval
```

NOTE

See also the param and params functions, in this chapter, and the discussion of parameter passing in Chapter 4, "Handling Messages."

Params

SYNTAX

```
the params
params()
```

EXAMPLE

```
put the params into field "messageReceived"
```

DESCRIPTION

The params function returns the entire parameter list, including the message name, passed to the currently executing handler.

Params 327

Functions

SCRIPT

The following example handler is useful primarily for debugging, to see if the parameters passed to a handler are correct:

```
on myMessage
  put the params
  -- rest of myMessage handler goes here
end myMessage
```

NOTE

See also the param and paramCount functions, in this chapter, and the discussion of parameter passing in Chapter 4, "Handling Messages."

Programs

SYNTAX

```
the programs
programs()
```

EXAMPLES

```
answer the programs
put programs() into field id 4
```

DESCRIPTION

The programs function produces a return-delimited list of all the System 7–friendly processes currently running on your machine.

NOTE

See also the answer command in Chapter 10 and the discussion of Apple events in Chapter 1.

Random

SYNTAX

```
the random of factor random(expression)
```

Factor and expression yield positive integers.

EXAMPLE

```
set the loc of button "jumpy" to random(320), random(200)
```

DESCRIPTION

The random function returns a random integer between 1 and the integer derived from *factor* or *expression*, inclusive. Random supports integers up to 2^{31} –2.

SCRIPT

The following example handler draws 10 unique random numbers between 1 and 100:

```
on mouseUp
  put empty into randomList
  put the itemDelimiter into delim
  repeat until the number of items in randomList is 10
     get random of 100
     if (delim&it&delim) is not in (delim&randomList) then
     put it & delim after randomList
     end if
  end repeat
  -- get rid of extra item delimiter
  delete last char of randomList
  put randomList
end mouseUp
```

Random 329

Result

SYNTAX

the result
result()

EXAMPLE

if the result is not empty then answer "Try again."

DESCRIPTION

The result function returns an explanatory text string if an immediately preceding close file, convert, create stack, find, go, import paint, export paint, open file, picture, read, or save command was unsuccessful. The result function returns empty if the command executed successfully. The value of the result can also be set by a return statement in a message handler or by an external command. The value of the result is reset by execution of another command and at the end of the handler.

SCRIPT

The following example handler searches for a string and displays either the string or the error message if it doesn't find the string:

```
on doMenu var

if var is "Find..." then

global findMe

repeat

ask "Find what string:" with findMe

if It is not empty then find It

else exit doMenu -- cancel clicked

if the result is not empty then

put the result into findMe -- display error

next repeat
```

```
else

put It into findMe -- display string
exit repeat
end if
end repeat
else pass doMenu
end doMenu
```

NOTES

It is safer to depend on the empty result of a successful execution than on the particular value of some error message, because those values could be different in future versions of HyperCard.

If any of the commands listed in the result function description are sent from the Message box and generate an error, HyperCard displays the text of the result function in a dialog box. For example, if you sent a go command using the without dialog form from the Message box and used the name of a stack that doesn't exist, a dialog box containing "No such stack" is displayed after the command is sent. The same command sent in a handler would put the error message into the result but would not display a dialog box. If you want a dialog box displayed, you could include an answer statement in your handler that displays the result—for example:

```
on mouseUp
go stack quote& clickText &quote without dialog
put the result into goError
if goError is not empty
then answer goError with "OK"
end mouseUp
```

Chapter 9 discusses the return statement. Appendix A contains information about external commands.

Result 331

Round

SYNTAX

```
the round of factor round(expression)
```

Factor and expression yield numbers.

EXAMPLE

```
put round(resultVariable) into field 1
```

DESCRIPTION

The round function returns the source number rounded off to the nearest integer.

Any odd integer plus exactly 0.5 rounds up; any even integer (or 0) plus exactly 0.5 rounds down. If the source number is negative, HyperCard internally removes the negative sign, rounds its absolute value, then puts the negative sign back on.

SCRIPT

The following function handler rounds off an amount to the nearest dollar:

```
function roundToDollar amount
   set numberFormat to ".00" -- sets dollar format
   return round(amount)
end roundToDollar
```

ScreenRect

SYNTAX

the screenRect
screenRect()

EXAMPLE

put the screenRect into menuLoc

DESCRIPTION

The screenRect function returns the rectangle of the screen in which HyperCard's menu bar is displayed; the value returned is four integers, separated by commas, representing the pixel offsets of the left, top, right, and bottom edges, respectively, from the top-left corner of the screen.

Seconds

SYNTAX

the seconds seconds()

EXAMPLE

put (the seconds-startTime) into runTime

DESCRIPTION

The seconds function returns an integer showing the number of seconds between midnight, January 1, 1904, and the current time set in your Macintosh. The seconds function can be abbreviated secs.

ScreenRect 333

SCRIPT

The following example handler counts the number of seconds the user holds down the mouse button:

```
on mouseDown

put the long time into now -- what time is it now?

convert now to seconds

wait while the mouse is down

-- wait until mouse is released

put the seconds-now into msg

-- how many seconds have elapsed?

end mouseDown
```

NOTE

See also the convert command in Chapter 10, "Commands."

SelectedButton

SYNTAX

```
the selectedButton of family selectedButton(family)
```

Family specifies a card or background button family.

EXAMPLES

```
put the selectedButton of card family 1
get the selectedButton of family 4 of card 4
```

DESCRIPTION

The selectedButton function returns the descriptor of the currently high-lighted button in the specified card or background button family, such as card button 3. If no button in the family is highlighted, selectedButton returns empty.

NOTE

To change the value returned by selectedButton for a family, set the hilite property of one of the buttons. The select command has a different effect: select button 1 chooses the Button tool and selects the specified button for editing.

SelectedChunk

SYNTAX

```
the selectedChunk selectedChunk()
```

EXAMPLES

```
get selectedChunk()
put the selectedChunk
```

DESCRIPTION

The selectedChunk function returns a chunk expression describing the location of the selected text or the insertion point in a card or background field. For selected text, it is in the form of first character selected to last character selected of the field containing the selected text: for example, char 7 to 15 of card field 3.

SelectedChunk 335

If no text is selected but the insertion point is in a field, selectedChunk returns the number of the character on either side of the insertion point in reverse order with the highest number first. For example, if the insertion point is located between characters 9 and 10 in card field 2, selectedChunk returns char 10 to 9 of card field 2. If nothing is selected and the insertion point is not in a field, it returns empty.

NOTES

If you use the selectedChunk() form, be sure to leave the parentheses empty or you will get an error message.

Changing the highlight state of a button (clicking a button with autoHilite set to true) deselects the text and causes the selectedChunk function to return empty. Many other actions, such as clicking the card, clicking a locked field, or running an idle message handler that periodically changes some part of the display, also deselect the text, so you should put the result of selectedChunk into a container before any other action takes place.

You can put the selectedChunk result into the Message box or other container from a script, but you get an empty result if you make a selectedChunk function call from the Message box. This is the correct result of the call, since typing in the Message box and pressing the Return key or Enter key deselects any selected text.

You can get and set the text properties textFont, textSize, and textStyle of the selectedChunk function. See Chapter 12, "Properties," for more information about the text properties.

SelectedField

SYNTAX

the selectedField
selectedField()

CHAPTER 11

Functions

EXAMPLES

```
get selectedField()
put the selectedField
```

DESCRIPTION

The selectedField function returns the descriptor of the field containing the selected text or the insertion point. If the selection or insertion point is in the Message box, selectedField returns the string message box.

NOTES

Changing the highlight state of a button (clicking a button with autoHilite set to true) deselects the text and causes the selectedField function to return empty. Many other actions, such as clicking the card or clicking a locked field, also deselect the text, so you should put the result of selectedField into a container before any other action takes place.

You can put the selectedField result into the Message box or other container from a script, but you get an empty result if you make a selectedField function call from the Message box. This is the correct result of the call, since typing in the Message box and pressing the Return key or Enter key deselects any selected field.

The selectedField function does not apply to list fields.

SelectedLine

SYNTAX

```
the selectedLine [of button|field] selectedLine([button|field])
```

Button is a pop-up style button descriptor, and *field* is a field descriptor.

SelectedLine 337

EXAMPLES

```
get selectedLine()
put the selectedLine of card field 3
put word 2 of (selectedLine(btn 1))
```

DESCRIPTION

For pop-up buttons, the selectedLine function returns a chunk expression describing the currently selected line of the button's contents as a string in the form

line *number* of card|bkgnd button *number*

For fields specified explicitly, the selectedLine function returns a chunk expression describing the line containing the selected text or insertion point in the form

line number to number of card|bkgnd field number

If no field or button is specified, the selectedLine function returns a chunk expression describing the line of a field or the Message box that contains the current selection or insertion point. The expression is of the form

line *number* of card|bkqnd field *number*

NOTES

Lines in fields are defined as ending with the return character, and because text can wrap in fields, there may be several lines of text on the screen between return characters. For example, line 8 always specifies the text between the seventh and eighth return characters.

The selectedLine function can also be spelled selectedLines.

For fields other than list fields, many actions, such as clicking a button or other field, deselect the text, so you should put the result of selectedLine into a container before any other action takes place. In contrast, list fields retain their selectedLine value until the user changes it specifically.

If no lines are selected in an explicitly specified field, selectedLine returns empty. If no field or button is specified with the function call, and there is no current selection or insertion point, selectedLine returns empty.

SCRIPT

The following handler belongs in a list field (autoHilite, lockText, and dontWrap are true; multipleLines in this field should be false). Each line in the list field contains a glossary term. Each term corresponds to a card in the glossary stack, and the terms can be located by card number in the stack (that is, the term in line 2 of the field corresponds to card 2 of the glossary stack).

```
on mouseUp

put the selectedLine of me into selLine

put word 2 of selLine into whichEntry

select line 0 of me -- deselect

go card whichEntry of stack "Glossary" in a new window
end mouseUp
```

SelectedLoc

SYNTAX

```
the selectedLoc
selectedLoc()
```

EXAMPLES

```
get selectedLoc()
put the selectedLoc
```

SelectedLoc 339

DESCRIPTION

The selectedLoc function returns a point at which the selected text begins. The selectedLoc function returns the point as two commaseparated integers that represent the offset from the top-left corner of the card to the bottom (baseline) left of the selected text.

The value returned by the selectedLoc function is the same as the value returned by the TEGetPoint routine, which is described in *Inside Macintosh: Text*.

SelectedText

SYNTAX

```
the selectedText [of button|field] selectedText([button|field])
```

Button is a pop-up style button descriptor, and *field* is a field descriptor.

EXAMPLES

```
get selectedText(card field 1)
put the selectedText
get the selectedText of button "My Pop-Up Button"
```

DESCRIPTION

The selectedText function returns the currently selected text in a field or pop-up button specified with the function call. If no field or button is specified, selectedText returns the text of the current selection in a nonlist field or the Message box. If there is no text selected, selectedText returns empty.

NOTES

When no field or button is specified, selectedText returns the same result as the selection or the value of the selectedChunk.

For fields other than list fields, many actions, such as clicking a button or other field, deselect the text, so you should put the result of selectedLine into a container before any other action takes place. In contrast, list fields retain their selectedLine value until the user changes it specifically.

You can put the selectedText result into the Message box or other container from a script, but you get an empty result if you make a selectedText function call from the Message box. This is the correct result of the call, since typing in the Message box and pressing the Return key or Enter key deselects any selected text.

ShiftKey

SYNTAX

```
the shiftKey shiftKey()
```

EXAMPLE

```
if the shiftKey is down then put ¬
numToChar(charToNum(msq)-32) into msq
```

DESCRIPTION

The shiftKey function returns the constant up if the Shift key is not pressed, down if it is pressed.

ShiftKey 341

SCRIPT

The following handlers in the script of a field enable the user to change uppercase characters to lowercase and vice versa. The user selects a chunk of text (not including any Return characters) and presses Enter. If the Shift key is down, the script changes the case of the characters.

```
on enterInField
   if the shiftKey is down then
      toggleCaps the selectedChunk, the selectedText
   end if
   pass enterInField
end enterInField
on toggleCaps theChunk, theText
   if theChunk is empty or ¬
   (word 2 of theChunk > word 4 of theChunk)
   then exit toggleCaps
   repeat with i = 1 to length(theText)
      put swapcase(char i of theText) into ¬
      char i of theText
   end repeat
   do "put" && quote & theText & quote ¬
   && "into" && theChunk
end toggleCaps
function swapcase the Char
   get charToNum(theChar)
   if it \geq 65 and it \leq 90 then return numToChar(it+32)
   if it \geq 97 and it \leq 122 then return numToChar(it-32)
   return theChar
end swapCase
```

NOTE

See also the commandKey and optionKey functions earlier in this chapter.

Sin

SYNTAX

the sin of factor
sin(expression)

Factor and expression yield numbers.

EXAMPLE

put the sin of 2 -- puts 0.909297 into the Message box

DESCRIPTION

The sin function returns the sine of the angle that is passed to it. The angle must be expressed in radians.

NOTE

Radians can be converted to degrees by multiplying by 180 and dividing the result by the value of the constant pi.

Sound

SYNTAX

the sound sound()

EXAMPLE

wait until the sound is "done"

Sin 343

DESCRIPTION

The sound function returns the name of the sound resource currently playing (such as "boing") or the string "done" if no sound is currently playing. The sound function enables you to synchronize sounds with other actions, because in most cases scripts continue to run while sounds play. In the event of a low-memory situation, such as when playing a large sound while a large Home stack or several other stacks are in use and HyperCard is set to the default memory allocations, HyperCard may suspend other actions until the sound is finished playing. Increasing HyperCard's memory allocation should alleviate this problem.

SCRIPT

The following example handler repeats a series of visual effects until a tune specified by the play command finishes:

```
on boogie

play "harpsichord" tempo 200 ¬

"ce gq fe ee de ce gq fe ee ce gq fe ee ce"

repeat until the sound is "done"

visual effect dissolve to black

visual effect zoom open to white

visual effect barn door close to card

go this card

end repeat

end boogie
```

NOTES

The "done" string is returned as a literal; it's not a HyperTalk constant like up or true.

See also the play command in Chapter 10.

Sqrt

SYNTAX

```
the sqrt of factor sqrt(expression)
```

Factor and expression yield numbers.

EXAMPLE

```
put the sqrt of msg
-- converts the number in msg to its square root
```

DESCRIPTION

The sqrt function returns the square root of the positive number passed to it. If you pass a negative number, you get the result -NAN(001), which means "not a number."

Stacks

SYNTAX

```
the stacks
stacks()
```

EXAMPLE

put the stacks into card field 2

DESCRIPTION

The stacks function returns a return-delimited list of the pathnames of all the currently open stacks. The stack returned in the first line is the active stack.

Sqrt 345

StackSpace

SYNTAX

the stackSpace
stackspace()

EXAMPLE

put the stackSpace into howMuch

DESCRIPTION

The stackSpace function returns an integer that represents the space remaining on the Macintosh operating system stack. *Stack* in this case refers to an internal data structure rather than a HyperCard stack.

Sum

SYNTAX

sum(list)

List is a sequence of comma-separated expressions that yield numbers, or it is a single container that contains such a sequence.

EXAMPLE

get sum (1,2,3,4)

DESCRIPTION

The sum function returns the sum of a list of numbers passed to it. If the source of the list is a container with more than one line in it, only the first line is used.

SystemVersion

SYNTAX

```
the systemVersion
systemVersion()
```

EXAMPLE

put the systemVersion

DESCRIPTION

The systemVersion function returns a decimal string that represents the running version of system software.

You might use this function to determine if a particular HyperCard command or handler will run correctly under that version of the software.

SCRIPT

The following code makes sure that the machine that HyperCard is running on is using System 7; if not, HyperCard posts an appropriate message:

```
if the systemVersion < 7
then answer "This stack requires System 7." with "Quit"
doMenu "quit Hypercard"</pre>
```

Tan

SYNTAX

```
the tan of factor tan(expression)
```

Factor and expression yield numbers.

SystemVersion 347

CHAPTER 11

Functions

EXAMPLE

put the tan of 2 -- puts -2.18504 into the Message box

DESCRIPTION

The tan function returns the tangent of the angle that is passed to it. The angle must be expressed in radians.

NOTE

Radians can be converted to degrees by multiplying by 180 and dividing the result by the value of the constant pi.

Target

SYNTAX

the target

EXAMPLE

if the target is "card id 2875" then pass mouseUp

DESCRIPTION

The target function returns a string indicating the original recipient of the message. The string returned is one of the following:

```
stack "name"
bkgnd of card "name" | id number
card "name" | id number
bkgnd field "name" | id number
card field "name" | id number
bkgnd button "name" | id number
card button "name" | id number
```

For example, the target function enables you to tell, in a mouseUp handler in a background, whether

- the mouse was clicked over a field or button (which either would have had no mouseUp handler or would have passed the message on explicitly): the target would return the button or field name, if it has one, or ID number if not
- the mouse was clicked outside the area of all buttons and fields: the target would return the card name, if it has one, or ID number if not
- the message was sent directly to the background with the send command: the target would return the background name, if it has one, or ID number if not

You can use the target in place of an object descriptor to determine any of the target's properties:

```
get the short name of the target
```

NOTES

The send command resets the value of the target to the value of the object the message is being sent to.

If the target is a button or field, the expression target (without the) evaluates to the contents of the button or field.

Ticks

SYNTAX

the ticks ticks()

EXAMPLE

put the ticks into clock

Ticks 349

DESCRIPTION

The ticks function returns an integer representing the number of ticks (1/60 second) since the Macintosh was turned on or restarted.

SCRIPT

The following example handler measures how long it takes to go to the Help stack and find the word ticks:

```
on mouseUp

put the ticks into startTicks

go "HyperCard Help"

find "ticks"

put (the ticks - startTicks) into howLong

answer "It took" && howLong div 60¬

&& "second(s) to find Help."

end mouseUp
```

Time

SYNTAX

```
the [adjective] time
time()
```

Adjective can be long, short, or abbreviated (or abbrev, or abbr).

EXAMPLE

put the time into the Message box

DESCRIPTION

The time function returns the time as a text string. The short and abbreviated forms are the same, returning the hour and minutes, such as 8:55 AM. The long time form returns seconds as well, such as 8:55:23 AM.

SCRIPT

The following example records the time at which a field is updated:

```
on closeField
  put return & the time after card field "updateList"
end closeField
```

NOTES

An adjective can't be used to modify the form of the time function that uses parentheses.

The time string returned by the time function can be in either 24- or 12-hour format depending on the time format set in the Date and Time control panel. The time format can also be altered in the international resources of the System file. If you are going to perform calculations on the time, you should first convert it to the invariant seconds format. See the convert command in Chapter 10.

Tool

SYNTAX

the tool
tool()

EXAMPLE

if the tool is "field tool" then choose browse tool

Tool 351

DESCRIPTION

The tool function returns the name of the currently chosen tool. Possible values returned by the tool function are

browse tool oval tool brush tool pencil tool bucket tool polygon tool button tool rectangle tool curve tool regular polygon tool eraser tool round rect tool field tool select tool lasso tool spray tool line tool text tool

SCRIPT

The following example handler chooses the proper tool to manipulate a button or field when you move the pointer over either object:

```
on mouseWithin -- in card, background, or stack script
if "button" is in the target and the optionKey is down
then choose button tool
else if "field" is in the target and ¬
the optionKey is down
then choose field tool
end mouseWithin
```

NOTE

See also the choose command in Chapter 10.

Trunc

SYNTAX

```
the trunc of factor trunc(expression)
```

Factor and expression yield numbers.

EXAMPLE

put the trunc of someNumber into msg

DESCRIPTION

The trunc function returns the integer part of the number passed to it. Any fractional part is disregarded, regardless of sign.

SCRIPT

The following example handler draws rectangles in increasing sizes, using the trunc function to ensure that the computed values used with the drag command are integers:

```
on mouseUp
push card
doMenu "New Card"
reset paint
choose rectangle tool
put 50 into left
put 150 into right
put 50 into top
put 150 into bottom
```

Trunc 353

CHAPTER 11

Functions

```
repeat 5 -- the drag command only takes integers
   drag from left,top to right,bottom
   put trunc(left/1.2) into left
   put trunc(right/1.2) into right
   put trunc(top/1.2) into top
   put trunc(bottom/1.2) into bottom
   end repeat
   choose browse tool
end mouseUp
```

Value

SYNTAX

the value of *factor* value(*expression*)

Factor and expression yield any values.

EXAMPLE

put the value of field "formula" into field "result"

DESCRIPTION

The value function evaluates the string derived from *factor* or *expression* as an expression. Note that multitoken literal expressions evaluate to themselves:

```
put value ("HyperCard 2.2") -- returns HyperCard 2.2
```

SCRIPT

The following example handler demonstrates the value function by forcing a second level of evaluation of a variable:

```
on mouseUp
  put "3 + 4" into expression
  put expression -- yields "3 + 4"
  wait 2 seconds
  put value of expression -- yields 7
end mouseUp
```

Windows

SYNTAX

```
the windows windows()
```

EXAMPLES

DESCRIPTION

The windows function returns a return-delimited list containing the names of all of the windows currently available to HyperCard and the current stack. The order of the window names corresponds to the front-to-back ordering of the windows. The windows include built-in palettes (Tool and Pattern), FatBits, the Message box, open card windows, and external windows (for example, Message Watcher, Navigator palette, Scroll window, Variable Watcher).

NOTE

The windows returned in the list may not currently be visible.

Windows 355

This chapter describes HyperCard properties. Properties are the defining characteristics of objects, other elements such as menus and windows, and the HyperCard environment.

Object properties determine how objects look and act. Global properties control aspects of the overall HyperCard environment. Painting properties control aspects of the HyperCard painting environment, which is invoked when you choose a Paint tool. Window properties determine how card windows, the Message box, the Tools and Patterns palettes, and external windows are displayed. Menu, menu bar, and menu item properties control aspects of HyperCard menus. There are also a few properties that apply to the Message Watcher or the Variable Watcher.

This chapter includes a set of tables that list the HyperCard properties by category. Button properties, field properties, window properties, and so on are each listed in a separate table. The tables are followed by complete descriptions of all the properties in alphabetical order.

Retrieving and Setting Properties

HyperTalk lets you retrieve most properties by using the property name as a function in a script or the Message box. You must precede the property name with the word the or follow it with of if it's an object or window property. You can't use parentheses after the property name, as you do with built-in functions. The following example retrieves the location property of button 1 and puts it into the Message box:

put the loc of button 1 into msg

You set properties with the set command:

```
set loc of button 1 to 100,100
```

Some properties can't be set, although other actions affect them. For example, the size of a stack is read-only, but it can be changed by compacting it and by adding objects.

You can get the value of most properties with the get command:

```
get the property of object
```

Most of the examples in this chapter do not include the syntax for the get *property* command, because it is faster to put a property directly into a container or variable (rather than using the get command and then the put command).

Object Properties

You can see the value of many object properties by looking at an object's Info dialog box, an example of which is shown in Figure 12-1. (You bring up an object's Info dialog box by choosing the appropriate command from the Objects menu.)

Figure 12-1 An object's Info dialog box



You can also set many properties for the current object from the Info dialog boxes. To set the properties of any object in the current stack, you use the set command, either in a script or in the Message box.

Different HyperCard objects have different properties. For example, fields have a property determining their text style, but cards do not.

Stack Properties

Stack properties pertain to any stack on any disk or file server currently accessible to your Macintosh. A stack is specified as explained in Chapter 5, "Referring to Objects, Menus, and Windows." Settable properties of the current stack can be manipulated from a script or through the Stack Info dialog box invoked from the Objects menu.

The stack properties are listed in Table 12-1. More detailed information about each property is given later in this chapter.

Table 12-1 Stack properties

Deparinties
Description
Controls whether or not the user can use Command-period to stop execution of scripts.
Controls whether or not the user can delete the specified stack.
Controls whether or not the stack can be changed in any way.
Controls whether or not the user can look at button or field scripts with Command-Option.
Determines the amount of free space of the specified stack in bytes.
Determines or changes the name of the specified stack, which is its Macintosh filename.
Determines the report-printing templates of the stack.
Retrieves or replaces the script of the specified stack.

Table 12-1 Stack properties (continued)

Stack property name	Description
scriptingLanguage	Determines or changes the scripting language of the stack.
size	Determines the size of the specified stack in bytes.
version	Determines the versions of HyperCard that created and modified the specified stack.

Background Properties

Background properties pertain to any background in the current stack. The background is specified as explained in Chapter 5, "Referring to Objects, Menus, and Windows." Background properties can be manipulated from a script or from the Message box. Properties of the current background can also be manipulated through the Bkgnd Info dialog box invoked from the Objects menu, or in the script editor window in the case of scriptingLanguage.

The background properties are listed in Table 12-2. More detailed information about each property is given later in this chapter.

Table 12-2 Background properties

Background property name	Description
cantDelete	Controls whether or not the user can delete the specified background.
dontSearch	Determines whether or not the fields in a specified background are searched with the find command.
ID	Determines the permanent ID number of any background in the current stack.
name	Determines or changes the name of the specified background.
number	Determines the number of any background in the current stack.

Table 12-2 Background properties (continued)

Background property name	Description
script	Retrieves or replaces the script of the specified background.
scriptingLanguage	Determines or changes the scripting language of the specified background.
showPict	Determines whether or not the picture of the specified background in shown.

Card Properties

Card properties pertain to any card in the current stack. The card is specified as explained in Chapter 5, "Referring to Objects, Menus, and Windows." You can manipulate card properties from a script, in the Message box, or through the Card Info dialog box invoked from the Objects menu, or in the script editor window in the case of scriptingLanguage.

The card properties are listed in Table 12-3. More detailed information about each property is given later in this chapter.

Table 12-3 Card properties

Card property name	Description
cantDelete	Controls whether or not the user can delete the specified card.
dontSearch	Determines whether or not the fields in a specified card are searched with the find command.
ID	Determines the permanent ID number of any card in the current stack.
marked	Determines or changes whether a specified card is marked.
name	Determines or changes the name of the specified card.

Table 12-3 Card properties (continued)

Card property name	Description
number	Determines the number of any card in the current stack.
owner	Returns the name of the background shared by this card.
rect[angle]	Determines or changes the size of the rectangle occupied by the specified card. See also Table 12-6.
script	Retrieves or replaces the script of the specified card.
scriptingLanguage	Determines or changes the scripting language of the specified card.
showPict	Determines whether or not the picture of the specified card is shown.

Field Properties

Field properties pertain to any card field or background field in the current stack. The field is specified as explained in Chapter 5, "Referring to Objects, Menus, and Windows." You can manipulate field properties from a script or from the Message box, or through the Field Info dialog box invoked from the Objects menu, or in the script editor window in the case of scriptingLanguage. (You must have the Field tool chosen and a specific card or background field selected or have the insertion point in a field to activate the Field Info dialog box.)

The field properties are listed in Table 12-4. More detailed information about each property is given later in this chapter.

Table 12-4Field properties

Field property name	Description
autoSelect	Enables a field to behave as a list when its dontWrap and lockText property are also true.
autoTab	Determines or changes whether or not the specified nonscrolling field sends the tabKey message to the current card.
dontSearch	Determines or changes whether or not the specified field is searched with the find command.
dontWrap	Determines or changes whether or not text at the edge of the specified field automatically wraps around to the next line.
fixedLineHeight	Determines or changes whether or not the lines in the specified field have a fixed line height.
ID	Determines the permanent ID number of the specified field.
location	Determines or changes the location of the specified field.
lockText	Determines or changes whether editing of text within the specified field in the current stack is allowed or prevented.
multipleLines	Determines or changes whether or not the user can select multiple lines in a list field.
name	Determines or changes the name of the specified field.
number	Determines the number of the specified field.
partNumber	Determines or changes the number that represents the ordering of the buttons and fields within their enclosing card or background. Setting this property can have the effect of either bringing the field closer or moving it farther (behind) other buttons and fields.

Table 12-4 Field properties (continued)

Field property name	Description
rect[angle]	Determines or changes the location and size of the rectangle occupied by the specified field. See also Table 12-6.
script	Retrieves or replaces the script of the specified field.
scriptingLanguage	Determines or changes the scripting language of the specified field.
scroll	Determines or changes how much material is hidden above the top of the specified scrolling field's rectangle.
sharedText	Determines or changes whether the text in the specified background field appears on each card of that background.
showLines	Determines or changes whether the text baselines in the specified field appear or are invisible.
style	Determines or changes the style of the specified field in the current stack.
textAlign	Determines or changes the way lines of text are aligned in the specified field.
textFont	Determines or changes the font in which text in the specified field appears.
textHeight	Determines or changes the space between baselines of text in the specified field.
textSize	Determines or changes the type size in which text in the specified field appears.
textStyle	Determines or changes the style in which text in the specified field appears.
visible	Determines or changes whether the specified field is shown or hidden. The default value of the visible property is true.
wideMargins	Determines or changes whether some extra space is included at the left and right sides of each line in the specified field (to make the text easier to read).

Button Properties

Button properties pertain to any card button or background button in the current stack. The button is specified as explained in Chapter 5, "Referring to Objects, Menus, and Windows."

You can manipulate the properties of any button in the current stack from a script or from the Message box. Additionally, you can manipulate the properties of a button on the current card or background through the Button Info dialog box invoked from the Objects menu, or in the script editor window in the case of scriptingLanguage. (You must have the Button tool and a specific card or background button selected to activate the Button Info dialog box.)

The button properties are listed in Table 12-5. More detailed information about each property is given later in this chapter.

Table 12-5 Button properties

Button	
property name	Description
autoHilite	Determines or changes whether the specified button highlights when that button is pressed.
enabled	Determines or changes whether the specified button appears and behaves in an enabled or disabled state.
family	Groups two or more buttons together into a family specified by the numbers 1 to 15, inclusive.
hilite	Determines or changes whether the specified button is highlighted (displayed in inverse video).
icon	Determines or changes the icon for the specified button in the current stack.
ID	Determines the permanent ID number of the specified button.
loc[ation]	Determines or changes the location of the specified button.
name	Determines or changes the name of the specified button.
	continued

 Table 12-5
 Button properties (continued)

Button property name	Description
number	Determines the number of the specified button.
partNumber	Determines or changes the number that represents the ordering of the buttons and fields within their enclosing card or background.
rect[angle]	Determines or changes the location and size of the rectangle occupied by the specified button. See also Table 12-6.
script	Retrieves or replaces the script of the specified button.
scriptingLanguage	Determines or changes the scripting language of the specified field.
sharedHilite	Determines or changes whether the specified background button is displayed highlighted on all cards of that background.
showName	Determines or changes whether the name of the specified button (if it has one) is displayed in its rectangle on the screen.
style	Determines or changes the style of the specified button in the current stack.
textAlign	Determines or changes the way lines of text are aligned in the specified button.
textFont	Determines or changes the font in which text in the specified button appears.
textHeight	Determines or changes the space between baselines of text in the specified button.
textSize	Determines or changes the type size in which text in the specified button appears.
textStyle	Determines or changes the style in which text in the specified button appears.

Table 12-5 Button properties (continued)

Button property name	Description
titleWidth	Determines or changes the width of the area in which a pop-up button's name appears.
visible	Determines or changes whether the specified button is shown or hidden. The default value of the visible property is true.

Rectangle Properties

The properties described in this section pertain to the screen rectangles of the menu bar, buttons and fields, the Tools and Patterns palettes (called *windows* in scripts), the Scroll window, the FatBits window, card windows, stack windows, the Message box, and external windows (if the XCMD that created the window supports control of rectangle properties).

The rectangle property itself also applies to buttons, fields, windows, and the menu bar. The rectangle property is two points, the top-left and bottom-right corners of an object's rectangle. The points are represented as four integers separated by commas: left (item 1), top (item 2), right (item 3), bottom (item 4). The rectangle properties affect these four items, one at a time or two at a time.

The rectangle properties are listed in Table 12-6. More detailed information about each property is given later in this chapter.

Table 12-6 Rectangle properties

Rectangle property name	Description
bottom	Determines or changes the value of item 4 of the rectangle property when applied to the specified object or window.
bottomRight	Determines or changes items 3 and 4 of the value of the rectangle property when applied to the specified object or window.

Table 12-6 Rectangle properties (continued)

Rectangle property name	Description
height	Determines or changes the vertical distance in pixels occupied by the rectangle of the specified button or field.
left	Determines or changes the value of item 1 of the rectangle property when applied to the specified object or window.
right	Determines or changes the value of item 3 of the rectangle property when applied to the specified object or window.
top	Determines or changes the value of item 2 of the rectangle property when applied to the specified object or window.
topLeft	Determines or changes items 1 and 2 of the value of the rectangle property when applied to the specified object or window.
width	Determines or changes the horizontal distance in pixels occupied by the rectangle of the specified button or field.

Environmental Properties

Some of the global properties, such as the userLevel property, can be set on the User Preferences card of the Home stack; others, such as the lockMessages property, can be retrieved and set only through HyperTalk. (However, the User Preferences card uses HyperTalk to set properties, and it could be extended to set any of the others.) The window properties, which pertain to the Message box and the tear-off palettes, can be set by clicking and dragging the windows themselves, as well as through HyperTalk. Painting properties, which pertain to the painting environment, can be controlled with the menus and palettes that appear when a Paint tool is selected, as well as through HyperTalk.

Global Properties

You use global properties to choose how particular aspects of the HyperCard environment perform. You set global properties from any script or from the Message box, and their settings pertain to all objects—if you set userLevel to 3, for example, it remains 3 until you reset it (although a protected stack might impose some other user level while you are in that stack).

All of the printing properties, such as printMargins, can be restored simultaneously to their default values with the reset printing command, described in Chapter 10, "Commands."

The global properties are listed in Table 12-7. More detailed information about each property is given later in this chapter.

Table 12-7 Global properties

Global property name	Description
address	Determines where your HyperCard application is running. If you're connected to a network, this property returns a string in the form "zone:Macintosh:program." If you're not on a network, or on a network with just one AppleTalk zone, HyperCard substitutes an asterisk (*) for the network name.
blindTyping	Determines or changes whether you can type messages into the Message box and send them (execute them) without having the Message box visible.
cursor	Changes the image that appears at the pointer location on the screen.
debugger	Determines or changes the name of the current HyperTalk debugger. Custom debuggers can be created as XCMDs and called with HyperTalk.
dialingTime	Determines how long HyperCard waits before closing the serial connection to a modem after dialing. Time units for this property are in ticks (1/60th of a second) with the default time set to 180 ticks (3 seconds).

 Table 12-7
 Global properties (continued)

Global property name	Description
dialingVolume	Determines or changes the volume of the touch tones generated through the Macintosh speaker by the dial command.
dragSpeed	Determines or changes how many pixels per second the pointer moves when manipulated by all subsequent drag commands.
editBkgnd	Determines or changes where any painting or creating of buttons or fields happens—on the current card or on its background.
environment	Determines the environment of the currently running HyperCard application; returns development if it is the fully enabled development version, and player if the HyperCard Player is running.
ID	Determines the permanent signature of HyperCard, 'WILD'.
itemDelimiter	Determines what delimiter is used to separate a list of items. HyperCard resets the delimiter to its default, the comma, when the computer is idle.
language	Determines or changes the language dialect in which HyperTalk scripts are written and displayed.
lockErrorDialogs	Determines or changes whether HyperCard displays an error dialog. This property is set to false at idle time, so it has no effect if you enter it through the Message box.
lockMessages	Determines or changes whether HyperCard sends system messages such as openCard, closeCard, and so on.
lockRecent	Determines or changes whether HyperCard adds miniature representations to the Recent card.
lockScreen	Determines or changes whether HyperCard updates the screen when you go to another card.

continued

 Table 12-7
 Global properties (continued)

Global property name	Description
longWindowTitles	Determines or changes whether HyperCard displays the long name of a stack in its title bar.
messageWatcher	Determines or changes the name of the current message watcher. A custom message watcher can be created as an XCMD and called with HyperTalk.
numberFormat	Determines or changes the precision with which the results of mathematical operations are displayed in fields and the Message box.
powerKeys	Determines or changes whether keyboard shortcuts for painting actions are available.
printMargins	Specifies the page margins to use when printing reports and expressions.
printTextAlign	Specifies the text alignment to use in the header of a print report and when printing variables.
printTextFont	Specifies the text font to use in the header of a print report and when printing variables.
printTextHeight	Specifies the line height to use in the header of a print report and when printing variables.
printTextSize	Specifies the text size to use in the header of a print report and when printing variables.
printTextStyle	Specifies the text style to use in the header of a print report and when printing variables.
scriptEditor	Determines or changes the current script editor to use. A custom script editor can be created as an XCMD and called with HyperTalk.
scriptingLanguage	Determines or changes the scripting language of the Message box.
scriptTextFont	Determines or changes which font to use in the script editor.
scriptTextSize	Determines or changes which font size to use in the script editor.

Table 12-7 Global properties (continued)

Global property name	Description
stacksInUse	Determines which stacks are currently in the message-passing hierarchy.
suspended	Determines whether HyperCard is currently running in the background under MultiFinder or System 7.
textArrows	Alters the function of the Right Arrow, Left Arrow, Up Arrow, and Down Arrow keys.
traceDelay	Determines the time between execution of statements while tracing.
userLevel	Sets or retrieves the value of the current HyperCard user level. $ \label{eq:current} % \begin{subarray}{ll} \end{subarray} % \begin{subarray}{ll$
userModify	Determines or changes whether or not a user can type into fields or use Paint tools in a stack that has been write-protected.
variableWatcher	Determines or changes the name of the current variable watcher. Custom variable watchers can be created as XCMDs and called with HyperTalk.
version	Determines the version number of the HyperCard application currently running or the versions of HyperCard that created and modified a specified stack.

Painting Properties

Painting properties are aspects of the painting environment invoked when you choose a Paint tool from the Tools palette. Most of these properties are usually manipulated from the Options and Patterns menus that appear when a Paint tool is selected. The text attributes pertain to Paint text; they are usually manipulated from the dialog box that appears when you double-click the Paint Text tool in the Tools palette or when you choose Text Style from the Edit menu. Changes to the settings made from HyperTalk are reflected on their respective palettes and menus.

All of the painting properties can be restored to their default values simultaneously with the reset paint command, described in Chapter 10, "Commands."

The painting properties are listed in Table 12-8. More detailed information about each property is given later in this chapter.

 Table 12-8
 Painting properties

Painting	
property name	Description
brush	Determines or changes the current brush shape used by the Brush tool.
centered	Determines or changes the Draw Centered setting.
filled	Determines or changes the Draw Filled setting.
grid	Determines or changes the painting Grid setting.
lineSize	Determines or changes the thickness of the lines drawn by the line and shape tools.
multiple	Determines or changes the Draw Multiple setting.
multiSpace	Determines or changes the amount of space left between edges of the multiple images drawn by the shape tools when the multiple property is true.
pattern	Determines or changes the current pattern used to fill shapes and to paint with the Brush tool.
polySides	Determines or changes the number of sides of the polygon created by the Regular Polygon tool.
textAlign	Determines or changes the way characters are aligned around the insertion point as you type them with the Paint Text tool.
textFont	Determine or changes the font in which Paint text appears.
textHeight	Determines or changes the space between baselines of Paint text.
textSize	Determines or changes the font size in which Paint text appears on the screen.
textStyle	Determines or changes the style in which Paint text appears.

Window Properties

Window properties let you find out about and change the way that the Message box, Tools palette, Patterns palette, card window, Scroll window, Navigator window, Message Watcher window, Variable Watcher window, stack window, and external windows are displayed. The window names these properties apply to are

card window	window "Navigator"
message [box]	window "patterns"
message [window]	window "Scroll"
msg	window stackName
pattern window	window "tools"
tool window	window "Variable Watcher"
window "Message Watcher"	window windowName

Message can be abbreviated msg.

The properties that apply only to the Message Watcher and Variable Watcher are listed in Table 12-11.

The window properties are listed in Table 12-9. If the property only applies to a specific window, it is called out in the description column. More detailed information about each property is given later in this chapter.

Table 12-9 Window properties

Window property name	Description
ID	Determines the permanent ID number of a window in the current stack.
loc[ation]	Determines or changes the location at which the window is displayed.
name	Determines the name of the specified window.
number	Determines the ordinal position in the window layers of any window on your screen.

continued

Table 12-9 Window properties (continued)

Window property name	Description
owner of window	Returns the name of the entity that created the window; this could be HyperCard or the name of an XCMD like Picture, etc.
	<i>Window</i> is an expression yielding a valid window identifier including either the name, ID, or layer number of the window.
rect[angle]	Determines or changes the size of card and stack window rectangles. See also Table 12-6.
scroll	Determines or changes the scroll of the specified card picture in the card window or picture in the specified picture window.
visible	Determines or changes whether a window is shown or hidden on the screen.
zoomed	Determines or changes whether a window is set to its maximum size and centered on the screen, as when the user clicks its zoom box.

Menu, Menu Bar, and Menu Item Properties

The menu item properties described in this section pertain to any specified menu item created with the put command. You can manipulate the properties of menu items from a script or from the Message box.

You can use the delete, disable, and enable commands to delete, disable, or enable the Tools, Patterns, Font, and Apple menus, but you cannot alter the contents of those menus with any other HyperTalk commands. You can also enable and disable those menus with the enabled property. However, you cannot manipulate the menu items of these menus.

Since there is only one menu bar per computer screen, this HyperCard object does not follow the HyperCard object identifier convention where objects can be specified by name, number, and ID. However, HyperTalk now supports both the visible and rectangle properties for the menu bar. Of these properties, visible is the only one that is modifiable. The rectangle properties are useful only for determining the size of the menu bar.

The menu, menu bar, and menu item properties are listed in Table 12-10. More detailed information about each property is given later in this chapter.

Table 12-10 Menu, menu bar, and menu item properties

Menu property name	Description
checkMark	Determines or changes the current checked value of a specified menu item; a Boolean value.
commandChar	Determines or changes the current character to be used with the Command key as a keyboard shortcut for a specified menu item. The commandChar property can be abbreviated cmdChar.
enabled	Determines or changes the enabled or disabled state of a specified menu or menu item; a Boolean value.
markChar	Determines or changes the current character that indicates a specified menu item is checked.
menuMessage	Determines or changes the current message to be sent when a specified menu item is chosen.
[english] name	Determines and changes the language for the specified menu or menu item name. The adjective english lets you code tests for the names of menus and menu items. This is a read-only property for the Tools, Patterns, Font, and Apple menus.
textStyle	Determines or changes the text style of the specified menu item.

Message Watcher and Variable Watcher Properties

The Message Watcher and Variable Watcher properties described in this chapter pertain to the built-in Message Watcher or Variable Watcher external windows. You can manipulate their properties from a script or from the Message box. You can also manipulate some Variable Watcher properties with the mouse.

The Message Watcher and Variable Watcher properties are listed in Table 12-11. More detailed information about each property is given later in this chapter.

 Table 12-11
 Message Watcher and Variable Watcher properties

Property name hBarLoc	Description Determines or changes the position of the horizontal bar in the Variable Watcher window.
hideIdle	Determines or changes whether the "Hide idle" checkbox is checked in the Message Watcher window.
hideUnused	Determines or changes whether the "Hide unused messages" checkbox is checked in the Message Watcher window.
rect	Determines or changes the size of the Variable Watcher window. Read-only property for the Message Watcher window.
vBarLoc	Determines or changes the position of the vertical bar in the Variable Watcher window.

HyperCard Property Descriptions

The rest of this chapter contains all of the HyperCard properties in alphabetical order for easy reference. The first line of each description tells which objects (stack, background, card, field, button, rectangle) or elements (menu item, Message Watcher, or Variable Watcher) or environment (global, window, or painting) the property applies to.

Some of the syntax statements and examples in this chapter use the soft return (\neg) character to continue long statements onto the next line. The soft return is used here because of the line-length limitations of the page format used in this chapter.

Address

APPLIES TO

Global environment

SYNTAX

put the address [of HyperCard]
get address [of HyperCard]

EXAMPLES

answer the address put the address into HCPathname

DESCRIPTION

You use the address property to ascertain the path of the currently executing HyperCard program. It returns the program path of your copy of HyperCard in the format "zone:Mac:HyperCard." For instance, if you're running HyperCard on a computer named Quill on a network called HyperText, the statement

put the address

yields

HyperText:Quill:HyperCard

If your computer is not on a network or the network only has one zone, the address property returns "*:MyMac:HyperCard". If your computer is also not named, it returns "*::HyperCard." This property works only when you are running under System 7.

NOTE

The address property is read-only, and it works only when HyperCard is running under System 7.

AutoHilite

APPLIES TO

Buttons

SYNTAX

set [the] autoHilite of button to boolean

Button is an expression that yields a button descriptor. *Boolean* is an expression that yields either true or false.

EXAMPLE

set autoHilite of button 6 to true

DESCRIPTION

You use the autoHilite property to determine or change whether the specified button highlights when that button is pressed.

NOTES

If a button is a member of a button family, then the press of the mouse button in the button's rectangle not only highlights that button and sets its hilite property to true but also sets the hilite property of the rest of the buttons in the button family to false.

The effect is that the button is highlighted (displayed in inverse video) when the user clicks it, thus giving visual feedback for the click action. If the button is part of a button family, clicking one of the button rectangles unhighlights the rest of the buttons in that family when the mouse button is released.

The default value of autoHilite is false.

The autoHilite property can be set to true or false from a script or by clicking the Auto Hilite checkbox in the Button Info dialog box.

See also the hilite and sharedHilite properties, later in this chapter.

AutoHilite 379

AutoSelect

APPLIES TO

Fields

SYNTAX

set [the] autoSelect of field to boolean

Field is an expression that yields a field descriptor. *Boolean* is an expression that yields either true or false.

EXAMPLE

set autoSelect of field "myListField" to true

DESCRIPTION

You use the autoSelect property to determine or change whether the specified field behaves as a list field.

NOTES

You can use the autoSelect property in conjunction with the lockText and dontWrap properties to make a field behave as a list. That is, if autoSelect, dontWrap, and lockText are true, when the user clicks on a line of text in the field, the entire line is selected (and therefore appears highlighted). If the multipleLines property is also true, the user can select multiple lines in the list field by holding down the Shift key while clicking or by dragging the mouse.

You can determine which lines the user selects in a list field using the selectedLine function. You can examine the contents of the lines the user selects in a list field using the selectedText function. You can select one or more lines in a list field from a script using the select command.

The autoSelect property for a button or field can be set to true or false from a script or by clicking the Auto Select checkbox in the Field Info dialog box. When you set a field's autoSelect property to true, HyperCard auto-

matically sets the field's dontWrap property to true. When you set a field's dontWrap property to false, HyperCard automatically sets the field's autoSelect property to false.

See also the dontWrap, lockText, and multipleLines properties, later in this chapter.

AutoTab

APPLIES TO

Fields

SYNTAX

set [the] autoTab of field to boolean

Field is an expression that yields a nonscrolling background or card field descriptor. *Boolean* is an expression that yields either true or false.

EXAMPLE

set autoTab of field 6 to true

DESCRIPTION

You use the autoTab property to determine or change whether the specified nonscrolling field will send the tabKey message to the current card. When the autoTab property is true, pressing Return with the insertion point in the last line of that field moves the insertion point to the next field on that card.

The normal tabbing order for fields is as follows: if the field you are leaving is a card field, the insertion point moves to the next higher-numbered card field or the lowest-numbered background field if no higher-numbered card field exists; if the field you are leaving is a background field, the insertion point moves to the next higher-numbered background field or to the lowest-numbered card field if no higher-numbered background field exists.

AutoTab 381

NOTE

The autoTab property can be changed from a script or by clicking the "Auto tab" checkbox in the Field Info dialog box.

BlindTyping

APPLIES TO

Global environment

SYNTAX

set blindTyping to boolean

Boolean is an expression that yields either true or false.

EXAMPLES

```
set blindTyping to true
set blindTyping to false
put the blindTyping -- puts current value into message box
```

DESCRIPTION

You use the blindTyping property to determine or change whether you can type messages into the Message box and send them (execute them) without having the Message box visible. Blind typing is available only if the user level is set to 5 (Scripting) and is usually set with a checkbox on the User Preferences card of the Home stack.

NOTES

The blindTyping property is set to the value saved on the User Preferences card of the standard Home stack by a startup handler in that stack.

If you try to type into the Message box when it's hidden and blindTyping is false, HyperCard makes the computer beep.

Bottom

APPLIES TO

Buttons, fields, windows

SYNTAX

```
set [the] bottom of object to number
```

Object yields one of the following:

a valid button descriptor in the current stack a valid field descriptor in the current stack message [box] or message [window] or window "message" pattern window or window "patterns" (the Patterns palette) tool window or window "tools" (the Tools palette) window "navigator" (the Navigator palette) scroll window or window "scroll" window "Fatbits" message watcher or window "message watcher" variable watcher or window "variable watcher" card window window stackName menubar window "Fatbits" window stackName scroll window or window "scroll"

Number is an expression that yields an integer representing the vertical offset in pixels from the top of the card window to the bottom of the specified object. When the specified object is a card window, the offset measures from the top of the screen. *StackName* is an expression that yields the name of an open stack.

Bottom 383

CHAPTER 12

Properties

EXAMPLES

```
set bottom of button "Mover" to 64 put bottom of card button 4 put the bottom of this card window set bottom of message box to 350
```

DESCRIPTION

You use the bottom property to determine or change the value of item 4 of the rectangle property (left, top, right, bottom) when applied to the specified object or window.

NOTES

Message can be abbreviated msg.

See also the rectangle property, later in this chapter.

BottomRight

APPLIES TO

Buttons, fields, windows

SYNTAX

```
set [the] bottomRight of object to point
```

Object yields one of the following:

```
a valid button descriptor in the current stack
a valid field descriptor in the current stack
message [box] or message [window] or window "message"
pattern window or window "patterns" (the Patterns palette)
```

```
tool window or window "tools" (the Tools palette)
window "navigator" (the Navigator palette)
message watcher or window "message watcher"
variable watcher or window "variable watcher"
card window
window stackName
scroll window or window "scroll"
window "Fatbits"
menubar
```

Point is an expression that yields a list of two integers separated by a comma. *Point* represents the horizontal and vertical offsets, respectively, in pixels from the top-left corner of the card to the bottom-right corner of the specified object. *StackName* is an expression that yields the name of an open stack.

EXAMPLES

```
set bottomRight of bkgnd button id 23 to 64,100 put bottomRight of button "Mover" put the bottomRight of window "Tools" set bottomRight of message box to 250,30
```

DESCRIPTION

You use the bottomRight property to determine or change the value of items 3 and 4 of the rectangle property (left, top, right, bottom) when applied to the specified object or window. The bottomRight property can be abbreviated botRight.

NOTES

Message can be abbreviated msg.

See also the rectangle property, later in this chapter.

BottomRight 385

Brush

APPLIES TO

Painting environment

SYNTAX

set [the] brush to number

Number is an expression that yields one of the numbers for the brush shapes shown in Figure 12-2.

EXAMPLE


set brush to 5

DESCRIPTION

You use the brush property to determine or to change the current brush shape used by the Brush tool. It's normally manipulated from the Brush Shape dialog box (shown in Figure 12-2) invoked by choosing Brush Shape from the Options menu or by double-clicking the Brush tool.

The value of the brush property can be any integer from 1 to 32, each representing a brush shape from the Brush Shape dialog box. If you set the value of brush to a number lower than 1 or higher than 32, it automatically reverts to 1 or 32, respectively. The default brush setting is 7.

Figure 12-2 Brush Shape dialog box and property values



CantAbort

APPLIES TO

Stacks

SYNTAX

set cantAbort of stack stackName to boolean

StackName is an expression that yields a stack name. *Boolean* is an expression that yields either true or false.

CantAbort 387

CHAPTER 12

Properties

EXAMPLES

```
set cantAbort of this stack to true
set cantAbort of stack "Shoes and socks" to false
```

DESCRIPTION

The cantAbort property pertains to any stack accessible to your Macintosh. It controls whether or not you can use Command-period to stop execution of a script. This property checks or unchecks the Can't Abort option in the Protect Stack dialog box.

NOTE

The cantAbort property should be used with caution.

CantDelete

APPLIES TO

Backgrounds, cards, stacks

SYNTAX

set cantDelete of object to boolean

Object is an expression that yields a valid background, card, or stack descriptor. *Boolean* is an expression that yields either true or false.

EXAMPLES

```
set cantDelete of first card to true
set cantDelete of this bkgnd to true
set cantDelete of this stack to false
```

DESCRIPTION

The cantDelete property pertains to any background, card, or stack accessible to your Macintosh. It controls whether or not the user can delete the specified object. The default value of cantDelete is false.

For backgrounds and cards, this property checks or unchecks the Can't Delete option in the object Info dialog box of the specified object.

For stacks, this property checks or unchecks the Can't Delete Stack option in the Protect Stack dialog box. When the cantDelete property for a stack is set to true, the Delete Stack command in the File menu is unavailable. (If the user has checked Can't Delete Stack, however, and a script sets cantModify to true and then false, Can't Delete Stack is left checked.)

NOTE

The cantDelete property of a stack is automatically set when the user sets the cantModify property.

CantModify

APPLIES TO

Stacks

SYNTAX

set cantModify of stack to boolean

Stack is an expression that yields a valid stack descriptor. *Boolean* is an expression that yields either true or false.

EXAMPLE

set cantModify of this stack to true

CantModify 389

DESCRIPTION

The cantModify property controls whether or not the stack can be changed in any way. This property checks or unchecks the Can't Modify Stack option and the Can't Delete Stack option in the Protect Stack dialog box. When the cantModify property for a stack is set to true, the Compact Stack command in the File menu is unavailable. (If the user has checked Can't Delete Stack, however, and a script sets cantModify to true and then false, Can't Delete Stack is left checked.)

NOTES

When you set cantModify for a stack from a script, you override whatever the user last set manually in the Protect Stack dialog box. This works in reverse as well. The user can override the script by resetting the value in the Protect Stack dialog box. Setting cantModify to false does not, however, override protection provided by media that are write-protected in other ways.

See also the cantDelete and userModify properties in this chapter.

CantPeek

APPLIES TO

Stacks

SYNTAX

set cantPeek of stack stackName to boolean

StackName is an expression that yields a stack name. *Boolean* is an expression that yields either true or false.

EXAMPLES

set cantPeek of this stack to true
set cantPeek of stack "TreeFrogs" to false

DESCRIPTION

The cantPeek property pertains to any stack accessible to your Macintosh. It controls whether or not you can view button outlines by pressing Command-Option, view field outlines by pressing Shift-Command-Option, or pop open scripts by clicking the mouse button while peeking. This property also checks or unchecks the Can't Peek option in the Protect Stack dialog box.

Centered

APPLIES TO

Painting environment

SYNTAX

set [the] centered to boolean

Boolean is an expression that yields either true or false.

EXAMPLES

set centered to true set centered to false

DESCRIPTION

You use the centered property to determine or to change the Draw Centered setting. When centered is set to true, shapes are drawn from the center rather than the corner. The default value of the centered property is false.

NOTE

You can also set the centered property by choosing Draw Centered on the Options menu.

Centered 391

CheckMark

APPLIES TO

Menu items

SYNTAX

set [the] checkMark of menuItem of menu to boolean

MenuItem is an expression that yields a menu item descriptor that is in the menu *menu*. *Menu* is an expression that yields a menu descriptor. *Boolean* is an expression that yields either true or false.

EXAMPLES

```
set checkMark of menuItem "Get Back" of menu ¬
   "Direction" to false
put the checkMark of menuItem "Get Back" of menu ¬
   "Direction"

if the checkMark of menuItem "Get Back" of ¬
   menu "Direction" is true then
   disable menuItem "Get Back" of menu "Direction"
end if
```

DESCRIPTION

You use the checkMark property to set or determine whether the checkmark character for a menu item is currently displayed. When the checkMark property is set to true, a checkmark character appears to the left of the menu item.

HyperCard does not automatically check or uncheck custom menu items each time a menu item is chosen, as it does for its own standard menus. Once an added menu item with a checkmark is chosen, the checkmark remains next to the menu item regardless of whether it is chosen again. You need to create handlers to keep track of the checked and unchecked menu items.

If you try to set or determine the checkMark property for a menu item that does not exist, HyperCard displays a "No such menu item" dialog box.

NOTE

See also the create menu and put commands in Chapter 10, "Commands," and the markChar property in this chapter.

CommandChar

APPLIES TO

Menu items

SYNTAX

set [the] commandChar of menuItem of menu to char

MenuItem is an expression that yields a menu item descriptor that is in the menu menu. Menu is an expression that yields a descriptor menu. Char is the character you want to use in combination with the Command key as the keyboard equivalent of the specified menu item.

EXAMPLES

```
set the commandChar of menuItem "Get Back" of menu¬
"Direction" to "D"

put the commandChar of menuItem "Get Back" of menu¬
"Direction"
```

DESCRIPTION

You use the commandChar property to set or determine the character to be used in combination with the Command key as the keyboard equivalent for a specified menu item. The character is displayed to the right side of the specified menu item along with the Command key symbol, **%**.

CommandChar 393

Menu items usually send messages when invoked. The menu item message is specified with the menuMessage property, which is described later in this chapter.

CommandChar can be abbreviated cmdChar.

NOTES

If you try to set or determine the commandChar property for a menuItem that does not exist, HyperCard displays a "No such menu item" dialog box.

Command-key equivalents do not work for menu items that have been deleted or disabled. However, with HyperCard's standard menu items, you can still send a doMenu command to invoke a menu item action even when the menu item has been deleted.

See also the menuMessage property later in this chapter and the create menu and put commands in Chapter 10, "Commands."

Cursor

APPLIES TO

Global environment

SYNTAX

set cursor to cursorType

CursorType yields one of the cursor names or numbers listed in the description.

EXAMPLES

set cursor to 4 set cursor to plus

DESCRIPTION

The cursor property determines the image that appears at the pointer location on the screen. The cursor setting is the ID number or name of a Macintosh 'CURS' resource, which must be available in the HyperCard file itself or in the current stack file. 'CURS' resources can be installed, removed, and created with a Macintosh resource editor.

HyperCard resets the cursor to the one for the current tool at idle, when no other action is happening. Each available cursor has a name, and some of them also have a number:

Number	Name
1	I-beam
2	cross
3	plus
4	watch
	hand
	arrow
	busy
	none

SCRIPT

The following handler spins the busy cursor two full revolutions. The busy cursor looks like a beach ball. Each time it is set, it turns 45° clockwise:

```
on spinMe
repeat 16 times
set the cursor to busy
wait 4 ticks
end repeat
end spinMe
```

NOTE

You can't get the cursor property or use it as a function; you can only set it.

Cursor 395

Debugger

APPLIES TO

Global environment

SYNTAX

```
set [the] debugger to debuggerName
```

DebuggerName is an expression that yields the name of the HyperCard debugger or a custom XCMD debugger.

EXAMPLES

```
set the debugger to "ScriptEditor"
set the debugger to "MyDebugger"
put the debugger
```

DESCRIPTION

You use the debugger property to set or determine the current debugger to use when debugging HyperTalk scripts. The default HyperTalk debugger is a built-in XCMD named ScriptEditor.

If you set a name for the debugger that HyperCard can't find, it uses the built-in HyperTalk debugger.

NOTE

See the description of the HyperTalk debugger in Chapter 3, and see Appendix A, "External Commands and Functions," for more information about custom debuggers.

DialingTime

APPLIES TO

Global environment

SYNTAX

set [the] dialingTime to numberOfTicks

NumberOfTicks is a positive integer representing ticks, or sixtieths of a second; the default value is 180 (3 seconds).

EXAMPLE

set the dialingTime to 300 -- wait 5 seconds

DESCRIPTION

This property is used to designate how long HyperCard waits before closing the serial connection to the modem after dialing.

NOTE

See also the dial command in Chapter 10, "Commands."

DialingTime 397

DialingVolume

APPLIES TO

Global environment

SYNTAX

set [the] dialingVolume to volume

Volume is an integer from 0 to 7, inclusive; the default value is 7.

EXAMPLE

if the dialingVolume is 7 -- too loud then set the dialingVolume to 4

DESCRIPTION

This property is used to control the volume of the touch tones generated through the Macintosh speaker by the dial command.

DontSearch

APPLIES TO

Backgrounds, cards, fields

SYNTAX

set [the] dontSearch of object to boolean

Object is an expression that yields any valid background, card, or field descriptor. *Boolean* is an expression that yields either true or false.

CHAPTER 12

Properties

EXAMPLES

set dontSearch of bkgnd 4 to true
put the dontSearch of bkgnd 3 into msg

if the short name of bkgnd field 2 of this cd is "Secrets" then set dontSearch of bkgnd field 2 to true

DESCRIPTION

You use the dontSearch property to set or determine whether or not the find command searches the specified background, card, or field in the current stack. When the dontSearch property of an object is set to true, the find command doesn't search that object. The default value for the dontSearch property is false.

When the dontSearch property of a background is set to true, the find command ignores all card or background fields on all of the cards of the specified background.

NOTE

You can set the dontSearch property from a script or by clicking the Don't Search checkbox in the object's Info dialog box.

DontWrap

APPLIES TO

Fields

SYNTAX

set [the] dontWrap of field to boolean

Field is an expression that yields any valid field descriptor. *Boolean* is an expression that yields either true or false.

DontWrap 399

CHAPTER 12

Properties

EXAMPLE

set the dontWrap of bkgnd fld 4 to true

DESCRIPTION

You use the dontWrap property to determine or change the dontWrap value for a field in the current stack. When the dontWrap property of a field is set to true, the text in the specified field does not wrap around to the next line at the boundary of the field. The default value for the dontWrap property is false (wrap at the boundary of the field).

NOTES

You can also set the dontWrap property by clicking the Don't Wrap checkbox in the Field Info dialog box. When you set a field's autoSelect property to true, HyperCard automatically sets dontWrap to true. When you set a field's dontWrap property to false, HyperCard automatically sets autoSelect to false.

DragSpeed

APPLIES TO

Global environment

SYNTAX

set dragSpeed to *number*

Number is an expression that yields a positive integer; 1 is the slowest possible speed.

EXAMPLE

set dragSpeed to 120

DESCRIPTION

The dragSpeed property determines how many pixels per second the pointer moves when manipulated by all subsequent drag commands.

SCRIPT

The following handler, placed in a button's script, creates a new card to draw on, sets a slow dragSpeed value, and slowly draws a diamond shape. It then fills the diamond with a pattern, waits a short time, deletes the card, and sends you back to the card where you started. You can change the dragSpeed property to drag faster by increasing the dragSpeed value, or slower by decreasing the value.

```
on mouseUp
  push card
  doMenu "New Card"
   set dragSpeed to 60
   choose line tool
  drag from 100,50 to 50,100
  drag from 50,100 to 100,150
  drag from 100,50 to 150,100
  drag from 100,150 to 150,100
   choose bucket tool
   set pattern to 10
   click at 100,100
  reset paint
  wait 25 ticks
  doMenu "Delete Card"
   choose browse tool
  pop card
end mouseUp
```

DragSpeed affects all of the Paint tools except the Bucket and Text tools. At idle time, HyperCard resets the dragSpeed property to 0. In this case, a value of 0 represents the fastest possible speed.

DragSpeed 401

EditBkgnd

APPLIES TO

Global environment

SYNTAX

set editBkgnd to boolean

Boolean is an expression that yields either true or false.

EXAMPLES

set editBkgnd to true
set editBkgnd to false

DESCRIPTION

The editBkgnd property determines where any painting or creating of buttons or fields happens—on the current card (false) or on its background (true). It's usually set with the Edit menu and is available only when the user level is Painting (3) or higher. The default setting is false (editing on the card).

Enabled

APPLIES TO

Menus, menu items, and buttons

SYNTAX

```
set [the] enabled of [menuItem of] menu to boolean set [the] enabled of button to boolean
```

MenuItem is an expression that yields the descriptor of a menu item that is in the specified menu. Menu is an expression that yields a menu descriptor. Button is an expression that yields a button descriptor. Boolean is either true or false.

EXAMPLES

```
set the enabled of button "Go For It" to true set enabled of menuItem 4 of menu "Utilities" to false the enabled of menu "Home" the enabled of menuItem "Repeat" of menu "Control" put the enabled of the fifth menu
```

DESCRIPTION

You use the enabled property to set or determine the state (either enabled or disabled) of a specified menu, menu item, or button. When you create any of these, the default for the enabled property is true and the menu, menu item, or button appears in solid outline (active). If you set enabled to false, the object is dimmed (disabled).

When the enabled of a button is false, it does not receive mouseDown, mouseStillDown, mouseUp, or mouseDoubleClick messages. However, the button continues to receive mouseEnter, mouseWithin, and mouseLeave messages.

NOTES

If you try to set or determine the enabled property for a menu, menu item, or button that does not exist, HyperCard displays a dialog box informing you of your error.

Command-key equivalents do not work on custom menu items that have been disabled.

See also the menuMsg property in this chapter and the create menu, disable, enable, and put commands in Chapter 10, "Commands."

Enabled 403

Environment

APPLIES TO

Global environment

SYNTAX

put [the] environment

EXAMPLE

if the environment is "development" then set userLevel to 5

DESCRIPTION

The environment property returns development if the currently running version of HyperCard is the fully enabled development version, and player if the HyperCard Player is running.

Family

APPLIES TO

Buttons

SYNTAX

```
set [the] family of buttonName to number
put [the] family of buttonName
```

ButtonName is an expression that specifies either a background or card button descriptor; if you don't specify whether the owner of a family is a card or background, the default owner is the card. Number is a positive integer between 1 and 15, inclusive, which represents the family number of a group of buttons; the number 0 indicates that the specified button does not belong to a family.

EXAMPLES

```
set the family of button 6 to 7 set the family of button "Home" to 0 --no family
```

SCRIPT

The following example handler sets up a family of radio buttons so they automatically function properly, with only one highlighted at a time:

```
on setFamily
  repeat with i = 1 to 5
    set the family of card button i to 2
  end repeat
end setFamily
```

DESCRIPTION

HyperCard uses the family property to group related buttons of a card or background. This grouping provides a convenient means to make sure that only one button of a group is highlighted at one time. When someone clicks one of the buttons in a family, then that button's hilite property is set to true and the hilite property of any previously highlighted button in that family is automatically set to false.

You can assign any number of buttons to a family and can have up to 15 families of buttons on any card or background. You can use the set command to assign a button to a family from a script, or you can do it manually by using the Family pop-up menu in each button's Button Info dialog box.

NOTES

Buttons can be members of either a family of background buttons or a family of card buttons but cannot belong to both families. A group of card buttons of family 6 are totally unrelated to the family 6 background buttons.

You can also use the Family pop-up menu in the Button Info dialog box to assign a family to a button. When you assign a button to a family, HyperCard sets its autoHilite property to true. HyperCard preserves the state of the

Family 405

CHAPTER 12

Properties

autoHilite property of a button existing prior to assigning a family; if you later select None in the Family pop-up menu, HyperCard restores the former autoHilite state.

See also the sharedHilite and autoHilite properties in this chapter.

Filled

APPLIES TO

Painting environment

SYNTAX

set [the] filled to boolean

Boolean is an expression that yields either true or false.

EXAMPLES

set filled to true set filled to false

DESCRIPTION

You use the filled property to determine or to change the Draw Filled setting. When filled is true, the current pattern on the Patterns palette is used to fill shapes as they are drawn. The default value of the filled property is false.

NOTE

You can also set the filled property by choosing Draw Filled from the Options menu.

FixedLineHeight

APPLIES TO

Fields

SYNTAX

set [the] fixedLineHeight of field to boolean

Field is any expression that yields the descriptor of a field. *Boolean* is an expression that yields either true or false.

EXAMPLES

```
set the fixedLineHeight of field 6 to true
get fixedLineHeight of bkgnd field 3

if fixedLineHeight of field 6 is false then
   put "fixedLineHeight is false"
end if
```

DESCRIPTION

You use the fixedLineHeight property to determine or specify whether a field has fixed line spacing when the text is of different sizes. If widely varying sizes of text are going to be used in a field, the value of the fixedLineHeight property needs to be set to false. The default setting of fixedLineHeight is false.

NOTES

You can also change the value of the fixedLineHeight property by clicking the Fixed Line Height checkbox in the Field Info dialog box.

The fixedLineHeight property is true for fields created with versions of HyperCard earlier than 2.0. When the same stacks are converted to the HyperCard 2.0 format, fixedLineHeight remains true.

FixedLineHeight 407

CHAPTER 12

Properties

The fixedLineHeight property is set to true when showLines is set to true. If fixedLineHeight is set to false, showLines is also set to false.

See the textSize property, later in this chapter, for more information on how to set different sizes of text in fields.

FreeSize

APPLIES TO

Stacks

SYNTAX

put [the] freeSize of stack stackName [into container]

StackName is an expression that yields any stack name currently available to HyperCard, and *container* is any field, variable, the selection, or the Message box.

EXAMPLE

put freeSize of stack "dogfeathers" into field "Size"

DESCRIPTION

You use the freeSize property to determine the amount of free space of the specified stack in bytes. (Free space changes in a stack each time you add or delete an object.)

SCRIPT

The following handler compacts a stack based on a specified freeSize value:

```
on closeStack
  if the freeSize of this stack > 24000
  then doMenu "Compact Stack"
end closeStack
```

NOTE

The freeSize property can be changed only by choosing Compact Stack from the File menu (or executing the HyperTalk command doMenu Compact Stack), which changes its value to 0, or by editing the stack.

Grid

APPLIES TO

Painting environment

SYNTAX

set [the] grid to boolean

Boolean is an expression that yields either true or false.

EXAMPLES

set grid to true set grid to false

DESCRIPTION

You use the grid property to determine or to change the painting grid setting. When the value of grid is true, movement of the Rectangle, Round Rect, Oval, and Polygon Paint tools is constrained to 8-pixel intervals. The default value of the grid property is false.

NOTE

You can set the grid property from a script or by choosing Grid from the Options menu.

Grid 409

HBarLoc

APPLIES TO

Variable watcher windows

SYNTAX

set [the] hBarLoc of window "Variable Watcher" to number

Number is an expression that yields a positive integer that represents the offset in pixels from the bottom of the Variable Watcher window title bar to the horizontal bar in the window.

EXAMPLES

set the hBarLoc of window "Variable Watcher" to 123 put the hBarLoc of window "Variable Watcher"

DESCRIPTION

You use the hBarLoc property to determine or to change the current position of the horizontal bar in the Variable Watcher window. The horizontal bar determines how many of the variable name and value fields are visible in the Variable Watcher window.

NOTES

The built-in Variable Watcher window is a HyperCard XCMD. It can be replaced with a custom variable watcher XCMD by setting the variableWatcher property to the name of a variable watcher XCMD.

Custom variable watcher XCMDs can respond to or ignore the hBarLoc property.

For more information about creating and calling a custom variable watcher XCMD, see Appendix A, "External Commands and Functions."

See also the description of the Variable Watcher in Chapter 3, "The Scripting Environment," and the rect, variableWatcher, and vBarLoc properties, later in this chapter.

Height

APPLIES TO

Buttons, cards, fields, menu bar, windows

SYNTAX

```
set [the] height of object to number
put [the] height of object
```

Object is an expression that yields any valid button, card, field, or window descriptor, or the word menubar.

Number is an expression that yields a positive integer. *Number* represents the total number of pixels in the vertical height of the specified object.

EXAMPLES

```
set the height of bkgnd button 2 to 60
set the height of bkgnd field "phoneList" to 220
put the height of window "Home"
set the height of cd window to height of cd window div 2
```

DESCRIPTION

You use the height property to determine or change the vertical distance in pixels occupied by the rectangle of the specified button, field, or window. You can change the height of a button, field, or window rectangle with the set command.

When you set the height of a button, field, or window, its location property (center coordinate) remains the same.

NOTE

See also the rectangle property, later in this chapter.

Height 411

HideIdle

APPLIES TO

Message watcher windows

SYNTAX

set [the] hideIdle of window messageWatcher to boolean

MessageWatcher is an expression that yields the name of a message watcher window. *Boolean* is an expression that yields either true or false.

EXAMPLES

set the hideIdle of window "Message Watcher" to true put hideIdle of window "Message Watcher"

DESCRIPTION

You use the hideIdle property to determine or change whether the "Hide idle" checkbox is checked in a message watcher window.

The name of the message watcher window can be either the built-in HyperCard Message Watcher, window "Message Watcher", or the name of a custom message watcher window that supports a "Hide idle" checkbox.

NOTES

See also the description of the Message Watcher in Chapter 3, "The Scripting Environment." For more information about creating a custom message watcher XCMD, see Appendix A, "External Commands and Functions."

See also the hideUnused and messageWatcher properties, later in this chapter.

HideUnused

APPLIES TO

Message watcher windows

SYNTAX

set [the] hideUnused of window messageWindow to boolean

MessageWindow is an expression that yields the name of a message watcher window. *Boolean* is an expression that yields either true or false.

EXAMPLES

set the hideUnused of window "Message Watcher" to true put hideUnused of window "Message Watcher"

DESCRIPTION

You use the hideUnused property to determine or change whether the "Hide unused messages" checkbox is checked in a message watcher window.

The name of the message watcher window can be either the built-in HyperCard Message Watcher, window "Message Watcher", or the name of a custom message watcher window that supports the "Hide unused messages" checkbox.

NOTE

See also the description of the Message Watcher in Chapter 3, "The Scripting Environment." For more information about creating a custom message watcher XCMD, see Appendix A, "External Commands and Functions."

See also the hideIdle and messageWatcher properties in this chapter.

HideUnused 413

Hilite

APPLIES TO

Buttons

SYNTAX

set [the] hilite of button to boolean

Button is an expression that yields a background button or card button descriptor. *Boolean* is an expression that yields either true or false.

EXAMPLES

set hilite of button "You're on" to true put the hilite of bkgnd button 3

DESCRIPTION

You use the hilite property to determine or to change whether the specified button is highlighted (displayed in inverse video). The default value of the hilite property is false. To see what highlighting for the various button styles looks like, see the *HyperCard Reference*.

NOTES

The hilite property can be changed using the set command, either from a script or from the Message box, or, if the autoHilite property is true, by pressing the button. In that case, for all styles of buttons except checkboxes and radio buttons, the hilite property becomes true when you press the button, and it becomes false when you release it.

For checkboxes and radio buttons with their autoHilite property set to true, the hilite property toggles to its opposite state when the button is clicked and stays that way until it is clicked again. That is, when a checkbox is highlighted, it appears with an "X" checkmark in its box; when it's not highlighted, the checkmark does not appear. If autoHilite is true, an unselected checkbox displays an "X" when you click it; if you click it again,

the "X" disappears. The appearance of the checkmark correlates to the state of the button's hilite property. The situation is similar for radio buttons, except that the true highlighted state is indicated by a solid dot inside the button's circle.

See also the description of the autoHilite, family, and sharedHilite properties in this chapter.

Icon

APPLIES TO

Buttons

SYNTAX

set [the] icon of button to designator

Button is an expression that yields a background or card button descriptor. Designator yields the ID number of an available icon resource or the name of an icon (if it has one).

EXAMPLES

```
set icon of button "Instant" to 5005
set icon of button "Instant" to "DoGood"
put the icon of button "Instant"
```

DESCRIPTION

You use the icon property to determine or to change the icon, if any, that is displayed with the specified button. If a button has no icon, the icon property is 0. An icon is identified by its ID number or by its name, if it has one.

Icons are small images that exist as Macintosh files and are editable with the HyperCard icon editor. For an icon to be displayed on a button, its resource must be available in the current stack, another stack in the hierarchy, or the HyperCard application.

Icon 415

NOTES

The icon can also be changed by clicking the Icon button in the Button Info dialog box, which brings up another dialog box that displays the available icons graphically. When you click an icon in the icon display dialog box, the ID and name are displayed in the upper-left corner. The icon name is displayed in the dialog box only if the icon has a name.

If you use the put command with the icon property, you get the ID number of the icon, not the name. You cannot retrieve an icon name for a button.

ID

APPLIES TO

Backgrounds, buttons, cards, fields, menus, windows, HyperCard

SYNTAX

```
put [the] [adjective] ID of object | windowName | HyperCard ¬
    [into container]
```

Adjective is one of the long, short, and abbreviated modifiers as described in the section "Object ID Numbers" in Chapter 5. Object is an expression that yields any valid background, button, card, or field descriptor. WindowName yields a valid window descriptor. A container is the selection, a field, a variable, or the Message box.

EXAMPLES

```
put the ID of HyperCard
put the long ID of bkgnd 3
if the ID of bkgnd 1 is 2282 then answer "Welcome Home"
put the short ID of card 35
put the id of field 1 into msg
put the ID of bkgnd button 3 into field "Button IDs"
put the short ID of card 35 after line 2 of field 2
put the id of window "DogPicture"
```

DESCRIPTION

You use the ID property to determine the permanent ID number of any background, button, card, field, or window in the current stack.

You can also use the ID property to determine the application signature of HyperCard. Unless the current stack is running under a stand-alone application whose application signature has been modified, the ID property of HyperCard will contain WILD.

You can't use the set command to change the ID of any object.

SCRIPT

The following script uses the name and ID properties to produce a list of button names and IDs. You need to create a field for the button name and ID list.

```
on mouseUp

put empty into field "MyField"

repeat with nums = 1 to the number of buttons

put "Button name" && quote & short name of button ¬

nums & quote && "has id number" && id of button ¬

nums & return after field "MyField"

end repeat

end mouseUp
```

You can place the script in any button or field, then click the button or field to get a list of all the buttons names and IDs on the current card. If you put the script into the same field you want to put the list into, be sure to set the lockText property of that field to true, so that the field receives the mouseUp message. Also, change all references to the field descriptor field "MyField" to match the descriptor for the field you created for the list. If the field created for the list is the same field the script is in, you can use me in place of field "MyField".

NOTES

When HyperCard retrieves the ID of a window, field, or button, it ignores any adjectives and always reports the ID as an unlabeled number. For instance, if

ID 417

you execute the following command line from the Message Box, you will get a number result like the one shown on the line following it:

```
put the long id of window "Home"
10883218
```

If you ask for a long ID of a card, HyperCard returns a labeled response, as shown in this example:

```
put the long id of cd 1
```

The response returned is

```
card id 3916 of stack "oh dear:Desktop Folder:Home"
```

You should also be aware that a window must already exist before you call for its ID. Many windows go out of existence when you click their close boxes and are created by XCMDs each time you call for them.

ItemDelimiter

APPLIES TO

Global environment

SYNTAX

```
the itemDelimiter
set [the] itemDelimiter to character
```

Character yields an ASCII character or a constant that represents an ASCII character.

EXAMPLES

```
if the itemDelimiter <> comma
then set the itemDelimiter to comma
set itemDelimiter to "#"
```

DESCRIPTION

You use the itemDelimiter property to change the character that delimits items in a list. The default value is comma, and, if changed, the value will revert to comma on idle.

Changing the item delimiter has no effect on comma-delimited HyperCard structures such as dateItems, location, and rectangle.

SCRIPT

The following card script's function handler returns the pathname of the current stack without the stack name (useful when you need to refer to other files at the same level). You can call this function handler by typing shortPath() in the Message box and then pressing Return.

```
function shortPath -- Card handler
    -- Save old item delimiter value for resetting later
    put the itemDelimiter into oldDelimiter
    put the value of word 2 of the long name ¬
        of this stack into longName
          -- saves: Volume:Stacks Folder:This Stack
          -- reset item delimiter
        set itemDelimiter to colon
        delete last item of longName
          -- 'Volume:Stacks Folder' goes in longName
          -- Reset delimiter
        set itemDelimiter to oldDelimiter
        return longName & colon
end shortPath
```

The following part of a script is useful for retrieving the name of a program from a colon-delimited list on machines running system software version 7.0 or later:

```
set the itemDelimiter to ":"
answer program "Select a program"
get the last item of it
```

ItemDelimiter 419

Language

APPLIES TO

Global environment

SYNTAX

set language to languageName

LanguageName is a text string that yields English or a language for which there is a HyperTalk translator resource.

EXAMPLE

set language to French

DESCRIPTION

You use the language property to choose a HyperTalk translator, which is a code resource that translates between HyperTalk and a foreign-language version of HyperTalk. If the language property is not English, when the user invokes the script editor to view a script, HyperCard translates it to the specified language. When the user closes the script, HyperCard translates it back to English HyperTalk before storing it with its object.

NOTES

The language property refers only to the HyperTalk scripting language; it has no effect on scripts written in other scripting languages.

The languages available depend on the script translator resources available in the current stack, another stack in the hierarchy, or the HyperCard application. The default setting is English, and it's always available.

Left

APPLIES TO

Buttons, fields, menu bar, windows

SYNTAX

```
set [the] left of object to number
```

Object yields one of the following:

a valid button descriptor in the current stack
a valid field descriptor in the current stack
message [box] or message [window] or window "message"
pattern window or window "patterns" (the Patterns palette)
tool window or window "tools" (the Tools palette)
window "navigator" (the Navigator palette)
scroll window or window "scroll"
window "Fatbits"
message watcher or window "message watcher"
variable watcher or window "variable watcher"
card window
window stackName

Number yields an integer that is the horizontal offset in pixels from the left side of the card to the left side of the object. When the object is the card window, the offset is relative to the left side of the screen. *StackName* is an expression that yields the name of an open stack.

EXAMPLES

```
set left of button 2 to 34
put left of button 2
put the left of card field 3
set left of tool window to 65
```

Left 421

DESCRIPTION

You use the left property to determine or change the value of item 1 of the rectangle property (left, top, right, bottom) when applied to the specified object or window. The left property of an object can also be set to a value off the screen. Setting the left property of an object to a value off the screen makes the object seem hidden.

NOTES

The left of the menu bar is a read-only property.

Message can be abbreviated msg.

See also the rectangle property, later in this chapter.

LineSize

APPLIES TO

Painting environment

SYNTAX

set [the] lineSize to number

Number yields a positive integer that is the total number of pixels in a line's width. It can be 1, 2, 3, 4, 6, or 8.

EXAMPLE

set lineSize to 8

DESCRIPTION

You use the lineSize property to determine or to change the thickness of the lines drawn by the Line and Shape tools. The default value of the lineSize property is 1. If you set the value of lineSize to a number lower than 1 or higher than 8, it automatically reverts to 1 or 8, respectively.

NOTE

You can also set the lineSize property by choosing Line Size from the Options menu or double-clicking the Line tool.

Location

APPLIES TO

Buttons, fields, menu bar, windows

SYNTAX

set loc[ation] of object to point

Object yields one of the following:

a valid button descriptor in the current stack
a valid field descriptor in the current stack
message [box] or message [window] or window "message"
pattern window or window "patterns" (the Patterns palette)
tool window or window "tools" (the Tools palette)
window "navigator" (the Navigator palette)
scroll window or window "scroll"
window "Fatbits"
message watcher or window "message watcher"
variable watcher or window "variable watcher"
card window
window stackName
windows created with the picture command

Point is an expression that yields two integers separated by a comma. *StackName* is an expression that yields the name of a stack in quotation marks.

Location 423

EXAMPLES

```
set loc of tool window to "100,100"
put the loc of field 3
put the loc of pattern window
set loc of msg to 30,150
set the loc of card window to 48,90
set the loc of window "Navigator" to "45,60"
set the loc of scroll window to "165,45"
```

DESCRIPTION

The location property sets or retrieves the location at which the window or object is displayed.

The point represents the horizontal and vertical offsets, respectively, in pixels from the top-left corner of the card to the center of a resizable window (a button or field) or the top-left corner of a nonresizable window (Tools palette, Patterns palette, Message box, Navigator palette, or Scroll window), disregarding the drag bar at the top of the window. The value for *point* must be within quotation marks for the Navigator palette.

The point for a card window represents the horizontal and vertical offsets, respectively, in pixels from the top-left corner of the screen to the top-left corner of the card window.

The point for windows created with the picture command represents the horizontal and vertical offsets, respectively, in pixels from the top-left corner of the current card window to the top-left corner of the picture window. The value for *point* must be within quotation marks.

NOTES

The location of the menu bar is a read-only property.

If you always put the value of *point* within quotation marks, it works with all of the HyperCard objects and elements for which you can set the location. An example that places quoted values in variables is shown under the multiSpace property, later in this chapter.

If you want to move a card on the screen, you set the location property for the card window of the current stack, not the location of the card.

The number that represents the horizontal offset for the card window is shifted to the closest multiple of 16 regardless of how you set it. For example, the statement set the loc of cd window to 50,90 would result in the card location of 48,90. It would shift to the next 16 pixels when the horizontal value of the location property reached the halfway point to the next higher or lower 16 pixels. For example, a horizontal value of 38 would shift the card window left to a horizontal offset of 32.

When you move a card window with the location property, the system message moveWindow is sent. The moveWindow message is also sent when you drag the window to a new location, zoom it in or out with the zoom box, causing the location property to change, or show the card window at a new location with the show command.

See also the rectangle property later in this chapter; the palette, picture, and show commands in Chapter 10, "Commands"; and the moveWindow system message in Chapter 8, "System Messages."

LockErrorDialogs

APPLIES TO

Global environment

SYNTAX

set lockErrorDialogs to boolean

Boolean is an expression that yields either true or false.

EXAMPLE

set lockErrorDialogs to true

DESCRIPTION

You use the lockErrorDialogs property to prevent HyperCard from displaying error dialogs when a script causes an error. This property is set to false at idle time, so it has no effect if you enter it through the Message box.

LockErrorDialogs 425

NOTES

When the lockErrorDialogs property is set to true, HyperCard sends the message errorDialog *errorMessage* to the current card instead of displaying the error dialog.

Errors produced through the Message box still get dialogs, regardless of the setting of lockErrorDialogs.

LockMessages

APPLIES TO

Global environment

SYNTAX

set lockMessages to boolean

Boolean is an expression that yields either true or false.

EXAMPLES

set lockMessages to true set lockMessages to false

DESCRIPTION

You use the lockMessages property to prevent HyperCard from sending all open, close, suspend, and resume system messages. The default setting is false. HyperCard resets lockMessages to false at idle time (in effect, at the end of all pending handlers).

NOTE

Setting the lockMessages property to true speeds up execution of scripts in which you go to cards, and those in which you create and delete cards, backgrounds, and stacks, because it prevents HyperCard from sending

messages such as openCard, closeCard, and so on. The lockMessages property does not affect new and delete system messages such as newCard and deleteField. Setting the lockMessages property to true also prevents execution of handlers invoked by system messages, which may be used to set up an environment—hiding the Message box, and so on. It's particularly useful when you want to go to a card to retrieve or write some information, but you don't want to stay there.

LockRecent

APPLIES TO

Global environment

SYNTAX

set lockRecent to boolean

Boolean is an expression that yields either true or false.

EXAMPLE

set lockRecent to true

DESCRIPTION

You use the lockRecent property to prevent HyperCard from adding miniature representations to the Recent Cards dialog box. (The Recent Cards dialog box is invoked by Command-R or by choosing Recent from the Go menu.)

The default setting is false. HyperCard resets lockRecent to false at idle time (in effect, at the end of all pending handlers).

LockRecent 427

NOTES

LockRecent is set to true when the lockScreen property is set to true regardless of the current setting of lockRecent. Setting the lockRecent property to true speeds up execution of scripts in which you go to cards.

See also the next property, lockScreen.

LockScreen

APPLIES TO

Global environment

SYNTAX

set lockScreen to boolean

Boolean is an expression that yields either true or false.

EXAMPLE

set lockScreen to true

DESCRIPTION

You use the lockScreen property to prevent HyperCard from updating the screen when you go to another card.

The default setting is false. HyperCard resets lockScreen to false at idle time (in effect, at the end of all pending handlers).

NOTES

Setting the lockScreen property to true enables you to open different cards without displaying them on the screen, and it speeds up execution of scripts in which you go to cards. For example, you can lock the screen, then go to another

card to read information out of a field, then return to the first card without having the second card appear to the user.

To ensure that the display is unlocked, each set lockScreen to true must be balanced with a set lockScreen to false.

See also the lock and unlock commands in Chapter 10.

LockText

APPLIES TO

Fields

SYNTAX

set [the] lockText of field to boolean

Field is an expression that yields any valid card field or background field descriptor. *Boolean* is an expression that yields either true or false.

EXAMPLES

```
set the lockText of field "Glossary" to true set the lockText of field "Glossary" to false
```

DESCRIPTION

You use the lockText property to prevent or allow editing of text within a field in the current stack.

When the Browse tool is selected and the pointer is moved over an unlocked field, the pointer changes to an I-beam; clicking then lets you edit the text in the field. If the field is locked (lockText is true), the cursor doesn't change, and the text cannot be edited. A locked field also receives the messages mouseDown, mouseStillDown, and mouseUp when you click it. The default value of lockText is false.

LockText 429

NOTES

You can also change this property by clicking the Lock Text checkbox in the Field Info dialog box.

When the cantModify property for the current stack is true and the userModify property is false, no changes can be made in a field. When cantModify is true, userModify is true, and lockText is false, any editing done in a field is lost when the user moves to another card.

LongWindowTitles

APPLIES TO

Global environment

SYNTAX

set [the] longWindowTitles to boolean

Boolean is an expression that yields either true or false.

EXAMPLES

set longWindowTitles to true
set the longWindowTitles to false

DESCRIPTION

You use the longWindowTitles property to determine whether the stack name or the full pathname appears in the title bar of the card window.

The default value of longWindowTitles is false and shows only the stack name in the title bar. If longWindowTitles is set to true, the full pathname of the stack is shown in the card window title bar.

NOTE

See also Chapter 5, "Referring to Objects, Menus, and Windows," for more information about stack names and the full pathname of a stack.

MarkChar

APPLIES TO

Menu items

SYNTAX

set [the] markChar of menuItem of menu to char

MenuItem is an expression that yields a menu item descriptor that is in the menu menu. Menu is an expression that yields a menu descriptor. Char is an expression that yields the checkmark character you want to display in the menu to the left side of the specified menu item when it is chosen.

EXAMPLES

set markChar of menuItem "Blue" of menu "Colors" to >
put the markChar of menuItem 4 of the sixth menu

DESCRIPTION

You use the markChar property to set or determine the checkmark character for a menu item. When the markChar of a menu item is not empty, the menu item's checkMark property is true. To remove a checkmark character from a menu item, set its markChar property to empty or set its checkMark property to false.

HyperCard does not automatically check or uncheck custom menu items each time a menu item is chosen, as it does for its own standard menus. Once an added menu item with a checkmark is chosen, the checkmark remains next to the menu item regardless of whether it is chosen again. You need to create handlers to keep track of checked and unchecked custom menu items.

If you try to set or determine the markChar property of a menu item that does not exist, HyperCard displays a "No such menu item" dialog box.

NOTE

See also the put command in Chapter 10, "Commands," and the checkMark property, earlier in this chapter.

MarkChar 431

Marked

APPLIES TO

Cards

SYNTAX

set [the] marked of card to boolean

Card is an expression that yields the descriptor of any card within the current stack. *Boolean* is an expression that yields either true or false.

EXAMPLES

put [the] marked of card 35
set marked of card 2 to true
if the marked of this card is true then doSomething

DESCRIPTION

You use the marked property to set or determine the marked state of any card in the current or specified stack. The default value of marked is false. A marked card or group of marked cards can be referred to in complicated searches and when printing.

NOTES

You can also set the marked property with the Card Marked option in the Card Info dialog box.

See also the mark and unmark commands in Chapter 10, "Commands."

MenuMessage

APPLIES TO

Menu items

SYNTAX

set [the] menuMessage of menuItem of menu to message

MenuItem is an expression that yields a menu item descriptor that is in the menu menu. Menu is an expression that yields a menu descriptor. Message is an expression that yields a message to be sent by the menu item.

EXAMPLES

set menuMessage of menuItem 7 of menu 10 to doMenu "Prev" put the menuMessage of menuItem "Next" of menu "Pictures" put "Maple" after menu "Syrups" with menuMsg "go card 4"

DESCRIPTION

You use the menuMessage property to specify the message sent to the current card by a specified menu item. You can also specify a menu message for a menu item when you create a menu item with the put command.

You may respond to the choosing of menu items in your scripts in two ways. Whenever a menu item is chosen, HyperCard sends a doMenu message. You can respond to the choosing of menu items by writing doMenu handlers in your scripts (this is the first way). If the doMenu message is not intercepted by any script, HyperCard checks the menu item's menuMessage property. If menuMessage is not empty, HyperCard sends that message to the current card. Therefore you can respond to the choosing of menu items by assigning them menu messages (this is the second way). If menuMessage is empty, HyperCard checks whether the item is one of its standard menu items. If it is a standard menu item, the standard behavior of that menu item occurs.

MenuMessage 433

Custom menu items with the same name as a standard HyperCard menu item inherit the standard behavior of the HyperCard menu item. For example, if you add Background to a menu called Special, choosing it has the same effect as choosing the standard Background command from the Edit menu, unless you assign a custom menu message or intercept the doMenu message.

If you try to set or determine the menuMessage property of a menu item that does not exist, HyperCard displays a "No such menu item" dialog box.

NOTES

In the case of HyperCard's standard menu items, the doMenu command works even when the item is deleted. For example, if the following handler is executed, HyperCard exits to the Finder:

```
on mouseDown
  delete menuItem "Quit HyperCard" from menu "File"
  doMenu "Quit HyperCard"
end mouseDown
```

The menuMessage property returns values for standard HyperCard menus only if they have been changed from the default HyperCard menu messages.

MenuMessage can be abbreviate menuMsg.

You can't set the menuMessage property of menu items in the Tools, Patterns, Font, or Apple menus, except for the menuMessage property of the About HyperCard menu item in the Apple menu, which you can set.

See also the create menu, delete, doMenu, and put commands in Chapter 10, "Commands."

MessageWatcher

APPLIES TO

Global environment

SYNTAX

set [the] messageWatcher to name

Name is an expression that yields a valid message watcher XCMD name.

EXAMPLES

set messageWatcher to "MyWatcher"
put the messageWatcher

DESCRIPTION

You use the messageWatcher property to determine or to change the current message watcher. The default value is messageWatcher, the built-in message watcher XCMD. You display the current message watcher with the show command or by setting the visible property of the message watcher window to true.

The built-in message watcher is a HyperCard XCMD. It can be replaced with a custom message watcher XCMD by setting the messageWatcher property to the name of a custom message watcher XCMD.

NOTES

See also the description of the Message Watcher in Chapter 3, "The Scripting Environment."

For more information about creating a custom message watcher XCMD, see Appendix A, "External Commands and Functions."

MessageWatcher 435

Multiple

APPLIES TO

Painting environment

SYNTAX

set [the] multiple to boolean

Boolean is an expression that yields either true or false.

EXAMPLES

set multiple to true set multiple to false

DESCRIPTION

You use the multiple property to determine or to change the Draw Multiple setting. When multiple is true, multiple images are drawn as you drag a shape tool.

Tools affected by the multiple property are the Line, Rectangle, Rounded Rectangle, Oval, and Regular Polygon tools. The default value of the multiple property is false.

NOTE

You can also set the multiple property by choosing Draw Multiple from the Options menu. Setting multiple to true puts a checkmark next to the Draw Multiple item in the Options menu. See also the multiSpace property, described later in this chapter.

MultipleLines

APPLIES TO

Fields

SYNTAX

set [the] multipleLines of field to boolean

Field is an expression that yields any valid field descriptor. *Boolean* is an expression that yields either true or false.

EXAMPLE

set the multipleLines of card field 1 to true

DESCRIPTION

You use the multipleLines property to determine or change whether multiple-line selections are allowed in the field when it is configured as a list field (that is, when its autoHilite, lockText, and dontWrap properties are true).

NOTES

You can set the multipleLines property from a script or by clicking the Multiple Lines checkbox in the Field Info dialog box.

MultipleLines 437

MultiSpace

APPLIES TO

Painting environment

SYNTAX

```
set [the] multiSpace to number
```

Number is an expression that yields any positive integer.

EXAMPLE

```
set multiSpace to 12
```

DESCRIPTION

You use the multiSpace property to determine or to change the amount of space left between edges of the multiple images drawn by the shape tools when the multiple property is true. The default value of the multiSpace property is 1.

SCRIPT

The following script uses the multiSpace and multiple properties to create an interesting image. It also cleans up after it is completed.

```
on roundyRound
doMenu "New Card"
reset paint
choose oval tool
set multiple to true
set dragSpeed to 200
set multiSpace to 15
put "60,25" into upperLeft
put "260,175" into botRight
```

```
put "260,25" into upperRight
put "60,175" into botLeft
drag from upperLeft to botRight with shiftKey
drag from botRight to upperLeft with shiftKey
drag from botLeft to upperRight with shiftKey
drag from upperRight to botLeft with shiftKey
wait 60 ticks
set lockScreen to true
choose browse tool
play boing
doMenu "Delete Card"
doMenu "Back"
set lockScreen to false
end roundyRound
```

Name

APPLIES TO

Backgrounds, buttons, cards, fields, HyperCard, menus, menu items, stacks

SYNTAX

```
set [the] name of object to objectName
set [the] name of menuItem of menu to itemName
[the] [english] name of menuNumber
```

Object is an expression that yields a valid background, button, card, field, or stack descriptor. *ObjectName* is an expression that yields any valid HyperCard object name. The object name can be a maximum of 31 characters.

MenuItem is an expression that yields a menu item descriptor that is in the menu menu. Menu is an expression that yields a menu descriptor. ItemName is an expression that yields the new text to replace the current menu item name. MenuNumber is an expression that yields the number form of a menu descriptor.

Name 439

EXAMPLES

```
put the english name of menu 1

put the english name of menuitem 2 of menu 3

set name of this stack to "TooHip"

put the long name of this stack into field 2

set name of this bkgnd to "TrueGrit"

put the long name of this background into field 3

put the long name of field 3 into msg

set name of menuItem "Dogs" of menu "Animals" to "Canines"

put the name of the third menuItem of menu "Direction"

put the name of menu 8

put the name of the third menu
```

DESCRIPTION

You use the name property to determine or to change the name of the specified background, button, card, field, stack, or menu item. You can use the name property to determine the name of a menu, but not to set the name. A stack name must be a valid Macintosh filename.

When you use the name of *menuNumber* form of the name property to get the name of a menu, the descriptor for the menu is an expression that yields a valid number of one of the current HyperCard menus or custom menus in the menu bar. Menus are numbered from left to right, starting with number 1 for the Apple menu.

Using the adjective english in conjunction with the name property ensures that you can correctly refer to menu items even after they have been localized.

NOTES

If you try to retrieve an object's name when it has none, HyperCard returns its ID number.

If you try to modify or determine the name property of a menu item that does not exist, HyperCard displays a "No such menu item" dialog box.

If you try to modify or determine the name property of a menu that does not exist, HyperCard displays a "No such menu" dialog box.

You can set the name of the About HyperCard menu item in the Apple menu to a different value.

See also the put command in Chapter 10, "Commands."

Number

APPLIES TO

Backgrounds, buttons, cards, fields, windows

SYNTAX

put [the] number of object [into container]

Object is an expression that yields any valid background, button, card, or field descriptor. *Container* is the selection, any field, a variable, or the Message box.

EXAMPLES

if the number of this bkgnd is 2 then go next card put number of last card into msg

DESCRIPTION

You use the number property to determine the number of any background, button, card, or field in the current stack.

You can't set the number of a background, button, card, or field; the number of an object changes when you add or delete a background, a button, a card, or a field. The number of a field or button may also change if you change its partNumber property.

NOTE

See also the number function in Chapter 11, which returns the count (how many) of various elements, not the descriptor number of an individual object.

Number 441

NumberFormat

APPLIES TO

Global environment

SYNTAX

set numberFormat to formatType

FormatType is an expression that yields the format (within quotation marks) that is to be used for the display of numbers.

EXAMPLES

```
set numberFormat to "00.##" -- display 02.21 set numberFormat to "0" -- display 2 for the same value set numberFormat to "0." -- display 2.2
```

DESCRIPTION

The numberFormat property determines the precision with which the results of mathematical operations are displayed in fields and the Message box. Use zeros to show how many digits you want to appear, a period to show where you want the decimal point (if at all), and number signs (#) to the right of the decimal point in places where you want a trailing digit to appear, but only if it has value. Use zeros to the right of the decimal point if you always want the same number of digits to show, whether or not they have value. HyperTalk does calculations with up to 19 digits of accuracy.

HyperCard resets the numberFormat property to its default value, "0.######", at idle time (in effect, at the end of all pending handlers).

NOTE

The numberFormat property has no effect on how a number is displayed unless you perform a mathematical operation on it first (for details, see Chapter 6, "Values").

Owner

APPLIES TO

Card or window

SYNTAX

put [the] owner of window | card

Window is the name, ID, or layer number of a window, and *card* is the name, ID, or positional number of a card in the current stack.

EXAMPLES

```
put the owner of window 8
put the owner of card "Introduction"
```

DESCRIPTION

You can ask HyperCard to return the owner of either a card or a window. For a window, this read-only property returns the name of the entity that created the window. This might be HyperCard itself (as in the case of a stack window) or the name of an XCMD like Picture, Message Watcher, or Variable Watcher. The owner of a card is the name or ID of the background that card shares.

Owner 443

PartNumber

APPLIES TO

Button or field

SYNTAX

```
put [the] partNumber of button|field
set [the] partNumber of button|field to number
```

Button is an expression yielding a button identifier, *field* is an expression yielding a field identifier, and *number* is a positive integer that is less than or equal to the number of parts in the enclosing background or card.

EXAMPLES

```
put the partNumber of bg btn "StackKit"
put the partNumber of bg fld "Card Title"
set the partNumber of button "Apple Event Primer" to 1
-- sends that object back
```

DESCRIPTION

The partNumber property returns a number representing the order in which a button or field was placed in its enclosing object. For example, the order of buttons and fields within a card might be card field 1, card field 2, card button 1, card field 3. Even though the number of card button 1 is 1, it's actually in the third position within its enclosing object.

You can use partNumber to reset the ordering of parts within a background or card. A smaller number than the object's original partNumber sends the object back, and a larger number brings it forward.

Pattern

APPLIES TO

Painting environment

SYNTAX

set [the] pattern to number

Number is an expression that yields a positive integer in the range 1 to 40, each representing a pattern in the Patterns palette. The patterns are shown in Figure 12-3.


EXAMPLES

set pattern to 12 put the pattern

DESCRIPTION

You use the pattern property to determine or change the current pattern used to fill shapes (including Paint text) and to paint with the Brush tool.

Figure 12-3 Patterns palette and pattern numbers



1	11	21	31
2	12	22	32
3	13	23	33
4	14	24	34
5	15	25	35
6	16	26	36
7	17	27	37
8	18	28	38
9	19	29	39
10	20	30	40

Pattern 445

The pattern numbers correspond to the 40 positions in the Patterns palette, not to a specific pattern.

NOTE

You normally set the pattern property from the Patterns palette. You can edit a pattern by double-clicking it on the Patterns palette.

PolySides

APPLIES TO

Painting environment

SYNTAX

set [the] polySides to number

Number is an expression that yields a positive integer between 3 and 50. This integer is the number of sides in the polygon.

EXAMPLE

set polySides to 12

DESCRIPTION

You use the polySides property to determine or to change the number of sides of the polygon created by the Regular Polygon tool. The default value is 4.

If you set the value of polySides to a number lower than 3 or higher than 50, it automatically reverts to 3 or 50, respectively. If you choose the circle in the Polygon Sides dialog box, the setting becomes 0.

NOTE

You normally choose the Polygon Sides setting from a dialog box invoked by choosing Polygon Sides from the Options menu or by double-clicking the Regular Polygon tool.

446

PowerKeys

APPLIES TO

Global environment

SYNTAX

set powerKeys to boolean

Boolean is an expression that yields either true or false.

EXAMPLES

set powerKeys to true
set powerKeys to false

DESCRIPTION

You use the powerKeys property to provide keyboard shortcuts for painting actions. The availability of power keys is usually set on the User Preferences card of the Home stack.

The default setting is determined at startup and resume time by the setting on the User Preferences card of the Home stack.

NOTE

Setting powerKeys to true in a script puts a checkmark next to the Power Keys command in the Options menu and changes the setting on the User Preferences card.

PowerKeys 447

PrintMargins

APPLIES TO

Global environment

SYNTAX

set [the] printMargins to rectangle

Rectangle is an expression that yields two points, reported as four positive integers separated by commas.

EXAMPLES

set the printMargins to 78,78,340,440 the printMargins -- puts current margins in Msg box

DESCRIPTION

You use the printMargins property to determine or change the current margin of the print area to be used when printing an expression. It may also affect page margins when printing a field. The default value for the printMargins property is 0,0,0,0. The value of the printMargins property represents the top-left and bottom-right corners of the printing area.

NOTE

See also the printTextAlign, printTextFont, printTextHeight, printTextSize, and printTextStyle properties described in this chapter and the print and reset printing commands in Chapter 10.

PrintTextAlign

APPLIES TO

Global environment

SYNTAX

set [the] printTextAlign to alignment

Alignment is an expression that yields right, left, or center.

EXAMPLES

set the printTextAlign to Right
the printTextAlign -- puts current alignment in Msg box

DESCRIPTION

You use the printTextAlign property to determine or change the current alignment to be used when printing the contents of a variable or when you want to modify the text alignment in the header of a print report job. The default value for the printTextAlign property is left.

NOTE

See also the printMargins, printTextFont, printTextHeight, printTextSize, and printTextStyle properties described in this chapter and the print and reset printing commands in Chapter 10.

PrintTextAlign 449

PrintTextFont

APPLIES TO

Global environment

SYNTAX

set [the] printTextFont to font

Font is an expression that yields a valid font name in the current Macintosh system or the name of a font in a font resource installed in HyperCard or in the current stack.

EXAMPLES

set the printTextFont to "Palatino"
the printTextFont -- puts current font in Msg box

DESCRIPTION

You use the printTextFont property to determine or change the current font to be used when printing the contents of a variable or when you want to modify the font used in the header of a print report job. The default value for the printTextFont property is Geneva.

NOTE

See also the printMargins, printTextAlign, printTextFont, printTextSize, and printTextStyle properties described in this chapter and the print and reset printing commands in Chapter 10.

PrintTextHeight

APPLIES TO

Global environment

SYNTAX

set [the] printTextHeight to number

Number is an expression that yields a valid line height for a font in the current Macintosh system or a font in a font resource installed in HyperCard or in the current stack.

EXAMPLES

set the printTextHeight to 16 the printTextHeight -- puts current line height in Msg box

DESCRIPTION

You use the printTextHeight property to determine or change the space between baselines of text to be used when printing the contents of a variable or when you want to modify the line height of the text in the header of a print report job. The default value for the printTextHeight property is 13.

NOTE

See also the printMargins, printTextAlign, printTextFont, printTextSize, and printTextStyle properties described in this chapter and the print and reset printing commands in Chapter 10.

PrintTextHeight 451

PrintTextSize

APPLIES TO

Global environment

SYNTAX

```
set [the] printTextSize to number
```

Number is an expression that yields an integer that represents a valid font size in the current Macintosh system or the size of a font in a font resource installed in HyperCard or in the current stack.

EXAMPLES

```
set the printTextSize to 12
the printTextSize -- puts current text size in Msg box
```

DESCRIPTION

You use the printTextSize property to determine or change the current size of the font when printing the contents of a variable or when you want to modify the size of the text in the header of a print report job. The default value for the printTextSize property is 10.

SCRIPT

This script sets some of the printing properties and prints the contents of card field 1, which is put in the variable PJob:

```
on printField
  put card field 1 into PJob
  set the printTextFont to "New York"
  set the printTextStyle to "Outline"
  set the printTextSize to "12"
  print PJob
end printField
```

CHAPTER 12

Properties

NOTE

See also the printMargins, printTextAlign, printTextFont, printTextHeight, and printTextStyle properties described in this chapter and the print and reset printing commands in Chapter 10.

PrintTextStyle

APPLIES TO

Global environment

SYNTAX

set [the] printTextStyle to style

Style is an expression that yields a valid font style in the current Macintosh system or the style of a font in a font resource installed in HyperCard or in the current stack. Valid HyperCard font styles are bold, condense, extend, italic, outline, plain, and underline.

EXAMPLES

set the printTextStyle to bold
the printTextStyle -- puts current font style in Msg box

DESCRIPTION

You use the printTextStyle property to determine or change the current style of the font when printing the contents of a variable or when you want to modify the style of the text in the header of a print report job. The default value for the printTextStyle property is plain. The group style that is available in the HyperCard Style menu does not apply to printing.

NOTE

See also the printMargins, printTextAlign, printTextFont, printTextHeight, and printTextSize properties described in this chapter and the print and reset printing commands in Chapter 10.

PrintTextStyle 453

Rect

APPLIES TO

Variable and message watcher windows, picture windows, card windows, script windows

SYNTAX

```
set rect of window variableWatcher to location set rect of window name to location
```

VariableWatcher is an expression that yields the name of a variable watcher window. *Location* is an expression that yields two points, reported as four positive integers separated by commas. *Name* is an expression that yields the name of a picture or stack window.

EXAMPLES

```
set rect of window "Variable Watcher" to "0,0,168,185" put rect of window "MyWatcher" into msg
```

DESCRIPTION

The rect property is two points, reported as four integers separated by commas. You use the rect property to determine or change the size of the variable watcher window.

The points represent the rectangle's top-left (horizontal and vertical) and bottom-right (horizontal and vertical) corner offsets in pixels, respectively, from the top-left corner of the variable watcher window. The first point is always 0,0, and the second point is the offset from the first point.

NOTES

Rect is also the abbreviated form of the rectangle property and works on all of the objects and windows that the rectangle property works on.

Properties that work on HyperCard's built-in external windows may not work on custom external windows. It is the responsibility of the creator of the custom window to provide support for HyperTalk external window properties. See also the variableWatcher, hBarLoc, and vBarLoc properties in this chapter.

Rectangle

APPLIES TO

Buttons, cards, fields, menu bar, windows

SYNTAX

```
set [the] rect[angle] of object to location
```

Object yields one of the following:

```
a valid button descriptor in the current stack
a valid field descriptor in the current stack
message [box] or message [window] or window "message"
pattern window or window "patterns" (the Patterns palette)
tool window or window "tools" (the Tools palette)
window "navigator" (the Navigator palette)
scroll window or window "scroll"
window "Fatbits"
message watcher or window "message watcher"
variable watcher or window "variable watcher"
card window
window stackName
menubar
```

Location is an expression that yields two points, reported as four positive integers separated by commas. *StackName* is the name of a stack.

Rectangle 455

EXAMPLES

```
put rectangle of menubar

set the rectangle of field 4 to 23,45,68,85

put rectangle of field "Sweet" into msg

put the rect of message box -- puts h,v,h,v into Msg

set rect of card window to 64,81,576,441

set the rect of this card to 0,0,512,360
```

DESCRIPTION

The rectangle property is two points, reported as four integers separated by commas. You use the rectangle property to set or determine the size of buttons, fields, and windows. This property is a read-only property for the Message box, Tools palette, Patterns palette, Scroll window, and menu bar.

The points represent the rectangle's top-left (horizontal and vertical) and bottom-right (horizontal and vertical) corner offsets in pixels, respectively, from the top-left corner of the card. The offsets for card windows and menu bar measure from the top-left corner of the screen.

You can set either of the rectangle points of a field or button beyond the boundaries of the card rectangle, putting the field or button out of view until you reset its coordinates through HyperTalk.

You can set the bottom-right corner location of a button or field to a value smaller than the top-left corner location, effectively causing the button or field to disappear. If you set a field to a size smaller than the minimum (12 by 12 pixels) but large enough to see, HyperCard resets it to the minimum size when you click it with the corresponding tool.

You can also change a button or field rectangle by dragging the top-left or bottom-right corner of the button or field with the appropriate tool selected (Button or Field).

SCRIPT

The following example handler, placed in a button script, is invoked when you click the button. It waits until you move the pointer outside the button rectangle, then beeps when you move the pointer back inside the button rectangle:

```
on mouseUp

wait until the mouseLoc is not within rect of me

repeat until the mouseLoc is within rect of me

set cursor to busy -- spin beach ball while we wait

end repeat

beep

end mouseUp
```

NOTES

The rectangle property can be abbreviated rect. The four integers that make up the rectangle property can also be changed individually and in various combinations. See the descriptions of bottom, bottomRight, height, left, right, top, topLeft, and width in this chapter. These are known collectively as rectangle properties and are summarized in Table 12-6.

The rectangle property cannot be set for palettes or the built-in Message Watcher.

The rectangle property of the menu bar cannot be set.

The operator within pertains to any rectangle, such as the rectangles of buttons and fields, the Tools and Patterns palettes, the Message box, and the screen on which the HyperCard menu bar is displayed. The syntax of an expression in which within is valid is the following:

location is [not] within rectangle

Location is an expression that yields a list of two integers separated by a comma, and *rectangle* is an expression that yields a list of four integers separated by commas.

Rectangle 457

When you resize a card window with the rectangle property, a sizeWindow system message is sent. The sizeWindow message is also sent when you zoom a card window by clicking the zoom box or when you change its size with the Scroll window (Command-E).

If the location property of a card window changes when you set the rectangle property, a moveWindow system message is sent. The moveWindow message is also sent when you drag the window to a new location, zoom it in or out, or show the window at a new location with the show command.

See also the location property, earlier in this chapter.

ReportTemplates

APPLIES TO

Stacks

SYNTAX

put [the] reportTemplates of stack stackName

StackName is an expression that yields the name of a stack.

EXAMPLES

```
put reportTemplates of stack "People" into field 2
get the reportTemplates of stack "Forecast"
```

DESCRIPTION

The reportTemplates property is a read-only property of stacks. It returns a return-delimited list of the names of the report templates for the specified stack.

NOTES

Report templates are created and saved for a stack with the Print Report command in the File menu. See the *HyperCard Reference* for more information about creating report templates.

See also the open report printing command in Chapter 10.

Right

APPLIES TO

Buttons, fields, windows, menu bar

SYNTAX

set [the] right of object to number

Object yields one of the following:

a valid button descriptor in the current stack
a valid field descriptor in the current stack
message [box] or message [window] or window "message"
pattern window or window "patterns" (the Patterns palette)
tool window or window "tools" (the Tools palette)
window "navigator" (the Navigator palette)
scroll window or window "scroll"
window "Fatbits"
message watcher or window "message watcher"
variable watcher or window "variable watcher"
card window
window stackName
menubar

Number yields an integer that is the horizontal offset in pixels from the left side of the card to the right side of the object. When the object is the card window, the offset is relative to the left side of the screen. *StackName* is an expression that yields the name of an open stack.

Right 459

CHAPTER 12

Properties

EXAMPLES

```
set right of button 2 to 165
put right of button 2
put the right of the card window
set right of pattern window to 100
```

DESCRIPTION

You use the right property to determine or change the value of item 3 of the rectangle property (left, top, right, bottom) when applied to the specified object or window.

NOTE

The right of the menu bar is a read-only property.

See also the rectangle property, earlier in this chapter.

Script

APPLIES TO

Backgrounds, buttons, cards, fields, stacks

SYNTAX

set [the] script of object to scriptText

Object is the current background, button, card, field, or stack or any background, button, card, field, or stack name currently available to HyperCard. ScriptText yields any valid container that contains a script, or yields a text string that is a script.

CHAPTER 12

Properties

EXAMPLES

```
set script of field "Effect" of first card to empty
set the script of second bkgnd to empty
set the script of third card to field 3
put the script of stack "home" into field "Home Script"
```

DESCRIPTION

You use the script property to retrieve or to replace the script of the specified object. The value of the script property is the text string composing the script of the specified stack.

When you set the script property using the set command, you replace it entirely.

NOTE

Scripts are normally edited using the HyperCard script editor described in Chapter 3, "The Scripting Environment."

ScriptEditor

APPLIES TO

Scripting environment

SYNTAX

set [the] scriptEditor to name

Name is an expression that yields a valid script editor XCMD name.

ScriptEditor 461

EXAMPLES

set the scriptEditor to "MyEditor"
the scriptEditor -- puts current script editor in Msg box
put the scriptEditor after field "Editor in Use"

DESCRIPTION

You use the scriptEditor property to determine or change the current script editor. The default value for the scriptEditor property is scriptEditor, the name of the built-in script editor.

The built-in script editor is a HyperCard XCMD. It can be replaced with a custom script editor XCMD by setting the scriptEditor property to the name of a script editor XCMD.

NOTES

See also the scriptTextFont and scriptTextSize properties described later in this chapter and the description of the scripting environment in Chapter 3.

For more information about creating a custom script editor XCMD, see Appendix A, "External Commands and Functions."

ScriptingLanguage

APPLIES TO

Buttons, fields, parts, cards, background, stacks, global environment

SYNTAX

set the scriptingLanguage [of object] to scriptingLanguage

Object is any background, button, card, field, part, or stack name currently available to HyperCard. *ScriptingLanguage* is a scripting language installed on the current system.

CHAPTER 12

Properties

EXAMPLE

```
put the scriptingLanguage of this cd
set the scriptingLanguage to AppleScript
```

DESCRIPTION

The scriptingLanguage property lets you set any of the HyperCard objects to accept scripts written in the scripting language of your choice, among those available in your system. The script editor has a pop-up menu that displays the available scripting languages.

NOTE

You can use the unary operator there is a to test for the existence of a scripting language capability on the system where HyperCard is running, using the syntax

there is a scriptingLanguage scriptingLanguage

The statement returns a Boolean value.

ScriptTextFont

APPLIES TO

Scripting environment

SYNTAX

set [the] scriptTextFont to font

Font is an expression that yields a valid font name in the current Macintosh system.

ScriptTextFont 463

CHAPTER 12

Properties

EXAMPLES

DESCRIPTION

You use the scriptTextFont property to determine or change the current font in the script editor. The default value for the scriptTextFont property is monaco.

NOTES

You can also set the scriptTextFont property in the dialog box invoked by typing se into the Message box, using a handler provided in the standard Home stack script.

See also the scriptEditor and scriptTextSize properties described in this chapter and the description of the scripting environment in Chapter 3.

ScriptTextSize

APPLIES TO

Scripting environment

SYNTAX

```
set [the] scriptTextSize to number
```

Number is an expression that yields an integer that represents a valid font size in the current Macintosh system.

EXAMPLES

DESCRIPTION

You use the scriptTextSize property to determine or change the current size of the font used in the script editor. The default value for the scriptTextSize property is 9.

NOTES

You can also set the scriptTextSize property in the dialog box invoked by typing se into the Message box.

See also the scriptEditor and scriptTextFont properties described in this chapter and the description of the scripting environment in Chapter 3.

Scroll (fields)

APPLIES TO

Fields

SYNTAX

set [the] scroll of scrollingField to number

ScrollingField is any valid card or background scrolling field. *Number* is an expression that yields an integer representing the number of pixels that have scrolled above the top of the field rectangle.

EXAMPLES

```
set the scroll of field "Clues" to 0
put the scroll of field 1 div the textHeight of field 1¬
into linesAbove
```

DESCRIPTION

You use the scroll property to determine or to change how much material is hidden above the top of a scrolling field's rectangle. Figure 12-4 illustrates the scroll property.

Scroll (fields) 465


The value of the scroll property is 0 if the top of the field is visible. The number of text lines to which the scroll property correlates depends on the textHeight property of the field.

NOTES

You normally control how much material is above the top of the field rectangle by clicking or dragging in the scroll bar at the right side of the field.

If you try to get or set the scroll property of a nonscrolling field, you get an error dialog box.

Figure 12-4 The scroll property



Scroll (windows)

APPLIES TO

Card windows, picture windows

SYNTAX

```
set [the] scroll of [the] card window to point set [the] scroll of window to point
```

Point is an expression that yields two comma-separated positive integers that represent the point on the card or picture to be displayed at the top-left corner of the window. *Window* is an expression that yields a reference to a window created with the picture command or to a card window.

EXAMPLES

```
set the scroll of the card window to 45,60 put the scroll of card window into scrollVar set the scroll of window "Home" to "0,100"
```

DESCRIPTION

You use the scroll property to determine or change the horizontal and vertical scroll (position) of the card window over the current card or the window over the current picture. This property allows you to scroll over a card that is larger than the area of the card window region. The default position of the scroll property for a card window is 0,0.

NOTES

The scroll property has no effect on card windows that are the same size as the card. Card windows can't be larger than the card. You can reset the value of the scroll property to reposition the card window with the Scroll command in the Go menu. You cannot set the scroll property of a window that is displaying an inactive stack.

See also the rectangle property in this chapter and the picture command in Chapter 10.

Scroll (windows) 467

SharedHilite

APPLIES TO

Background buttons

SYNTAX

set [the] sharedHilite of button to boolean

Button is an expression that yields any valid background button descriptor. *Boolean* is an expression that yields either true or false.

EXAMPLES

set sharedHilite of bkgnd button "Flip card" to true put the sharedHilite of bkgnd button 2 into msg

DESCRIPTION

You use the sharedHilite property to determine or to change whether the specified background button shares the same highlight state on all cards of that background. The default value for new background buttons is true. When sharedHilite is set to true, the background button has the same highlight state on all cards of that background.

NOTES

Background buttons have two sets of highlight states, one you see when the button's sharedHilite is true and one you see when its sharedHilite is false. If you have a background button with its sharedHilite set to false, that button on each of those cards of that background can have a different highlight state (determined by the hilite property). If you change the sharedHilite property to true on that background button, the highlight state of that button on all of the cards of that background is set to false (not highlighted). The unshared highlight states of that background button are not lost, however. The unshared highlight states are stored separately with each card and can be returned to their previous values by setting the sharedHilite property back to false.

Background buttons copied and pasted to other cards have the same sharedHilite value as the button originally copied.

You can also change the sharedHilite property by clicking the Shared Hilite checkbox in the Button Info dialog box. See also the descriptions of the autoHilite and hilite properties, earlier in this chapter.

SharedText

APPLIES TO

Background fields

SYNTAX

set [the] sharedText of field to boolean

Field is an expression that yields any valid background field descriptor. *Boolean* is an expression that yields either true or false.

EXAMPLE

set the sharedText of field 3 to true

DESCRIPTION

You use the sharedText property to determine or to change whether the text in the specified background field appears on each card of that background. When the value of sharedText is true, the text in the specified background field is shared by all cards of that background. When it is false, the text can be different in the specified field on all the cards of that background. The default value of the sharedText property for new background fields is false.

NOTES

A background field with its sharedText property set to true effectively has its dontSearch property set to true. The find command excludes the field from any searches.

SharedText 469

If you change the sharedText property to true on a background field that previously had the sharedText property set to false (unshared text), no text is displayed in that field on any of the cards of that background. The previous unshared text of that background field on each of the cards with that background is not lost, however. The unshared text is stored separately with each card and can be redisplayed in the background field of those cards with that background by setting the sharedText property back to false.

You can also change sharedText by clicking the Shared Text checkbox in the Field Info dialog box.

ShowLines

APPLIES TO

Fields

SYNTAX

set [the] showLines of field to boolean

Field is an expression that yields any valid field descriptor. *Boolean* is an expression that yields either true or false.

EXAMPLES

set the showLines of field four to true put the showLines of card field 1 into msq

DESCRIPTION

You use the showLines property to determine or to change whether the text baselines in the card or background field show or not. The default value of the showLines property is false (lines don't show).

NOTES

You can also change showLines by clicking in the Show Lines checkbox in the Field Info dialog box. The showLines property does not apply to scrolling fields.

ShowName

APPLIES TO

Buttons

SYNTAX

set [the] showName of button to boolean

Button is an expression that yields any valid background or card button descriptor. *Boolean* is an expression that yields either true or false.

EXAMPLES

```
set showName of button "You who" to true put the showName of button "You who" into msq
```

DESCRIPTION

You use the showName property to determine or to change whether the name of the specified button (if it has one) is displayed in its rectangle on the screen. Buttons created with the New Button command have showName set to true. Buttons created by Command-dragging the button tool have their showName property initially set to false.

NOTE

You can also change this property by clicking the Show Name checkbox in the Button Info dialog box.

ShowName 471

ShowPict

APPLIES TO

Cards, backgrounds

SYNTAX

set [the] showPict of object to boolean

Object is an expression that yields any valid background or card descriptor. *Boolean* is an expression that yields either true or false.

EXAMPLES

```
set showPict of next card to false
set the showPict of this bkgnd to false
put showPict of bkqnd 3
```

DESCRIPTION

You use the showPict property to determine or to change whether the picture on the specified card or background (if it has one) is displayed on the screen. The default value is true (displayed).

Setting the showPict property of a card to false is the same as hiding it with the picture form of the hide command. Setting it to true is the same as showing it with the picture form of the show command.

NOTES

When the showPict property of the current background or card is false and you try to use a Paint tool on it manually, a dialog box appears asking if you want to make the picture visible; clicking OK sets the showPict property to true and the picture appears. You can draw on hidden pictures from a script.

See also the show and hide commands in Chapter 10.

Size

APPLIES TO

Stacks

SYNTAX

```
put [the] size of stack stackName [into container]
```

StackName is the current stack, or an expression that yields any stack name currently available to HyperCard. *Container* is an expression that yields any valid container.

EXAMPLES

```
get size of stack "Home"
put size of stack "Home" into field "Home Size"
```

DESCRIPTION

You use the size property to determine the size of the specified stack in bytes.

SCRIPT

The following handler examines a stack to see if it fits on an 800 KB disk:

```
on closeStack
  if size of this stack > 795000
  then answer "This stack won't fit on an 800 KB disk."
  pass closeStack
end closeStack
```

NOTES

The minimum stack size is 4096 bytes; the theoretical maximum is 512 MB.

Size 473

The size property can't be changed with the set command; it's changed only by adding things to and deleting things from the stack (you must then compact the stack for any deletions to affect its size).

StacksInUse

APPLIES TO

Global environment

SYNTAX

put [the] stacksInUse [into container]

Container is an expression that yields any valid container.

EXAMPLES

the stacksInUse -- puts stack list in Msg box put the stacksInUse into field "Message Path"

DESCRIPTION

You use the stacksInUse property to determine the stacks that have been added to the current message-passing hierarchy. StacksInUse returns a return-delimited list of the stacks in the current message-passing hierarchy. The stacks are listed in the order in which they are currently placed in the hierarchy.

The stacksInUse property can't be changed with the set command; the stacks in the current message-passing hierarchy can only be changed with the start using and stop using commands.

NOTES

See also the start using and stop using commands in Chapter 10 and the description of the message-passing hierarchy in Chapter 4.

If the message-passing hierarchy hasn't been altered with the start using command, stacksInUse returns empty.

Style

APPLIES TO

Buttons, fields

SYNTAX

set [the] style of object to objectStyle

Object is an expression that yields any valid button or field descriptor. ObjectStyle is an expression that yields one of the valid field or button styles. Button styles are transparent, opaque, rectangle, roundRect, shadow, checkBox, radioButton, standard, default, oval, and popup. Field styles are transparent, opaque, rectangle, shadow, and scrolling.

EXAMPLES

set the style of field 1 to scrolling
set style of button "You who" to roundRect
put the style of button 3 into msg
set the style of field 2 of card 4 to transparent

DESCRIPTION

You use the style property to determine or to change the style of any button or field in the current stack.

NOTE

You can also change the button or field style by using the Style pop-up menu in the Button or Field Info dialog box. Some useful peculiarities of radio buttons and checkbox buttons are described under the hilite property, in this chapter.

Style 475

Suspended

APPLIES TO

Global environment

SYNTAX

the suspended

DESCRIPTION

The suspended property returns whether or not HyperCard is currently running in the background under MultiFinder or System 7. A user can switch from HyperCard to another program while a handler is running and scripts will continue to run in the background.

Use the suspended property in a handler to alter the handler's behavior if it's running in the background—for example, to avoid displaying ask or answer dialog boxes.

HyperCard gives time to the system (and thus to other programs)

- after it executes each HyperTalk statement in a handler,
- whenever it rotates the busy cursor (during compacting, sorting, and printing),
- \blacksquare during the execution of the show cards command and the wait command.

EXAMPLE

```
if not (the suspended) then
   -- Show dialog when not running in background
   ask file "Save as what file?"
   put it into theFileName
else
   --We're in the background, use a default name
   put "Untitled" into theFileName
end if
```

TextAlign

APPLIES TO

Buttons, fields, painting environment

SYNTAX

set [the] textAlign [of object] to alignment

Object is an expression that yields a button or field descriptor. Alignment is an expression that yields one of the words left, right, and center.

EXAMPLES

set the textAlign of field 1 to left
set textAlign to center -- for paint text

DESCRIPTION

You use the textAlign property to determine or to change the way characters are aligned around the insertion point as you type them. This property applies to Paint text, button name text, and the text in fields. The default value of the textAlign property is left for fields and Paint text; the default value is center for buttons.

NOTES

For Paint text, you can also set the textAlign property from the Font dialog box, which is invoked by choosing Text Style from the Edit menu, by double-clicking the Paint Text tool, or by pressing Command-T when the Paint Text tool is selected.

For buttons or fields, you can also set the textAlign property by choosing one of the text alignment options from the Text Properties dialog box. To invoke the Text Properties dialog box, you click the Text Style button in the Button or Field Info dialog box, choose Text Style from the Edit menu, or press Command-T when a button or field is selected.

See also the printTextAlign property, earlier in this chapter.

TextAlign 477

TextArrows

APPLIES TO

Global environment

SYNTAX

set textArrows to boolean

Boolean is an expression that yields either true or false.

EXAMPLES

set textArrows to true
set textArrows to false

DESCRIPTION

The textArrows property alters the function of the Right Arrow, Left Arrow, Up Arrow, and Down Arrow keys.

The default value of the textArrows property is false. When the textArrows property is false, the Right Arrow and Left Arrow keys take you to the next and previous cards in the stack, respectively, and the Up Arrow and Down Arrow keys take you forward and backward, respectively, through the cards you've already viewed.

When the textArrows property is true, the arrow keys move the text insertion point around in a field that you've opened for text editing or in the Message box if you've clicked it. In the Message box, the Up Arrow and Down Arrow keys move the insertion point to the beginning and end of the line of text, respectively.

NOTE

When the textArrows property is true, holding down the Option key while you press the arrow keys produces the same effect as pressing them alone when textArrows is false.

TextFont

APPLIES TO

Buttons, fields, painting environment

SYNTAX

```
set [the] textFont [of chunk] of field to font
set [the] textFont [of object] to font
```

Chunk is any valid chunk expression. *Field* is an expression that yields a field descriptor. *Object* is an expression that yields a button or field descriptor. *Font* is an expression that yields one of the font names available in your Macintosh system.

EXAMPLES

```
set textFont of field 1 to "courier"
set the textFont of bkgnd button 3 to helvetica
set textFont to Palatino -- for paint text
```

DESCRIPTION

You use the textFont property to determine or to change the font in which text appears. This property applies to button name text, the text in fields, and Paint text. The default value of the textFont property is geneva for fields and Paint text; the default value for buttons is chicago.

NOTES

For Paint text, you can also set the textFont property from the Font dialog box, which is invoked by choosing Text Style from the Edit menu, by double-clicking the Paint Text tool, or by pressing Command-T while using a Paint tool.

For buttons or fields, you can also set this property by choosing one of the font names from the Font menu or from the Font dialog box. To invoke the Font

TextFont 479

dialog box, you click the Font button in the Field or Button Info dialog box, choose Text Style from the Edit menu, or press Command-T while a button or field is selected.

If you reset the default font for a field with the textFont property, any text that is already in that field is updated. If you try to set the textFont property to a font that doesn't exist, HyperCard sets it to geneva.

If different fonts are in a chunk of a field, textFont returns the result mixed.

See also the selectedChunk and selectedLine functions in Chapter 11, and the printTextFont and scriptTextFont properties, earlier in this chapter.

TextHeight

APPLIES TO

Buttons, fields, painting environment

SYNTAX

```
set [the] textHeight [of object] to number
```

Object is an expression that yields a button or field descriptor. *Number* is an expression that yields any positive integer.

EXAMPLES

```
set textHeight of field 1 to 20
set textHeight to 20 -- for paint text
```

DESCRIPTION

You use the textHeight property to determine or to change the space between baselines of button text, field text, and Paint text. The value of the textHeight property is in pixels.

NOTES

For Paint text, you can also set the textHeight property in the Line Height box of the Font dialog box, which is invoked by choosing Text Style from the Edit menu, by double-clicking the Paint Text tool, or by pressing Command-T when a Paint tool is selected.

For buttons or fields, you can also set this property by typing the line height in the Line Height box in the Font dialog box. To invoke the Font dialog box, you click the Font button in the Field or Button Info dialog box, choose Text Style from the Edit menu when the field or button is selected, or press Command-T when a button or field is selected.

Although you can set this property for a button, it is meaningless because button-name text has only one line. See also the fixedLineHeight and printTextHeight properties described earlier in this chapter.

TextSize

APPLIES TO

Buttons, fields, painting environment

SYNTAX

```
set [the] textSize [of chunk] of field to number
set [the] textSize [of object] to number
```

Chunk is any valid chunk expression. *Field* is an expression that yields a field descriptor. *Object* is an expression that yields a button or field descriptor. *Number* is an expression that yields any positive integer.

EXAMPLES

```
set textSize of field 1 to 18
set the textSize of word 3 of line 4 to 12
set textSize to 18 -- for paint text
```

TextSize 481

DESCRIPTION

You use the textSize property to determine or to change the font size in which text appears on the screen. The textSize property applies to button text, text in fields, and Paint text. The value of the textSize property is in pixels. The default value of the textSize property is 12.

Although you can use any integer for textSize, exact sizes of fonts available look best. Fonts available are in the Macintosh system or in the font resources in the current stack, a stack in use, the Home stack, or HyperCard.

NOTES

For Paint text, you can also set the textSize property from the Font dialog box, which is invoked by choosing Text Style from the Edit menu, by double-clicking the Paint Text tool, or by pressing Command-T while using a Paint tool.

For buttons or fields, you can also set this property from the Style menu or by selecting one of the font sizes shown or typing directly in the size box in the Font dialog box. To invoke the Font dialog box, you click the Font button in the Field or Button Info dialog box, choose Text Style from the Edit menu while a button or field is selected, or press Command-T while a button or field is selected.

If you reset the default text size for a field with the textSize property, any text that is already in that field is updated.

If different sizes of text are in a text selection, textSize returns the result mixed.

See also the printTextSize and scriptTextSize properties, earlier in this chapter.

TextStyle (buttons, fields, painting environment)

APPLIES TO

Buttons, fields, painting environment

SYNTAX

```
set [the] textStyle [of chunk] of field to style
set [the] textStyle [of object] to style
```

Chunk is any valid chunk expression. Field is an expression that yields a field descriptor. Object is an expression that yields a button or field descriptor. Style is an expression that yields a value of plain or any combination of the following: bold, italic, underline, outline, shadow, condensed, extend, and group (separated by commas).

EXAMPLES

```
set textStyle to plain -- for paint text
set textStyle to bold,italic,underline -- for paint text
set textStyle of field 1 to plain
set the textStyle of line 1 of field 1 to bold,group
set the textStyle of the first card field to bold
```

DESCRIPTION

You use the textStyle property to determine or to change the style in which text appears. The textStyle property applies to button text, text in fields, and Paint text. Its default value is plain. If you use plain in combination with any of the other values, the other values override plain.

NOTES

You use the group text style to group characters, words, or lines together so they are seen as a unit by HyperTalk. The group style does not apply to Paint text or button text.

Group text is supported through the mouseDown and mouseUp messages that are sent to locked fields when clicked and through three functions: clickChunk, clickLine, and clickText.

Here's an example in which you might use group text. You have a field with a list containing George Washington, King George, and George Bush, and you want to display more information about the appropriate George on the screen when his name is clicked. If these three phrases are set to plain text, clicking

"George" wouldn't be specific enough, because HyperTalk's clickText function would only return the single word George, without specifying more information about which George was clicked. If you set the style of each of the phrases George Bush, George Washington, and King George to group, then when the user clicks any word in the group phrase, the person's full name is returned and can be analyzed. If the user clicks either George or Bush in the phrase George Bush, the whole phrase—not just the word the user clicked—is returned by the clickText function.

For Paint text, you can also set the textStyle property from the Font dialog box, which is invoked by choosing Text Style from the Edit menu, by double-clicking the Paint Text tool, or by pressing Command-T while using a Paint tool.

For buttons or fields, you can also set the textStyle property by choosing a style from the Style menu or in the Font dialog box. To invoke the Font dialog box, you click the Font button in the Field or Button Info dialog box, choose Text Style from the Edit menu, or press Command-T while a button or field is selected.

If you reset the textStyle property for a field, any text that is already in that field is updated to the specified style.

If different styles of text are within a text selection, textStyle returns the result mixed.

See also the printTextStyle property, earlier in this chapter, and the clickChunk, clickLine, clickText, selectedChunk, and selectedLine functions in Chapter 11.

TextStyle (menu items)

APPLIES TO

Menu items

SYNTAX

set [the] textStyle of menultem of menu to style

MenuItem is an expression that yields a menu item descriptor. Menu is an expression that yields a menu descriptor. Style is an expression that yields a value of plain or any combination of the following: bold, italic, underline, outline, shadow, condensed, and extend (separated by commas).

EXAMPLES

```
set the textStyle of menuItem "Get Back" of ¬
  menu "Direction" to "outline"
put the textStyle of menuItem "Get Back" of ¬
  menu "Direction"
```

DESCRIPTION

You use the textStyle property to set or determine the text style of a specified menu item. The default value for the textStyle property is plain.

The textStyle property could be used with the checkMark property to indicate that a menu item has been chosen.

If you try to modify or determine the textStyle property of a menu item that does not exist, HyperCard displays a "No such menu item" dialog box.

NOTES

The text style of the menu items in the Font and Tools menu cannot be altered with the textStyle property.

See also the printTextStyle property, earlier in this chapter, and the create menu and put commands in Chapter 10, "Commands."

Ti+1	eWi	dth

APPLIES TO

Pop-up buttons

SYNTAX

set [the] titleWidth of button to number

Button is an expression that yields a valid button descriptor. *Number* is the width of the title area of the button in pixels.

EXAMPLE

set the titleWidth of last button to 65

DESCRIPTION

You use the titleWidth property to determine or change the width of the title area of a pop-up button. You can also adjust the width of the title area by using the mouse to drag the line separating the title area and the pop-up menu.

NOTE

See also the style property, earlier in this chapter.

Top

APPLIES TO

Buttons, fields, windows

SYNTAX

```
set [the] top of object to number
```

Object yields one of the following:

a valid button descriptor in the current stack
a valid field descriptor in the current stack
message [box] or message [window] or window "message"
pattern window or window "patterns" (the Patterns palette)
tool window or window "tools" (the Tools palette)
window "navigator" (the Navigator palette)
scroll window or window "scroll"
window "Fatbits"
message watcher or window "message watcher"
variable watcher or window "variable watcher"
card window
window stackName
menubar

Number is an expression that yields an integer that is the vertical offset in pixels of the top of the specified object. *StackName* is an expression that yields the name of an open stack.

EXAMPLES

```
set top of button 2 to 65
put top of button 2
set top of tool window to 10
```

DESCRIPTION

You use the top property to determine or change the value of item 2 of the rectangle property (left, top, right, bottom) when applied to the specified object or window. The top property of an object can also be set to a value off the screen. Setting the top property of an object to a value off the screen may make the object seem as though it is hidden.

Top 487

NOTE

See also the rectangle property, earlier in this chapter.

TopLeft

APPLIES TO

Buttons, fields, windows

SYNTAX

set [the] topLeft of object to point

Object yields one of the following:

a valid button descriptor in the current stack
a valid field descriptor in the current stack
message [box] or message [window] or window "message"
pattern window or window "patterns" (the Patterns palette)
tool window or window "tools" (the Tools palette)
window "navigator" (the Navigator palette)
scroll window or window "scroll"
window "Fatbits"
message watcher or window "message watcher"
variable watcher or window "variable watcher"
card window
window stackName
menubar

Point is an expression that yields a list of two integers separated by a comma. *Point* represents the horizontal and vertical offsets, respectively, in pixels from the top-left corner of the card to the top-left corner of the specified object. *StackName* is an expression that yields the name of an open stack window.

CHAPTER 12

Properties

EXAMPLES

```
set topLeft of bkgnd button id 23 to 64,30
put topLeft of window "scroll"
put the topLeft of tool window
set topLeft of message box to 150,75
```

DESCRIPTION

You use the topLeft property to determine or change items 1 and 2 of the value of the rectangle property (left, top, right, bottom) when applied to the specified object or window. When you change the topLeft property of an object, the entire object moves, its width and height remaining the same.

NOTE

See also the rectangle property, earlier in this chapter.

TraceDelay

APPLIES TO

Global environment

SYNTAX

```
set [the] traceDelay to number
```

Number is an expression that yields 0 or a positive integer.

EXAMPLES

```
set traceDelay to 32 put the traceDelay
```

TraceDelay 489

DESCRIPTION

You use the traceDelay property to set or retrieve the value of the debugger's trace rate. Setting the number value changes the number of ticks HyperCard waits between executing lines of HyperTalk while tracing. The default value for traceDelay is 0, the fastest trace rate.

UserLevel

APPLIES TO

Global environment

SYNTAX

set userLevel to number

Number is an expression that yields one of the valid user-level numbers, 1 through 5.

EXAMPLE

set userLevel to 5

DESCRIPTION

You use the userLevel property to set or retrieve the value of the current HyperCard user level. User levels give progressively more power to the user. The levels are 1 (Browsing), 2 (Typing), 3 (Painting), 4 (Authoring), and 5 (Scripting), as explained in the *HyperCard Reference*.

If you set the value of userLevel to a number lower than 1 or higher than 5, it automatically reverts to 1 or 5, respectively.

NOTES

You can invoke the Protect Stack dialog box from the File menu to impose a limit on the user level available in a stack. In that case, setting the user level

higher than the Protect Stack limit has no effect, although it generates no error message. On leaving the protected stack, the user level in effect when the stack was entered is restored.

If your stack script changes the value of userLevel, be sure to restore the original value of userLevel when your stack closes.

UserModify

APPLIES TO

Global environment

SYNTAX

set userModify to boolean

Boolean is an expression that yields either true or false.

EXAMPLES

```
set userModify to true
set userModify to false
```

DESCRIPTION

The userModify property is a global property pertaining to HyperCard itself. It controls whether or not a user can type into fields or use Paint tools on a stack that has been write-protected. A stack is write-protected under any of the following circumstances:

- The stack is on a CD-ROM.
- The stack is on a file server in a folder whose access privileges are set to Read Only.
- The Locked box is checked in the stack's Get Info dialog box in the Finder's File menu.

UserModify 491

- The stack is on a locked disk.
- "Can't modify stack" is checked in the stack's Protect Stack dialog box.

SCRIPT

The following openStack handler sets up HyperCard so that the stack can be used, even though it is locked:

```
on openStack
  if the cantModify of this stack is true then
    set the userModify to true
  end if
  pass openStack
end openStack
```

NOTES

Changes can be made only to the level that the userLevel settings allow. Any changes made to the stack are disregarded when the stack is closed.

See also the cantDelete and cantModify properties, earlier in this chapter.

VariableWatcher

APPLIES TO

Global environment

SYNTAX

```
set [the] variableWatcher to name
```

Name is an expression that yields a valid variable watcher XCMD name.

CHAPTER 12

Properties

EXAMPLES

set variableWatcher to "MyWatcher"
put the variableWatcher

DESCRIPTION

You use the variableWatcher property to determine or to change the current variable watcher. The default value for variableWatcher is variableWatcher, the built-in variable watcher. You display the current variable watcher with the show command or by setting the visible property of the variable watcher window to true.

The built-in variable watcher is a HyperCard XCMD. It can be replaced with a custom variable watcher XCMD by setting the variableWatcher property to the name of a custom variable watcher XCMD.

NOTES

See also the description of the Variable Watcher in Chapter 3, "The Scripting Environment."

For more information about creating and calling a custom variable watcher XCMD, see Appendix A, "External Commands and Functions."

VBarLoc

APPLIES TO

Variable watcher windows

SYNTAX

set [the] vBarLoc of window "variable watcher" to number

Number is an expression that yields a positive integer that represents the offset in pixels from the left side of the variable watcher window to the vertical bar in the window.

VBarLoc 493

CHAPTER 12

Properties

EXAMPLES

```
set the vBarLoc of window "variable watcher" to 123 put the vBarLoc of window "variable watcher"
```

DESCRIPTION

You use the vBarLoc property to determine or to change the current position of the vertical bar in the variable watcher window. The vertical bar separates the variable names from the actual values of the variables.

NOTES

The built-in variable watcher is a HyperCard XCMD. It can be replaced with a custom variable watcher XCMD by setting the variableWatcher property to the name of a variable watcher XCMD.

A custom variable watcher may or may not respond to the vBarLoc property. It is up to the variable watcher XCMD to provide support for variable watcher properties.

See also the description of the Variable Watcher in Chapter 3, "The Scripting Environment," and the hBarLoc, rect, and variableWatcher properties in this chapter.

For more information about creating and calling a custom variable watcher XCMD, see Appendix A, "External Commands and Functions."

Version

APPLIES TO

HyperCard, stacks

SYNTAX

the [long] version [of HyperCard] the version of stack *stackName*

StackName is an expression that yields a stack name.

EXAMPLE

if the version > 1.0 then set textArrows to true

DESCRIPTION

The version property returns the version number of the HyperCard application currently running or the versions of HyperCard that created and modified a specified stack.

The long version returns an eight-digit number that represents the major revision number, minor revision number, and software state (development, alpha, beta, or final, plus the release number). Here are the values the numbers represent:

version xxyyzzrr

xx major revision number

yy minor revision number

zz 80 = final

60 = beta

40 = alpha

20 = development

rr release number

For example, 0200600E is version 2.0 beta engineering release, and 02008000 is version 2.0 final.

The version of *stackName* form returns a list of five comma-separated eight-digit numbers. The first four of these numbers are of the form described previously for the long version. They are, respectively the version of HyperCard used to create this stack, the version of HyperCard that last compacted this stack, the version of HyperCard that last modified the stack, and the version of HyperCard that first modified the stack. The last number is the date and time (in seconds) of the most recent save before the start of the current session. (You can use the convert command to change the seconds format into a date and time format.)

Version 495

Visible

APPLIES TO

Buttons, fields, menu bar, windows

SYNTAX

set the visible of object to boolean

Object yields one of the following:

a valid button descriptor in the current stack
a valid field descriptor in the current stack
message [box] or message [window] or window "message"
pattern window or window "patterns" (the Patterns palette)
tool window or window "tools" (the Tools palette)
window "navigator" (the Navigator palette)
scroll window or window "scroll"
window "Fatbits"
message watcher or window "message watcher"
variable watcher or window "variable watcher"
card window
window stackName
menubar

Boolean is an expression that yields either true or false. *StackName* is an expression the yields the name of an open stack window.

EXAMPLES

if the visible of menubar is false
then set the visible of menubar to true
set the visible of tool window to false
set the visible of window "variable watcher" to true

DESCRIPTION

The visible property determines whether a button, field, menu bar, or window is shown or hidden on the screen.

The Tools and Patterns palettes become visible when you tear them off the menu bar; the Message box and the menu bar can be toggled between being visible and hidden by pressing Command-M and Command-Space bar, respectively.

SCRIPT

The script that follows could be used to show a hidden field that is used for making notes. Create a button and a background field with the sharedText property set to false. The script placed in the button would display a field named Notes with the show command based on the value of the visible property of the Notes field. It also hides the field if you click the button again:

```
on mouseUp -- button or field script to show a field if the visible of bkgnd field "Notes" then hide bkgnd field "Notes" else show bkgnd field "Notes" end if end mouseUp
```

The next short script makes a field disappear after it has been made visible. The script, when placed in a locked field, sets the visible property of the field to false when the field receives a mouseUp message. Whenever a user clicks the visible field, it disappears:

```
on mouseUp -- field script to set visible property set the visible of me to not the visible of me end mouseUp
```

NOTE

See also the show and hide commands in Chapter 10.

Visible 497

WideMargins

APPLIES TO

Fields

SYNTAX

set [the] wideMargins of field to boolean

Field is an expression that yields a background or card field descriptor. *Boolean* is an expression that yields either true or false.

EXAMPLES

set wideMargins of field "just fine" to true the wideMargins of field 1 -- puts value in Msg box

DESCRIPTION

You use the wideMargins property to specify whether some extra space is included at the left and right sides of each line in the field (to make the text easier to read). The default value of wideMargins is false.

NOTE

You can also change this property by clicking the Wide Margins checkbox in the Field Info dialog box.

Width

APPLIES TO

Buttons, fields, cards, windows, menu bar

SYNTAX

set [the] width of object to number

Object is an expression that yields a valid button, field, or window descriptor. *Number* is an expression that yields a positive integer. The *number* value represents the total number of pixels in the horizontal width of the specified object.

EXAMPLES

```
set width of cd window to width of cd window div 2
-- actually shrinks the window for all cards in the current
-- stack because all cards in a stack share same window
put width of button 4 -- puts width in Msg box
```

DESCRIPTION

You use the width property to determine or change the horizontal distance in pixels occupied by the rectangle of the specified button, field, or window.

NOTES

The width property is read-only for the Message box and menu bar.

See also the rectangle property, earlier in this chapter.

the width of bkgnd field "phoneList"

Width 499

Zoomed

APPLIES TO

Windows

SYNTAX

Set [the] zoomed of window to boolean

Window is an expression that yields a window descriptor. *Boolean* is an expression that yields either true or false.

EXAMPLE

set the zoomed of window "home" to true

DESCRIPTION

You use the zoomed property to determine or change whether a window is set to its maximum size and centered on the screen, as when the user clicks its zoom box in its upper-right corner.

Appendixes

This appendix describes the external command and function interface of HyperCard. In addition to general information about external commands and functions, this appendix contains specific information that requires a reading knowledge of 68000 assembly language, Pascal, or C to be understood. This appendix does not include information about how to write code, nor does it explain how to use a compiler or assembler to create an executable resource.

Definitions, Uses, and Examples

External commands and functions are extensions to the HyperTalk built-in command and function set. HyperCard includes interface procedures that make extending HyperTalk in this way convenient and practical for expert programmers.

XCMD and XFCN Resources

External commands (*ex-commands*, or XCMDs) and external functions (*ex-functions*, or XFCNs) are executable Macintosh code resources, written in a Macintosh programming language (such as Pascal, C, or 68000 assembly language), which are attached to the HyperCard application or a stack with a resource editor such as ResEdit. The resource type of an external command is 'XCMD', and the resource type of an external function is 'XFCN'.

An XCMD or XFCN is a compiled (or assembled) executable code module. After XCMDs or XFCNs have been created and attached to HyperCard or a stack, they're called from HyperTalk in much the same way that built-in commands or user-defined message and function handlers are called. They also use the message-passing hierarchy in the same way.

An XCMD or XFCN resource has no header bytes; it is invoked by a jump instruction to its entry point. These resources are simpler than Macintosh drivers: they can't have any global (or static) data, and they can't be larger

than 32 KB in size. (For more details about these restrictions, see "Guidelines for Writing XCMDs and XFCNs," later in this appendix.)

For detailed information on Macintosh resources, see the chapter "Resource Manager" in *Inside Macintosh: More Macintosh Toolbox*, published by Addison-Wesley.

Uses for XCMDs and XFCNs

External commands and functions can provide access to the Macintosh Toolbox and to some of HyperCard's own internal routines; they can provide fast processing speed for time-critical operations; and they can override built-in HyperTalk commands to provide custom solutions. XCMDs or XFCNs can be used for serial port input and output routines, custom search-and-replace routines, AppleCD SC control routines, file input and output routines, and so on.

A typical use for an XCMD would be as an interface for a driver, allowing HyperCard to control an external device such as a video disc player. Such an interface would have three parts: the driver, the XCMD, and a HyperTalk handler. The driver would be completely separate from HyperCard. (See *Inside Macintosh: Devices* for information about writing drivers.) The XCMD would be small; its purpose would be to convert HyperTalk messages to the appropriate driver calls. The HyperTalk handler would call the XCMD with various parameters directing it to open or close the driver or to perform a specific control call.

Using an XCMD or XFCN

You invoke XCMDs and XFCNs from HyperTalk using the regular message syntax and user-defined function call syntax. The message or function call is passed through the HyperCard message-passing hierarchy.

Invoking XCMDs and XFCNs

You invoke an XCMD as you do a message handler. That is, you type the name of the XCMD followed by its parameters in a HyperTalk script or in the Message box. Separate the parameters (if there are more than one) with commas, and put quotation marks around parameters of more than one word. When the script executes or when you send the Message box contents by pressing Return or Enter, HyperCard sends the message through the normal message-passing hierarchy. For external commands, the Macintosh resource name correlates to the message name—the first word in the message.

Similarly, you call an XFCN in a HyperTalk statement in the same way you would a user-defined function (use parentheses after the function rather than preceding the function with the word the). Enclose any parameters within parentheses, separate them (if more than one) with commas, and put quotation marks around parameters of more than one word. If the function takes no parameters, append empty parentheses after it. For external functions, the Macintosh resource name correlates to the function name—the word preceding parentheses in the function call.

You can pass a maximum of 16 parameters to an XCMD or XFCN.

Message-Passing Hierarchy


External commands and functions use the message-passing hierarchy in the same way as message and function handlers and built-in commands and functions. External commands and functions can be attached to any stack or to the HyperCard application.

If a stack receives a message or function call for which it has no handler, then before passing the message or function call to another stack (if added to the message-passing hierarchy with the start using command) or HyperCard, it checks to see if it has an external command or function of the same name. When HyperCard receives a message or function call, it checks to see if it has an external command or function before it looks for a built-in command or function.

That is, HyperCard searches for message and function handlers, XCMDs and XFCNs, and built-in commands and functions through the message-passing hierarchy shown in Figure A-1.

Chapter 4 discusses the message-passing hierarchy, including the dynamic path, in detail.

Figure A-1 Message-passing hierarchy, including XCMDs and XFCNs



Guidelines for Writing XCMDs and XFCNs

XCMDs and XFCNs can call most of the Macintosh Toolbox traps and routines, but they have certain limitations and restrictions. They can't do everything that an application can do because they are guests in HyperCard's memory space. In that regard they are more like desk accessories than applications. Here are some guidelines for writing XCMDs and XFCNs:

- Do not initialize the various Macintosh managers by calling their initialization routines. That is, don't call InitGraf, InitFonts, InitWindows, and so on.
- Do not rely upon having lots of RAM available for your XCMD. There is some extra space in HyperCard's heap, but if HyperCard is running in 750 KB under MultiFinder, for example, an XCMD should not be bigger than about 32 KB.
- Do not use register A5 of a 68000-family processor. The value in A5 belongs to HyperCard, and it points to HyperCard's global data, jump table, and other things that constitute an "A5 world." XCMDs do not currently have their own A5 world.
- XCMDs cannot have global data.
- You can use string literals in XCMDs compiled with the -b switch in MPW C version 3.0 or later. You can use 'STR' resources or put the strings in a short assembly-language glue file.
- XCMDs cannot have a jump table, so they cannot have code segments. This
 restriction imposes a 32 KB limit on the size of XCMDs for 68000-based
 machines (the 68020 supports longer branches).
- XCMDs can, however, allocate small chunks of memory by standard NewHandle calls. (You can also allocate memory with NewPtr calls, but they should be used sparingly to avoid heap fragmentation.)
- If your XCMD allocates some memory in the heap, it should also deallocate the memory.

- If an XCMD allocates a handle to save state information between invocations of the XCMD, then you must pass the handle back to HyperCard to be stored somewhere in the current stack, such as in a hidden field. You must convert the handle from a long integer to a string, because all values are treated as strings by HyperTalk.
- Since HyperCard jumps blindly to the start of an XCMD's code, it is important that the main routine actually ends up at the start of the XCMD. The link order is vitally important.
- If, as you write, the size of your XCMD begins to approach 32 KB, consider converting it to a driver.

Attaching an XCMD or XFCN

To attach an existing XCMD or XFCN (one that has already been compiled or assembled into a resource) to one of your stacks, use a resource editor such as ResEdit. The following steps describe the procedure using ResEdit:

- 1. Launch ResEdit.
- 2. Select and open the stack containing the 'XCMD' or 'XFCN' resource you want.
- 3. Select and open the resource type of 'XCMD' or 'XFCN'.
- 4. Select and open the particular resource you want by name.
- 5. Press Command-C to copy the resource.
- 6. Select and open the stack you want to paste the resource into.
- 7. If your stack has no resource fork, ResEdit displays a dialog box asking if you want to open one. Click OK. ResEdit opens a window.
- 8. Press Command-V to paste the resource into your stack.
- 9. Click the window's close box. When ResEdit asks if you want to save the file, click Yes.
- Quit ResEdit.

Parameter Block Data Structure

If HyperCard matches a message or function call with an external command or function, it passes a single argument to the XCMD or XFCN: a pointer to a parameter block called XCmdBlock. All communication between HyperCard and the XCMD or XFCN passes through the parameter block. In Pascal, the parameter block data structure is a record; in C it's a struct.

HyperCard uses the first two fields of the parameter block to pass information to the XCMD or XFCN before invoking its execution. The XCMD or XFCN uses the other data fields in XCmdBlock to pass back results and to communicate with HyperCard during execution.

The Pascal parameter block is shown below:

TYPE

END;

```
XCmdPtr = ^XCmdBlock;
XCmdBlock = RECORD
               paramCount: INTEGER; { If -1 then this is an
                            event handling call. }
               params:
                            ARRAY[1..16] OF Handle;
               returnValue: Handle;
               passFlaq:
                           BOOLEAN;
               entryPoint: ProcPtr; { to call back to HyperCard }
               request:
                            INTEGER;
               result:
                            INTEGER;
                           ARRAY[1..8] OF LongInt;
               inArgs:
               outArgs:
                           ARRAY[1..4] OF LongInt;
      END;
```

Parameter Block Data Structure

Passing Parameters to XCMDs and XFCNs

Before calling the XCMD or XFCN, HyperCard places the number of parameters and handles to the parameter strings in two fields of the parameter block: paramCount and params.

ParamCount

HyperCard puts an integer representing the parameter count in field paramcount. You can pass a maximum of 16 parameter strings.

Params

HyperCard evaluates the parameters and puts their values into memory as zero-terminated ASCII strings. Before it invokes the XCMD or XFCN, HyperCard puts the handles to the parameter strings into the params array. For example, the command Beep 5 creates a single handle in params [1] containing the ASCII equivalent of 5 and a zero terminator. HyperCard disposes of the handle.

Passing Back Results to HyperCard

When an XCMD or XFCN finishes executing, HyperCard examines two fields of the parameter block: returnValue and passFlag.

ReturnValue

An XCMD or XFCN can store one zero-terminated string to communicate the result of its execution. HyperCard looks for a handle to the result string in the returnValue field of XCmdBlock. Storing a result string is optional for an XCMD; it is expected of an XFCN, but it's not required. If you store a result string handle into returnValue in an XCMD, the user can get it by using the HyperTalk function the result (useful for explaining why there was an error). For an XFCN, HyperCard uses the returnValue string to replace the function call itself in the HyperTalk statement containing the call. If you don't store anything, the result is the empty string.

PassFlag

When an XCMD or XFCN terminates, HyperCard examines the Boolean value of the passFlag field. If passFlag is FALSE (the normal case), control passes back to the previously executing handler (or to HyperCard's idle state if no handler was executing). If passFlag is TRUE, HyperCard passes the message or function call to the next object in the hierarchy. This has the same effect as the pass control statement in a script.

Callbacks

The remaining five fields of the XCmdBlock record have to do with calling HyperCard back in the middle of execution of an XCMD or XFCN. You use the callback mechanism to obtain data or request HyperCard to perform an action. HyperCard has 77 callback requests (see "Callback Procedures and Functions," later in this appendix). The five XCmdBlock fields that compose the callback interface are entryPoint, request, result, inArgs, and outArgs. If you link your code with the HyperXLib library (the HyperXLib.o file that comes with MPW), then you will use only the result field.

EntryPoint

When HyperCard sets up the parameter block data structure before passing control to an XCMD or XFCN, it places an address in entryPoint. The XCMD or XFCN uses this address to execute a jump instruction to pass control to HyperCard for the callback.

Request

Before executing the jump instruction, the XCMD or XFCN puts an integer representing the callback request it's making into the request field.

Result

After it completes the callback request, HyperCard places an integer result code in the result field. The result code can be 0, 1, or 2. If the callback executed successfully, the result is 0; if it failed, the result is 1; if the callback request is not implemented in HyperCard, the result is 2.

InArgs

The XCMD or XFCN sends up to eight arguments to HyperCard as long integers in the inArgs array. Depending on the callback request, HyperCard expects arguments in certain elements of the inArgs array. In many callbacks, the arguments are pointers to zero-terminated strings. The callback arguments are shown in Pascal in "Callback Procedures and Functions," later in this appendix.

OutArgs

After it executes the callback request, HyperCard returns up to four long integers (or other types, such as handles) to the XCMD or XFCN as elements of the outArgs array. The arguments HyperCard returns from callbacks are shown in Pascal in "Callback Procedures and Functions," later in this appendix.

Callback Procedures and Functions

If you want to manage a callback to HyperCard yourself, you can define the XCmdBlock data structure in your XCMD or XFCN. Then you can put values you want to send to HyperCard in inArgs, put a request code in request, and execute a jump instruction to the address HyperCard places in entryPoint. HyperCard returns values in outArgs and a result code in result.

However, if you use MPW Pascal or C, you can take advantage of interface definition and library files. The definition and library files provide simple procedure and function calls that you can use inside your XCMD or XFCN to handle callback requests more easily. Include them when you compile and link your XCMD or XFCN.

The Pascal code for an XCMD or XFCN should include the definition file HyperXCmd.p at the beginning of the USES clause. There must be an argument of type XCmdPtr passed by HyperCard to the XCMD or XFCN. In the callback procedures and functions, all strings are Pascal strings unless noted as zero-terminated strings (which have no length byte; the end of the string is indicated by a null byte). In general, if a handle is returned, the XCMD or XFCN is responsible for disposing of it.

HyperTalk Utilities

```
FUNCTION EvalExpr(paramPtr: XCmdPtr; expr: Str255): Handle;
```

EvalExpr evaluates the HyperTalk expression passed in expr and returns a handle to a zero-terminated string containing the result of the evaluation. For example, EvalExpr('the long date') returns a handle to a string containing the current date in the long format (Saturday, June 25, 1988). The caller must dispose of the handle.

```
PROCEDURE RunHandler(paramPtr: XCmdPtr; handler: Handle);
```

The zero-terminated string in handler is interpreted first as a message. If it is a message (command or function), it is sent to the current card. The text can be one or more lines of HyperTalk, including conditional statements and repeat loops. The lines are executed as though sent from the Message box. If it is multiple lines beginning with on <code>messageName</code> and ending with end <code>messageName</code>, <code>messageName</code> is sent to this handler in the context of the card. If the handler exits, execution terminates. If the handler contains the line <code>passmessageName</code>, <code>messageName</code> is passed down HyperTalk's normal message-passing path, beginning with the current card script.

You can not override a script executed with RunHandler. For example, if the current card has an on <code>messageName</code> handler, and an XCMD issues a <code>runHandler</code> callback with an on <code>messageName</code>, the XCMD's handler executes. If the handler passes the message, the card's script executes.

Execution is somewhat slower using RunHandler than it would be running the same script as a card handler. You cannot use the debugging tools to debug scripts executed with RunHandler.

```
PROCEDURE SendCardMessage(paramPtr: XCmdPtr; msg: Str255);
```

The string in msg is sent as a message to the current card.

```
PROCEDURE SendHCMessage(paramPtr: XCmdPtr; msg: Str255);
```

The string in msg is sent as a message directly to HyperCard, bypassing the entire message-passing hierarchy.

Memory Utilities

```
FUNCTION GetGlobal(paramPtr: XCmdPtr; globName: Str255): Handle;
```

GetGlobal returns a handle to a zero-terminated string that contains a copy of the contents of the HyperTalk global variable globName. If globName doesn't exist, GetGlobal returns a handle to an empty string. The caller must dispose of the handle.

```
PROCEDURE SetGlobal(paramPtr: XCmdPtr; globName: Str255;
globValue: Handle);
```

SetGlobal copies the zero-terminated string to which globValue is a handle into the HyperTalk global variable named globName. If globName doesn't exist, SetGlobal creates it. HyperCard does not dispose of globValue.

```
PROCEDURE ZeroBytes(paramPtr: XCmdPtr; dstPtr: Ptr;
longCount: LongInt);
```

ZeroBytes sets longCount bytes beginning at dstPtr to 0. It performs no boundary checking. For example, it can write past the end of a zero-terminated string.

String Utilities

```
PROCEDURE ScanToReturn(paramPtr: XCmdPtr; VAR scanPtr:
Ptr);
```

ScanToReturn scans the zero-terminated string pointed to by scanPtr, stopping at the first return character or at the end of the string. ScanPtr is incremented to point to the new location.

```
PROCEDURE ScanToZero(paramPtr: XCmdPtr; VAR scanPtr: Ptr);
```

ScanToZero scans the zero-terminated string pointed to by scanPtr, stopping at the end of the string. ScanPtr is incremented to point to the new location.

```
FUNCTION StringEqual(paramPtr: XCmdPtr; str1,str2:
Str255): BOOLEAN;
```

StringEqual compares the two Pascal strings str1 and str2 (case-insensitive and diacritical-sensitive) and returns TRUE if the two strings are identical; otherwise, it returns FALSE.

```
FUNCTION StringLength(paramPtr: XCmdPtr; strPtr: Ptr):
LongInt;
```

StringLength returns the number of characters in the zero-terminated string pointed to by strPtr. Note that strPtr is a pointer, not a handle.

```
FUNCTION StringMatch(paramPtr: XCmdPtr; pattern: Str255;
target: Ptr): Ptr;
```

StringMatch performs a case-insensitive search for pattern (a Pascal string) in the zero-terminated string pointed to by target. If the search is successful, the location of the first matching character is returned as the function result. If the search is unsuccessful, StringMatch returns nil. This is equivalent to HyperTalk's offset function.

```
PROCEDURE ZeroTermHandle(paramPtr: XCmdPtr; hndl: Handle);
```

ZeroTermHandle increases the block referenced by hndl by 1 byte and then sets the extra byte to 0, making hndl legal for operations such as SaveXWScript, FormatScript, and ZeroToPas.

String Conversions

```
PROCEDURE BoolToStr(paramPtr: XCmdPtr; bool: BOOLEAN; VAR str: Str255);

BoolToStr converts bool to a Pascal string (TRUE or FALSE).

PROCEDURE ExtToStr(paramPtr: XCmdPtr; num: Extended; VAR str: Str255);
```

ExtToStr converts num (a SANE extended type) to a Pascal string.

```
PROCEDURE LongToStr(paramPtr: XCmdPtr; posNum: LongInt; VAR str: Str255);

LongToStr converts posNum (a 32-bit unsigned integer) to a Pascal string.

PROCEDURE NumToHex(paramPtr: XCmdPtr; num: LongInt; nDigits: INTEGER; VAR str: Str255);
```

NumToHex returns in str a hexadecimal (base 16) representation of the value of num, expanding the string to nDigits in length.

```
PROCEDURE NumToStr(paramPtr: XCmdPtr; num: LongInt; VAR str: Str255);
```

NumToStr converts num (a 32-bit signed integer) to a Pascal string.

```
FUNCTION PasToZero(paramPtr: XCmdPtr; str: Str255): Handle;
```

PasToZero converts str to a zero-terminated string and returns a handle to the new string. The caller must dispose of the handle.

```
PROCEDURE PointToStr(paramPtr: XCmdPtr; pt: Point; VAR pasStr: Str255);
```

PointToStr converts the point passed in pt to a Pascal string and returns the string in pasStr.

```
PROCEDURE RectToStr(paramPtr: XCmdPtr; rct: Rect; VAR pasStr: Str255);
```

RectToStr converts the rectangle passed in rct to a Pascal string and returns the point in pasStr.

```
PROCEDURE ReturnToPas(paramPtr: XCmdPtr; zeroStr: Ptr; VAR pasStr: Str255);
```

ReturnToPas copies characters from the zero-terminated string pointed to by zeroStr into the Pascal string pasStr, stopping at the first return character (ASCII \$0D), the end of the zero-terminated string, or the 255th

character, whichever comes first. The variable pasStr will not include the return character.

```
FUNCTION StrToBool(paramPtr: XCmdPtr; str: Str255):
BOOLEAN;
```

StrToBool converts str to a Boolean (TRUE or FALSE) and returns the Boolean value as its result.

```
FUNCTION StrToExt(paramPtr: XCmdPtr; str: Str255):
Extended;
```

StrToExt converts str to an extended type. Extended numbers contain a sign bit, 15 bits for the exponent, and 63 bits for the significand. This is the standard data type for SANE, the Standard Apple Numerics Environment.

```
FUNCTION StrToLong(paramPtr: XCmdPtr; str: Str255):
LongInt;
```

Converts str to a long (32-bit) unsigned integer. Unsigned long integers range from 0 to 4,294,967,295.

```
FUNCTION StrToNum(paramPtr: XCmdPtr; str: Str255): LongInt;
```

Converts str to a long (32-bit) signed integer. Signed long integers range from -2,147,483,648 to 2,147,483,647.

```
PROCEDURE StrToPoint(paramPtr: XCmdPtr; str: Str255; VAR pt: Point):
```

Converts the Pascal string passed in str to a point and returns the point in pt.

```
PROCEDURE StrToRect(paramPtr: XCmdPtr; str: Str255; VAR
rct: Rect):
```

Converts the Pascal string passed in str to a rectangle and returns the rectangle in rct.

```
PROCEDURE ZeroToPas(paramPtr: XCmdPtr; zeroStr: Ptr; VAR pasStr: Str255);
```

ZeroToPas converts the zero-terminated string pointed to by zeroStr to a Pascal string and returns the string in pasStr.

Field Utilities

```
FUNCTION GetFieldByID(paramPtr: XCmdPtr; cardFld: BOOLEAN; fldID: INTEGER): Handle;
```

GetFieldByID returns a handle to a zero-terminated string that contains a copy of the contents of field ID fldID. If cardFld is TRUE, fldID is a card field; otherwise, it is a background field.

```
FUNCTION GetFieldByName(paramPtr: XCmdPtr; cardFld: BOOLEAN; fldName: Str255): Handle;
```

GetFieldByName returns a handle to a zero-terminated string that contains a copy of the contents of field fldName. If cardfld is TRUE, fldName is a card field; otherwise, it is a background field.

```
FUNCTION GetFieldByNum(paramPtr: XCmdPtr; cardFld: BOOLEAN; fldNum: INTEGER): Handle;
```

GetFieldByNum returns a handle to a zero-terminated string that contains a copy of the contents of field number fldNum. If cardFld is TRUE, fldNum is a card field; otherwise, it is a background field.

```
FUNCTION GetFieldTE(paramPtr: XCmdPtr; cardFieldFlag:
BOOLEAN; fieldID, fieldNum: INTEGER; fieldNamePtr:
StringPtr): TEHandle;
```

GetFieldTE returns a copy of the styled TEHandle from the specified field, including style runs (see *Inside Macintosh: Text*). The caller must dispose of this TEHandle.

If fieldID is nonzero, then HyperTalk uses it; else if fieldNum is nonzero, then HyperTalk uses it; else if fieldNamePtr is not NIL, HyperTalk uses the

field name pointed to by it. If GetFieldTE returns NIL, the field was not found or there wasn't enough memory to copy the text and styles.

```
PROCEDURE SetFieldByID(paramPtr: XCmdPtr; cardFld: BOOLEAN; fldID: INTEGER; fldVal: Handle);
```

SetFieldByID copies the zero-terminated string to which fldVal is a handle into the field ID fldID. If cardFld is TRUE, fldID is a card field; otherwise, it is a background field. The caller must dispose of the handle.

```
PROCEDURE SetFieldByName(paramPtr: XCmdPtr; cardFld: BOOLEAN; fldName: Str255; fldVal: Handle);
```

SetFieldByName copies the zero-terminated string to which fldVal is a handle into field fldName. If cardFld is TRUE, fldName is a card field; otherwise, it is a background field. The caller must dispose of the handle.

```
PROCEDURE SetFieldByNum(paramPtr: XCmdPtr; cardFld: BOOLEAN; fldNum: INTEGER; fldVal: Handle);
```

SetFieldByNum copies the zero-terminated string to which fldVal is a handle into the field number fldNum. If cardFld is TRUE, fldNum is a card field; otherwise, it is a background field. The caller must dispose of the handle.

```
PROCEDURE SetFieldTE(paramPtr: XCmdPtr; cardFieldFlag: BOOLEAN; fieldID, fieldNum: INTEGER; fieldNamePtr: StringPtr; fieldTE: TEHandle);
```

SetFieldTE sets the text and styles of the field to the text and styles contained in fieldTE.

Miscellaneous Utilities

```
PROCEDURE BeginXSound(paramPtr: XCmdPtr; window:
WindowPtr);
```

BeginXSound informs HyperCard that an XCMD is about to use the Sound Manager. An XCMD should call BeginXSound before it attempts to allocate a sound channel or perform any other Sound Manager operation. After an

XCMD calls BeginXSound, HyperCard's built-in play command will not operate until the XCMD calls EndXSound (see the next procedure).

If an external window is making the callback, it should pass a pointer to its window in the window parameter. An XCMD should pass NIL for the window parameter. An XCMD or an external window can optionally pass a pointer to a valid external window in the window parameter if it wants to "aim" the call at another external window. If HyperCard gets a valid WindowPtr in window, it will post an xGiveUpSoundEvt event to that window at an appropriate time. If the XCMD passes NIL for window, HyperCard will be unable to signal the XCMD when HyperCard needs the sound channel back.

An XCMD that uses the Sound Manager can be structured as follows:

```
BeginXSound(paramPtr, NIL);
(* allocate a sound channel *)
(* do your sound thing *)
(* deallocate sound channel *)
EndXSound(paramPtr);

PROCEDURE EndXSound(paramPtr: XCmdPtr);
```

EndXSound informs HyperCard that an XCMD has finished using the Sound Manager. If the XCMD has not previously called BeginXSound, EndXSound does nothing.

```
FUNCTION FrontDocWindow(paramPtr: XCmdPtr): WindowPtr;
```

FrontDocWindow returns the WindowPtr of the document that is frontmost in HyperCard's document layer. It does not return the WindowPtr of a window in the miniwindow layer. To return the frontmost window of any type, use the Window Manager's FrontWindow function.

```
FUNCTION GetFilePath(paramPtr: XCmdPtr; fileName: Str255; numTypes: INTEGER; typeList: SFTypeList; askUser: BOOLEAN; VAR fileType: OSType; VAR fullName: Str255): BOOLEAN;
```

GetFilePath determines the full pathname of the file fileName using the search paths stored in the Home stack. If fileType is 'STAK', GetFilePath uses the stack search paths. If fileType is 'APPL', GetFilePath uses the

application search paths. If fileType is neither 'STAK' nor 'APPL', GetFilePath uses the document search paths. The parameters numTypes and typeList are used as described in the chapter "Standard File Package" in *Inside Macintosh: Files*. If askUser is TRUE and HyperCard fails to find the file on its own, GetFilePath prompts the user to find the file with a standard file dialog box. If the file is located either by HyperCard or by the user, the full pathname of the file is returned in fullName and the file type is returned in fileType. If the user clicks Cancel in the standard file dialog box or HyperCard fails to find the file for any other reason, GetFilePath returns FALSE.

```
PROCEDURE GetXResInfo(paramPtr: XCmdPtr; VAR resFile: INTEGER; VAR resID: INTEGER; VAR rType: ResType; VAR name: Str255);
```

GetXResInfo returns the file reference number of the resource file from which the calling XCMD was read in resFile and the resource ID of the XCMD in resID, the resource type (XCMD or XFCN) in rType, and the resource name in name.

```
PROCEDURE Notify(paramPtr: XCmdPtr);
```

If HyperCard is active or MultiFinder is not loaded, Notify returns immediately. Otherwise, Notify blinks the small HyperCard icon over the Apple in the Apple menu (System 6) or over the Applications menu (System 7) until the user switches to HyperCard's layer. Only then does Notify return. No other HyperCard processing takes place while Notify is waiting.

```
PROCEDURE SendHCEvent(paramPtr: XCmdPtr; event:
EventRecord);
```

SendHCEvent is useful only to XCMDs that call the Toolbox routines GetNextEvent and WaitNextEvent. Such XCMDs should use SendHCEvent to pass events required by HyperCard. For example, an XCMD that creates a draggable window and calls GetNextEvent may receive update events for HyperCard windows. HyperCard performs the updates if it receives the update events via this callback. More importantly, an XCMD that calls GetNextEvent and receives an app4Evt generated by MultiFinder must pass the event along to HyperCard. If HyperCard does not receive its suspend and resume events, unexpected results may occur.

XCMDs that create windows by means of the NewXWindow callback don't need to call GetNextEvent or WaitNextEvent and therefore don't need to use SendHCEvent.

```
PROCEDURE SendWindowMessage(paramPtr: XCmdPtr; windPtr: WindowPtr; windowName: Str255; msq: Str255);
```

SendWindowMessage is functionally equivalent to send *message* to window *windowName* from HyperTalk. Use this for direct communication between XCMDs that manage external windows. If windPtr is not NIL, the window pointer in WindowPtr is used to determine which window receives the message; otherwise, the name in windowName is used.

```
FUNCTION StackNameToNum(paramPtr: XCmdPtr; stackName:
Str255): LongInt;
```

Internally, HyperCard no longer remembers stacks only by their name. It uses a stack number to represent the stack. This number is similar to a volume reference number: it is valid as an indicator as long as the application is open, but won't be valid across multiple launches. This number is valid when used in an XTalkObject to get and set the scripts of objects. StackNameToNum translates the name of a stack into this number.

Creating and Disposing of External Windows

```
FUNCTION GetNewXWindow(paramPtr: XCmdPtr; templateType: ResType; templateID: INTEGER; colorWind: BOOLEAN; floating: BOOLEAN): WindowPtr;
```

GetNewXWindow creates a new window or dialog box from a resource. If the Window Manager fails to create the window, GetNewXWindow returns NIL. If the window is created successfully, GetNewXWindow sets up the mechanism by which events pertaining to the window are sent to the XCMD that created it.

TemplateType must be either 'WIND' or 'DLOG'. TemplateID is the resource ID of the window or dialog box template to be used. The template resource can exist in any resource file that's currently open.

If colorWind is TRUE, HyperTalk attempts to create a color window using the GetNewCWindow or NewCDialog toolbox trap. If colorWind is TRUE and Color QuickDraw is not present, the window is not created and GetNewXWindow returns NIL.

If floating is TRUE, HyperTalk places the new window in the miniwindow layer. Otherwise, the window is placed into the document layer. See "Window Layer Management," later in this appendix, for an explanation of these two layers and their relationship to each other.

Note

GetNewXWindow is compatible with nonstandard window definition functions (see NewXWindow for more information). ◆

```
FUNCTION NewXWindow(paramPtr: XCmdPtr; boundsRect: Rect;
title: Str255; visible: BOOLEAN; procID: INTEGER;
colorWind: BOOLEAN; floating: BOOLEAN): WindowPtr;
```

NewXWindow creates a new window and returns a pointer to it as the function's result. If the Window Manager fails to create the window, NewXWindow returns NIL. If the window is created successfully, NewXWindow sets up the mechanism by which events pertaining to the window are sent to the XCMD that created it.

If colorWind is TRUE, HyperTalk attempts to create a color window using the NewCWindow Toolbox trap. If colorWind is TRUE and Color QuickDraw is not present, the window is not created and NewXWindow returns NIL.

The value in procID is the same as the procID argument to the Window Manager routine NewWindow. For example, passing documentProc as the procID produces a standard document window with no zoom box. BoundsRect is the bounding rectangle for the window in global coordinates. Title becomes the title of the window.

The visible argument determines whether the window is created visible.

To create windows similar to HyperCard miniwindows, such as the Tools palette and the Message box, use HyperCard's built-in window definition function for windows.

Here are the possible built-in window values to use for procID:

```
paletteProc = 2048; { window with grow box }
palNoGrowProc = 2052; { standard window }
palZoomProc = 2056; { window with zoom and grow }
palZoomNoGrow = 2060; { window with zoom and no grow }
hasZoom = 8;
hasTallTBar = 2;
toggleHilite = 1;
```

For example, the Navigator palette uses palNoGrowProc for procID.

Note

NewXWindow is also compatible with other nonstandard window definition functions. ◆

```
PROCEDURE CloseXWindow(paramPtr: XCmdPtr; window:
WindowPtr);
```

When an XCMD that manages an external window requests that the window be closed, it should call CloseXWindow. When all pending calls to the XCMD have returned, HyperCard sends an xCloseEvt to the XCMD. Only in response to this event should it dispose of its data structures and exit.

When the external window receives the xCloseEvt, it signals its willingness to close by setting paramPtr^.passFlag to TRUE. If this is not done, HyperTalk will not proceed with the disposal of the window.

HyperTalk tries to close all open external windows when the user quits HyperCard. If any windows refuse to close at that time, HyperCard will not quit.

Do not use any of the following Toolbox routines to close external windows: CloseWindow, DisposeWindow, CloseDialog, and DisposDialog.

Any XCMD can close any external window created with the NewXWindow or GetNewXWindow calls by means of a call to CloseXWindow. CloseXWindow has no effect on windows that were not created by means of a call to NewXWindow or GetNewXWindow.

You can also close an external window from a script with the close window command.

Window Utilities

```
PROCEDURE HideHCPalettes(paramPtr: XCmdPtr);
```

HideHCPalettes hides all of HyperCard's built-in miniwindows (the Tools palette, the Patterns palette, the FatBits window, the Scroll window, and the Message box).

```
PROCEDURE RegisterXWMenu(paramPtr: XCmdPtr; menu: MenuHandle; registering: BOOLEAN);
```

RegisterXWMenu is useful only to XCMDs that manage external windows. RegisterXWMenu informs HyperCard that the given menu is meant for use with the external window. When an item in the menu is chosen by the user, the XCMD that registered the menu chosen receives a menu event (xMenuEvt). Note that an XCMD can register one of HyperCard's menus, for example, the Font menu, in order to borrow the menu temporarily.

RegisterXWMenu does not change the menu bar. The XCMD must call the Menu Manager in order to insert or delete the menu and to redraw the menu bar. Once the menu has been registered, it remains the property of the XCMD until RegisterXWMenu is called again with registering set to FALSE.

Note

HyperCard expects XCMD menus to have unique IDs but does not ensure that they do. You may employ the following function to find an unused menu ID. ◆

```
FUNCTION UnusedMenuID: INTEGER;
VAR thisID: INTEGER;
     menuHndl: MenuHandle;

BEGIN
   thisID := 1023;
   REPEAT
     thisID := thisID + 1;
     menuHndl := GetMHandle(thisID);
   UNTIL menuHndl = NIL;
   UnusedMenuID := thisID;

END;
```

```
PROCEDURE SetXWIdleTime(paramPtr: XCmdPtr; ticks: LongInt);
```

XCMDs that manage external windows can request idle time from HyperCard. Use SetXWIdleTime if your XCMD needs to perform a periodic action.

Until SetXWIdleTime is called by an XCMD, the XCMD does not receive periodic calls. A value greater than 0 for ticks represents the requested interval between periodic calls by HyperCard. HyperCard sends the XCMD a nullEvent message when making its periodic call. Call SetXWIdleTime only after your external window has received an xOpenEvt.

Whether HyperCard's periodic calls occur as often as requested depends on whether HyperCard is currently performing a timing-critical or data-intensive operation.

To give up idle time, call SetXWIdleTime with a value of 0 for ticks.

Note

NullEvent messages are sent in both the foreground and background under MultiFinder. ◆

```
PROCEDURE ShowHCPalettes(paramPtr: XCmdPtr);
```

ShowHCPalettes reverses the effect of HideHCPalettes, showing all of HyperCard's miniwindows that were visible when HideHCPalettes was called to hide them.

```
PROCEDURE XWHasInterruptCode(paramPtr: XCmdPtr; haveCode:
BOOLEAN);
```

When HyperCard creates an external window (by means of either the NewXWindow or GetNewXWindow callback), it is assumed that the code of the XCMD that manages it can be moved in memory when it is not executing.

If haveCode is TRUE, HyperCard never unlocks the relocatable block containing the XCMD code in memory. This allows ProcPtrs and other addresses within an XCMD's code to be preserved and valid at all times. XWHasInterruptCode should be used with extreme prudence and should be undone as soon as possible—HyperCard's memory management can become seriously taxed if there are any locked blocks inconveniently located in its heap. In particular, it's impossible to open card windows at the full size of large cards when a nonrelocatable block is located too close to the bottom of the application heap.

The preferred method for an XCMD to manage procedure pointers passed to the Toolbox is to refresh them as needed rather than to call XWHasInterruptCode to ensure their validity. This method permits HyperCard to unlock the XCMD's code between invocations. An example of such an XCMD is a text editor with a custom clikLoop routine. For best results, such an XCMD should recalculate and refresh its procPtr every time the user clicks the viewRect. For example:

An XCMD that uses this method will have no need to call XWHasInterruptCode.

An XCMD's code is always locked while it is actually executing. XWHasInterruptCode determines only whether the block of code can be unlocked when control is returned to HyperCard.

```
PROCEDURE XWAlwaysMoveHigh(paramPtr: XCmdPtr; moveHigh:
BOOLEAN);
```

XWAlwaysMoveHigh tells HyperTalk to always move the external window's code high on the heap before locking it down and calling it. External windows that may allocate large amounts of memory or send card messages to do such operations as go to another card should use this call.

In normal XCMD and external window operations, HyperTalk makes a determination at the time the code is jumped to as to whether the code should be moved high in the application heap before being locked down. Currently, this is done whenever an XCMD is called and when an external window is given the following events: xOpenEvt, xMenuEvt, mouseDown, and keyDown. All other events are assumed to rarely cause memory allocation or messages to be sent; therefore, HyperTalk can speed up the process of calling and returning from an external window. However, some external windows may allocate

memory on such things as an xSetPropEvt event. For example, a picture XCMD could be asked to change information about the currently displayed PICT, and that may cause memory to be allocated. A good rule of thumb is if your external window is not called repeatedly in a script and you might allocate memory on events other than the aforementioned events, call this with moveHigh = TRUE.

```
PROCEDURE XWAllowReEntrancy(paramPtr: XCmdPtr; allowSysEvts: BOOLEAN; allowHCEvts: BOOLEAN);
```

XWAllowReEntrancy allows an XCMD to tell HyperCard whether it is equipped to receive events (either system events or HyperCard-generated events) in a reentrant fashion. Either of the Booleans, allowSysEvts or allowHCEvts, can be set to TRUE or FALSE to enable or disable (respectively) this behavior.

In certain situations, it is possible for an external window to generate events for itself. In other words, calling the Window Manager's InvalRect routine on a portion of the window could create an updateEvt event for the window.

While running scripts, HyperTalk periodically checks the Event Manager to see if update, activate, or MultiFinder events are pending. This is how HyperCard processes events in the background. In the course of these checks, the Window Manager may report an update event for the external window if it notices that any or all of the window is invalid. The problem arises from external windows that use SendCardMessage, SendHCMessage, EvalExpr, or any other HyperTalk callback that can run a script. XWAllowReEntrancy was implemented to allow external windows to perform asynchronous handling of certain events. For example, if a SendCardMessage callback causes a lengthy script to be executed, the external window may want to be notified that the user switched out of HyperCard under MultiFinder. The default is for HyperTalk to not allow these reentrant calls to take place. Unlike system events, HyperTalk events are not queued, so unreceived events are ignored.

Note

An external window should only call XWAllowReEntrancy at the end of its response to an xOpenEvt event. The first event that is sent to an external window is its xOpenEvt event. •

Because xGetPropEvt and xSetPropEvt are events, if an external window has not called XWAllowReEntrancy(paramPtr,xxxx,TRUE), the scenario described below results in the external window never receiving its xSetPropEvt for its visible property:

```
SendCardMessage(paramPtr,'go next card');
  on closeCard
    hide window "fred" -- this call will fail
  end closeCard
```

The xSetPropEvt causes the external window to be reentered, so HyperTalk skips the event and continues. If your external window needs to communicate with running scripts, make sure that you allow it to be reentrant.

Writing completely reentrant code is difficult, and some development systems may not support reentrancy correctly. One tip is to make sure that every time an external window receives an event, it should completely save and restore its state. A good idea is to use the external window's refCon field to store a handle to all the window's state information. Beware of the use of global variables in stand-alone code resources. See Macintosh Technical Note 256 for more information.

Text Editing Utilities

```
PROCEDURE BeginXWEdit(paramPtr: XCmdPtr; window: WindowPtr);
```

BeginXWEdit registers an external window as the current editing environment. It can be called only by the XCMD that manages the window. Once it is called, HyperCard redirects all keystrokes to the XCMD, with the exception of Command-key combinations recognized by the Menu Manager as the equivalent of menu items. In addition, HyperCard passes events to the XCMD that correspond to the first five commands in the Edit menu whenever these commands are chosen. The XCMD still receives all of the other events pertaining to its window, including nullEvents if it has requested them.

Once the XCMD has registered itself as the current editing environment, it receives an xGiveUpEdit event from HyperCard when the user performs an action that activates a different editing environment, such as a click in the

Message box or in an unlocked field. When this happens, the XCMD should deactivate its editable area as appropriate, just as it does when its window is deactivated.

```
PROCEDURE EndXWEdit(paramPtr: XCmdPtr; window: WindowPtr);
```

EndXWEdit informs HyperCard that an XCMD no longer wants to receive keystrokes and edit events for its external window.

Call EndXWEdit before an external window that is an editing environment is closed.

```
FUNCTION HCWordBreakProc(paramPtr: XCmdPtr): ProcPtr;
```

HCWordBreakProc returns a procedure pointer to HyperCard's built-in word-break routine used for text in fields, scripts, and the Message box. Script editors and other text editing XCMDs can use this address in the wordBreak field of a TextEdit record.

```
PROCEDURE PrintTEHandle(paramPtr: XCmdPtr; hTE: TEHandle;
header: StringPtr);
```

Given a handle to a TextEdit record in hTE, PrintTEHandle displays a print job dialog box and prints the record using the font, size, and style information contained within it. PrintTEHandle works for both old- and new-style edit records.

Script Editor Utilities

```
PROCEDURE FormatScript(paramPtr: XCmdPtr; scriptHndl: Handle; VAR insertionPoint: LongInt; quickFormat: BOOLEAN);
```

FormatScript reformats the script contained in the zero-terminated string to which scriptHndl is a handle. Call ZeroTermHandle before calling FormatScript if the text is not zero-terminated.

The offset into the text passed in insertionPoint is adjusted as necessary to reflect the same position within the text both before and after formatting. An XCMD that uses TextEdit should pass TEHandle^^.selStart for this parameter, then call TESetSelection after FormatScript returns.

InsertionPoint is also used when quickFormat is TRUE to determine which handler within the script should be formatted.

Note

Using EvalExpr to get the script of an object formats it automatically. ◆

```
FUNCTION GetCheckPoints(paramPtr: XCmdPtr): CheckPtHandle;
```

GetCheckPoints returns a handle to the cached checkpoints for the window's script. The caller must dispose of the handle. If there are no cached checkpoints, GetCheckPoints returns NIL.

The structure of a CheckPtHandle is as follows:

Given a zero-terminated handle to a script in scriptText, SaveXWScript saves the script to disk. Call ZeroTermHandle before calling SaveXWScript if the text is not zero-terminated.

This callback is reserved for the use by XCMDs that implement script editors. It fails if the XCMD has not been called by HyperCard as the current script editor. SaveXWScript also fails if the text of the script exceeds 32 KB.

Note

An XCMD can set the script of any object using the following example code:

```
SetGlobal(paramPtr,'tempGlobal',scriptHndl);
SendCardMessage(paramPtr, CONCAT('set the script of ',objectName, ' to
   tempGlobal'));
SendCardMessage(paramPtr,'put empty into tempGlobal');
```

```
PROCEDURE SetCheckPoints(paramPtr: XCmdPtr; checkLines:
CheckPtHandle);
```

SetCheckPoints sets the checkpoints of a script to the array of lines in checkLines.

```
PROCEDURE GetObjectName(paramPtr: XCmdPtr; object:
XTalkObject; VAR objName: Str255);
```

Given an XTalkObject as input, returns the name of the object in objName.

```
PROCEDURE GetObjectScript(paramPtr: XCmdPtr; object:
XTalkObject; VAR scriptHndl: Handle);
```

Given an XTalkObject as input, returns the script of the object in scriptHndl.

```
PROCEDURE SetObjectScript(paramPtr: XCmdPtr; object:
XTalkObject; scriptHndl: Handle);
```

Given an XTalkObject and a handle to a script as input, sets the script of the object described by XTalkObject to the script in scriptHndl.

Variable Watcher Support

```
PROCEDURE CountHandlers(paramPtr: XCmdPtr; VAR
handlerCount: INTEGER);
```

CountHandlers returns the number of running handlers in handlerCount. If handlerCount is 0, then no handlers are currently running and the only variables that exist are global variables.

```
PROCEDURE GetHandlerInfo(paramPtr: XCmdPtr; handlerNum: INTEGER; VAR handlerName: Str255; VAR objectName: Str255; VAR varCount: INTEGER);
```

GetHandlerInfo returns information about handlers. If handlerNum is 1, GetHandlerInfo returns information about the current handler, if there is one. If handlerNum is greater than 1, GetHandlerInfo returns

information about a handler that has a pending call to another handler. For example, if handlerNum is 2, the information returned is for the handler that called the current handler. If there is no running handler, passing 0 for handlerNum yields information about the global variables.

```
PROCEDURE GetVarInfo(paramPtr: XCmdPtr; handlerNum: INTEGER; varNum: INTEGER; VAR varName: Str255; VAR isGlobal: BOOLEAN; VAR varValue: Str255; varHndl: Handle);
```

Given the variable number varNum in active handler number handlerNum, GetVarInfo returns information about the variable. If varHndl is NIL, a truncated version of the contents of the variable, limited to 255 characters, is returned in varValue. If varHndl is a valid handle, the entire contents of the variable are copied into that handle, which is resized as necessary. If there is no running handler, passing 0 for handlerNum returns information about the global variables.

```
PROCEDURE SetVarValue(paramPtr: XCmdPtr; handlerNum: INTEGER; varNum: INTEGER; varHndl: Handle);
```

SetVarValue sets the value of variable number varNum of handler handlerNum to the zero-terminated string passed in varHndl.

Note

Changing the value of a variable other than the global variables (handlerNum 0) or the variables local to the current handler (handlerNum 1) does not affect the handler until it is once again current. •

Debugger Support

```
PROCEDURE AbortScript(paramPtr: XCmdPtr);
```

AbortScript cancels the currently executing handlers. The effect is the same as pressing Command-period or choosing Abort from the HyperCard built-in Debugger menu.

Note

An XCMD that calls AbortScript is not itself aborted. It exits normally. ◆

```
FUNCTION GetStackCrawl(paramPtr: XCmdPtr): Handle;
```

Returns a zero-terminated handle to the chain of callers (indented) as in the Message Watcher.

```
PROCEDURE GoScript(paramPtr: XCmdPtr);
```

GoScript exits the debugger, closes all temporary debugger windows, and continues normal execution of scripts.

```
PROCEDURE StepScript(paramPtr: XCmdPtr; stepInto: BOOLEAN);
```

StepScript creates a temporary checkpoint after the currently executing line. If stepInto is TRUE, the checkpoint is created at the next line of HyperTalk to be executed, even if it belongs to another handler. If stepInto is FALSE, the checkpoint is created at the next line of the current handler. StepScript causes the debugger to step out of a handler if the current line is its last.

```
PROCEDURE TraceScript(paramPtr: XCmdPtr; traceInto:
BOOLEAN);
```

TraceScript is similar to StepScript above, except that execution continues after the line is highlighted by the debugger. TraceScript respects the new HyperTalk property traceDelay.

External Windows

The HyperCard XCMD interface includes support for external windows. HyperCard's built-in external windows are the script editor and the debugger tools Variable Watcher and Message Watcher, which are all described earlier in this book. All of these windows and their properties can be controlled through scripts. You can write your own XCMDs to replace any one of the built-in HyperCard external windows. You can also write XCMDs that provide any kind of useful application within a window, such as custom text editors, color picture editors, video overlay windows, and so on.

External windows are an extension of external commands. Two new callbacks, NewXWindow and GetNewXWindow, direct HyperCard to create a new external window. When an XCMD executes either of these callbacks, HyperCard creates a new window and saves with it a reference to the XCMD that made the call.

Then, whenever HyperCard receives an event from the Toolbox Event Manager, it first determines whether the event pertains to an external window. If so, HyperCard calls the XCMD that created the window with arguments that allow it to handle the event. Otherwise, HyperCard handles the event itself.

Whenever an XCMD is called by HyperCard, it receives a pointer to an XCmdBlock parameter block. See "Parameter Block Data Structure," earlier in this appendix, for the Pascal parameter block structure.

When HyperCard calls an XCMD to handle an event for an external window, some of the fields of XCmdBlock have new values. The paramCount field is set to -1, indicating that the XCMD has been called to handle an event. The first parameter, params[1], is a pointer to an XWEventInfo block, defined as follows:

```
XWEventInfoPtr = ^XWEventInfo;
XWEventInfo = RECORD
  ownerWindow: WindowPtr;
    theEvent: EventRecord;
    eventParams: ARRAY[1..9] OF LongInt;
    eventResult: Handle;
END;
```

Therefore, an XCMD that manages an external window can be structured as follows:

```
IF paramPtr^.paramCount >=0 THEN CreateMyWindow
ELSE
BEGIN
    WITH XWEventInfoPtr(paramPtr^.params[1])^ DO
    BEGIN
        myEvent := theEvent;
        myWindow := ownerWindow;
    END;
SetPort(myWindow);
CASE myEvent.what OF
    mouseDown: DoMouse;
    and more code here...
END;
```

External Windows 535

When an XCMD has been called to handle an event, it has full access to callback routines, just as it does when invoked from a HyperTalk script.

Events in External Windows

HyperCard automatically sends most standard Macintosh events to XCMDs that manage external windows. These include the following events:

```
activateEvt

app4Evt (miniwindows should hide themselves when suspended and show themselves when resumed)

mouseDown

nullEvent (see SetXWIdleTime)

updateEvt
```

Keyboard events (keyDown and autoKey) are delivered to the XCMD only if it has registered itself as the active editing environment with the BeginXWEdit callback. All keystrokes, with the exception of Command-key combinations recognized by the Menu Manager as equivalents of menu items, are sent to an XCMD when it is the active editing environment.

In addition, XCMDs that manage windows receive messages specific to HyperCard. These are delivered in the same EventRecord data structure used for standard Macintosh events, with the what field set to one of the following constants:

```
= 1000;
                           { the first event after window is created}
x0penEvt
xCloseEvt
                  = 1001;
                          { the window will be closed}
xGiveUpEditEvt
                  = 1002;
                           { you are losing Edit}
                          { the sound channel is requested}
xGiveUpSoundEvt
                  = 1003;
xEditUndo
                  = 1100;
                           { Edit--Undo}
xEditCut
                  = 1102;
                           { Edit--Cut}
                  = 1103;
                          { Edit--Copy}
xEditCopy
                  = 1104;
                          { Edit--Paste}
xEditPaste
xEditClear
                  = 1105;
                          { Edit--Clear}
xSendEvt
                  = 1200;
                           { script has sent a message (text)}
xSetPropEvt
                  = 1201;
                           { set a window property}
```

APPENDIX A

External Commands and Functions

```
xGetPropEvt
                  = 1202;
                           { get a window property}
xCursorWithin
                  = 1300;
                            { cursor is within the window}
                           { an item in your menu is selected}
xMenuEvt
                  = 1400;
xMBarClickedEvt
                  = 1401;
                           { menu is about to be shown or updated }
xShowWatchInfoEvt = 1501;
                           { variable and message watcher event}
xScriptErrorEvt
                  = 1502;
                           { place the insertion point}
xDebugErrorEvt
                  = 1503;
                           { user clicked Debug at complaint}
xDebugStepEvt
                  = 1504;
                           { highlight the line stepping}
xDebuqTraceEvt
                  = 1505;
                           { highlight the line tracing}
xDebugFinishedEvt = 1506;
                           { script ended}
```

Handling Events

Many of the events above require special attention. Many are specific to the debugger or other debugging tools. Here is a summary of all the events and their appropriate behavior:

xOpenEvt Use this event to set up the external window-specific parts of

your code, such as any of the callbacks that have an XW in their name. These are RegisterXWMenu, SetXWIdleTime,

XWHasInterruptCode, XWAlwaysMoveHigh, and

XWAllowReEntrancy.

xCloseEvt HyperTalk sends your external window an xCloseEvt event when

your window has called CloseXWindow, when another external window or XCMD has called CloseXWindow using your window's WindowPtr, or when the user has used the new close window "windowName" command. The external window should not dispose of any of its data until receiving this event. If the external window sets passFlag to TRUE, the window is disposed. If not, the window

is left open.

xGiveUpEditEvt When an external window calls BeginXWEdit, it will receive

keystrokes and Edit menu commands until the user clicks back in the card window or activates some other editing window (for example, the Message box). HyperTalk signals the current editor with an xGiveUpEditEvt event just before it activates the

other editor.

continued

External Windows 537

xGiveUpSoundEvt In the event that one external window requests the sound channel

(with BeginXSound) while another external window has the channel, the current owner is given an xGiveUpSoundEvt. If the external window doesn't set passFlag to TRUE, the other external window's callback returns with the result code set to xresFail. If an XCMD owns the sound channel, it can't be notified of the second

request, so that request will fail.

xEditUndo While an external window is the editing environment, it receives this

event, which corresponds to the Undo command in HyperCard's

built-in Edit menu.

xEditCut While an external window is the editing environment, it receives this

event, which corresponds to the Cut command in HyperCard's

built-in Edit menu.

xEditCopy While an external window is the editing environment, it receives this

event, which corresponds to the Copy command in HyperCard's

built-in Edit menu.

xEditPaste While an external window is the editing environment, it receives this

event, which corresponds to the Paste command in HyperCard's

built-in Edit menu.

xEditClear While an external window is the editing environment, it receives this

event, which corresponds to the Clear command in HyperCard's

built-in Edit menu.

xSendEvt When a user issues the send message to window command,

or when an XCMD or external window issues the

SendWindowMessage callback, the external command receives an xSendEvt event. When this event is received, eventParams[1] contains a pointer to a Pascal string (Str255) containing the name of the message. This is done for speed purposes and to expedite using the StringEqual callback to index through the commands your

window supports.

xSetPropEvt HyperTalk contains new extensible syntax for setting properties of

external windows. The syntax is

set property of window to propertyValue

xGetPropEvt HyperTalk contains new extensible syntax for getting properties of

external windows. The syntax is

get property of window

HyperTalk has two built-in properties of external windows: loc and visible. If an external window doesn't do anything special in response to being moved, shown, or hidden, it can set passFlag to TRUE in response to both xSetPropEvt and xGetPropEvt and HyperTalk handles the request. If a property is requested other than the two built-in ones and the external window passes the event, HyperTalk displays an error dialog box to the user.

HyperCard 2.2 adds these built-in properties: rectangle, width, height, and the corresponding rectangle properties (see Chapter 12). These properties are read-only. If you want to change these properties, your XCMD must handle this itself.

If the external window wishes to respond specially to these requests, or if it has additional properties it wants to support, it can directly handle all of HyperTalk's requests. In both xSetPropEvt and xGetPropEvt, eventParams[1] contains a pointer to a Pascal string (Str255) containing the name of the property. In the case of an xSetPropEvt, eventParams[2] contains a handle to the property value. In the case of an xGetPropEvt event, the external window must return a handle in the eventResult field with the value of the property requested.

HyperTalk gets and sets the visible property to translate the hide and show commands. In the event the user says hide window "Variable Watcher", HyperTalk informs the external window by giving it an xSetPropEvt event with the property visible and the value false.

For an example of the ability of external windows to use properties, try these properties of the Message Watcher window: loc, visible, hideIdle, hideUnused, text, and nextLine (set only). The Variable Watcher supports the following properties: loc, visible, hBarLoc, vBarLoc, and rect.

There are four new callbacks to aid in getting and setting properties: PointToStr, RectToStr, StrToPoint, and StrToRect.

xCursorWithin This event is sent when the cursor is over any part of the external

window. If the external window sets passFlag to TRUE,

HyperCard sets the cursor to an arrow.

xMenuEvt When an external window has used RegisterXWMenu for one or

more menus in HyperCard's menu bar, HyperTalk notifies it of an item being chosen by sending it an xMenuEvt event. This holds true for Command-key equivalents as well. When the event is received, eventParams[1] is the menu ID and eventParams[2]

is the menu item.

continued

External Windows 539

APPENDIX A

External Commands and Functions

xMBarClickedEvt If an external window has registered one or more menus in the

menu bar, HyperTalk sends it an xMBarClickedEvt event just before it calls the Menu Manager's MenuSelect or MenuKey routine. This is to allow the external window to adjust its menus

just before the user sees them.

xShowWatchInfoEvt Sent to the Message Watcher and Variable Watcher whenever it is

appropriate. For the Message Watcher, eventParams[1] contains a handle to the current message. For the Variable Watcher, there

are no arguments sent.

xScriptErrorEvt Sent to the current script editor when HyperTalk displays the

"Debug, Script, or Cancel" alert and the user clicks Script.

EventParams[1] contains the line number on which the

error occurred.

xDebugErrorEvt, xDebugStepEvt, xDebugTraceEvt Sent to the current debugger window.

xDebuqFinishedEvt Sent to all external windows when the user chooses the Go or

Abort command in the Debugger menu.

Closing an External Window

External windows should *only* dispose of their private data structures in response to an xCloseEvt event. Whenever an XCMD calls CloseXWindow, it should not dispose of any of its internal information until it receives its xCloseEvt event.

When an xCloseEvt event is sent, the XCMD must set passFlag to TRUE if it actually wants to close. If it does not set passFlag, it is telling HyperTalk that it wants to cancel the close operation. This is useful for editors that put up a "Save this document?" dialog box that includes a Cancel button.

Special XCmdBlock Values

Because special XCMDs like the Message Watcher and script editor look like normal XCMDs, there has to be some defense against a user typing ScriptEditor in the Message box and launching the script editor. Therefore, the special-case XCMDs are given special parameter blocks when they are opened by HyperTalk.

Message Watcher

When HyperTalk calls the Message Watcher to initialize itself, it sets $\label{lem:paramPtr^.paramCount} paramCount to xMessageWatcherID (-2). There are no parameters sent. The Message Watcher is called at startup time and is always present. If you switch to another message watcher (using set the messageWatcher to "MyWatcher"), that watcher is loaded immediately. The normal behavior of a message watcher is that it should be inactive when it is invisible.$

Variable Watcher

When HyperTalk calls the Variable Watcher to initialize itself, it sets paramPtr^.paramCount to xVariableWatcherID (-3). There are no parameters sent. The Variable Watcher is called at startup time and is always present. If you switch to another variable watcher (using set the variableWatcher to "MyWatcher"), that watcher is loaded immediately. The normal behavior of a variable watcher is that it should be inactive when it is invisible.

Script Editor

When HyperTalk calls a script editor to initialize itself, it sets paramPtr^.paramCount to xScriptEditorID (-4). There are three parameters sent. Params[1] is a zero-terminated handle to the script of the object (unindented). Params[2] is a pointer to a Pascal string (Str255) containing the name of the window as proposed by HyperTalk (for example, script of card button id 4 = "Fred"). Params[3] is a pointer to the XTalkObject structure describing the object to be edited (see the next section).

Note

There can be multiple script editors open at once, all sharing the same copy of the XCMD resource in memory. For this reason, XCMDs must not write to their own code, or serious problems can result. ◆

External Windows 541

Debugger

A debugger window is initialized the same as a script editor, with the exception that the paramPtr^.paramCount is set to xDebuggerID (-5).

XTalkObject

In order to increase a script editor's flexibility, it can communicate with HyperTalk using a special data structure called XTalkObject. Each time a script editor is opened, it is passed a pointer to this structure describing the object whose script is being edited. However, any XCMD can use it as long as the relevant fields are filled in correctly.

```
XTalkObjectPtr = ^XTalkObject;
XTalkObject = RECORD
      objectKind:
                      INTEGER; { stack, bkgnd, card, field,
                                or button }
      stackNum:
                      LongInt; { reference number of the
                                source stack }
      bkgndID:
                      LongInt;
      cardID:
                      LongInt;
      buttonID:
                      LongInt;
      fieldID:
                  LongInt;
   END;
```

objectKind The type of object: stackObj, bkgndObj, cardObj, fieldObj,

buttonObj.

The reference number of the stack containing the object. Use

StackNameToNum to get the stacknum of a stack when you know the name. Use GetObjectName to get the name of the stack if all you know is the number. If XTalkObject.objectKind = stackObj, this is the

last relevant field.

bkgndID The ID of the background. If XTalkObject.objectKind = bkgndObj,

this is the last relevant field. If the object is a card, this is the background to which the card belongs. If the object is a background field or button, this is

the ID of the background to which the field or button belongs.

continued

APPENDIX A

External Commands and Functions

cardID	The ID of the card. If XTalkObject.objectKind =	cardObj, this is
--------	---	------------------

the last relevant field. If the object is a card field or button, this is the ID of

the card to which the field or button belongs.

buttonID The buttonID is the ID of the button. If the button is a card button,

cardID contains the ID of the button's card. If the button is a background

button, bkqndID contains the ID of the button's background.

fieldID The fieldID is the ID of the field. If the field is a card field, cardID

contains the ID of the field's card. If the field is a background field,


bkgndID contains the ID of the field's background.

Window Layer Management

Within HyperCard, each window resides in one of three layers: the dialog layer, the miniwindow layer, or the document layer, as shown in Figure A-2.

External Windows 543

Figure A-2 HyperCard window layers



The front layer, the dialog layer, is reserved for modal dialog boxes. Any window that forces the user to complete a task before continuing, such as the standard file dialog box and HyperCard's ask dialog box, belongs in this layer.

The center layer, the miniwindow layer, is reserved for windows that have a single state, such as HyperCard's Tools palette, which is always active when it is visible. All of HyperCard's floating windows, including the Message box and the Tools palette, reside in this layer. Windows in this layer never receive activate events.

The rear layer is the document layer. Windows that have multiple states, active and inactive, such as HyperCard card windows and script editing windows, reside in this layer.

If your window resides in the document layer and you wish to determine whether it's frontmost in its layer, use the FrontDocWindow callback. The Window Manager routines, such as FindWindow and FrontWindow, operate

in the HyperCard window environment. For example, FrontWindow returns a pointer to the frontmost window.

HyperCard automatically inserts new external windows in the proper layer according to type (see the description of the NewXWindow callback).

An XCMD can determine the layer in which its external windows reside by using the floating argument to GetNewXWindow and NewXWindow. If floating is TRUE, the window is placed at the front of the miniwindow layer; otherwise, it is placed at the front of the document layer.

```
FUNCTION NewXWindow(paramPtr: XCmdPtr; boundsRect: Rect;
title: Str255; visible: BOOLEAN; procID: INTEGER; color:
BOOLEAN; floating: BOOLEAN): WindowPtr;

FUNCTION GetNewXWindow(paramPtr: XCmdPtr; templateType:
ResType; templateID: INTEGER; color: BOOLEAN; floating:
BOOLEAN): WindowPtr;
```

The dialog layer isn't really a layer at all; rather, it is reserved for use by modal windows and dialog boxes. Use the Macintosh Window Manager's routines to create and remove windows in the dialog layer, but do not leave them up after the XCMD has returned.

Flash: An Example XCMD

A simple example external command included with HyperCard is flash, which inverts the screen display (changes the black pixels to white and vice versa) a specified number of times. A version of flash written and compiled in MPW Pascal has already been attached to the HyperCard application file (that is, to HyperCard itself).

Flash is invoked from HyperCard just like a HyperTalk command. That is, you send the message flash to HyperCard from the Message box or from an executing script. The flash message takes one parameter: an integer. The flash XCMD inverts the screen display twice that many times. For example, the following handler, in response to a mouseUp message, sends the flash

message and its parameter. When the message reaches HyperCard, it invokes the flash external command, which inverts the screen display 20 times:

```
on mouseUp
flash 10
end mouseUp
```

The screen display flashes (is inverted and inverted back again) 10 times.

Flash Listing in MPW Pascal

Here's the Pascal listing for flash:

```
( *
* Flash.p-A sample HyperCard XCMD to highlight the screen
            Copyright Apple Computer, Inc. 1987-1993.
            All Rights Reserved.
* Build instructions for MPW 3.3 (puts XCMD in a ResEdit file):
  Pascal Flash.p -o Flash.p.o
  Link -t rsrc -c RSED -rt XCMD=0 -m ENTRYPOINT -sg Flash \partial
      Flash.p.o \partial
      "{Libraries}"HyperXLib.o \partial
      -o "Flash XCMD"
* )
{$R-}
{$S Flash} { Segment name must be same as command name }
( *
* DummyUnit is what HyperTalk jumps to when running the XCMD.
* Also note that XCMDs do not support their own A5 World,
```

```
* thus NO GLOBAL VARIABLES are allowed.
 *)
UNIT DummyUnit;
INTERFACE
USES Types, QuickDraw, SysEqu, HyperXCmd;
PROCEDURE EntryPoint(paramPtr: XCmdPtr);
IMPLEMENTATION
PROCEDURE Flash(paramPtr: XCmdPtr); FORWARD;
PROCEDURE EntryPoint(paramPtr: XCmdPtr);
BEGIN
  Flash(paramPtr);
END;
PROCEDURE Flash(paramPtr: XCmdPtr);
        flashCount: INTEGER;
  VAR
         again:
                    INTEGER;
        port:
                    GrafPtr;
                    Str255;
         str:
         when:
                    LONGINT;
        ticksPtr: ^LONGINT;
   BEGIN
      flashCount := 0;
      IF (paramPtr^.paramCount = 1) THEN BEGIN
         { first param is flash count }
         ZeroToPas(paramPtr, paramPtr^.params[1]^, str);
```

```
flashCount := StrToNum(paramPtr, str);
END;

IF (paramPtr^.paramCount <> 1) OR (flashCount < 1) THEN
    flashCount := 3;

GetPort(port);
ticksPtr := POINTER(Ticks); { 'Ticks' defined in SysEqu.p }

FOR again := 1 TO 2 * flashCount DO BEGIN
    when := ticksPtr^ + 4;
    InvertRect(port^.portRect);
    REPEAT UNTIL ticksPtr^ >= when;
END;
```

END.

Flash Listing in MPW C

Here's a version of flash written in MPW C:

```
Build instructions for THINK C 6.0:
      Build as a Code Resource of type XCMD;
      add MacTraps and HyperXLib libraries to project;
      will not need compiler's standard Prefix.
* /
#include<Types.h>
#include<Quickdraw.h>
#include<SysEqu.h>
#include<HyperXCmd.h>
/*
   Your routine MUST be the first code that is generated in the file,
   as HyperTalk simply JSRs to the start of the XCMD segment in
   memory. Note that XCMDs do not support their own A5 World,
   thus NO GLOBAL VARIABLES are allowed.
pascal void main( XCmdPtr paramPtr )
{
   short flashCount = 0, again;
  GrafPtr port;
   Str255
           str;
           when;
   long
   unsigned long *ticksPtr;
   if ( paramPtr->paramCount == 1)
      /* get flash count*/
      ZeroToPas(paramPtr, *(paramPtr->params[0]), (StringPtr)str);
      /* convert string to number*/
      flashCount = StrToNum(paramPtr, (StringPtr)str);
   }
```

```
if ((paramPtr->paramCount != 1) || (flashCount < 1))
    flashCount = 3;

GetPort(&port);
ticksPtr = (unsigned long *)Ticks;
flashCount *= 2;

for (again = 1; again <= flashCount; again++)
{
    when = *ticksPtr + 4;
    InvertRect( &port->portRect);
    while ( *ticksPtr < when );
}</pre>
```

Flash Listing in 68000 Assembly Language

Here's the 68000 assembly-language listing for flash:

```
* Flash.a

* A sample HyperCard XCMD in 68000 Assembly

* Copyright Apple Computer, Inc. 1988-1993

* All Rights Reserved.

* This version of the Flash XCMD, 'AFlash', only looks at the first character of parameter 1. It does not have the timing code of the Pascal and C versions.

* Build Instructions:

* Asm Flash.a -o Flash.a.o

* Link -t rsrc -c RSED -rt XCMD=7 -sg AFlash Flash.a.o d

* -o "AFlash XCMD"
```

APPENDIX A

External Commands and Functions

```
INCLUDE'QuickEqu.a'
  INCLUDE'Traps.a'
  SEG 'AFlash'
                    ; Segname must be same as command name
PROC
                    ; uses a0, a1, d1
AFlash
  link a6, #-4
  move.1 d4,-(sp)
                   ; save
                   ; StrToNum default result
  move.w #3,d4
  move.1 8(a6),a0; get paramPtr in a temp reg
  move.l 2(a0),a1
                   ; get handle to flashCount (as C string)
  cmpa.1 #0,a1
                    ; if handle NIL, use default
  beq.s @2
  move.l (a1),a1
                   ; deref
@1 move.b (a1)+,d1
                   ; get a char
  cmp.b #'1',d1
                    ; test for a non-0 digit
  blt.s @2
                    ; less than valid
  cmp.b #'9',d1
  bqt.s @2
                    ; greater than valid
  and.w #$000F,d1 ; mask to value of legal char
  move.w d1,d4
                    ; stick value into result
@2 pea -4(a6)
                    ; var result of GetPort
  GetPort
  bra.s @4
                    ; get into DBRA loop
@3 move.l -4(a6),a0 ; get port
  pea portRect(a0)
                    ; address or portRect
  InverRect
  move.1 -4(a6),a0
                   ; get port
  pea portRect(a0) ; address or portRect
```

```
_InverRect
@4 dbra d4,@3

move.l (sp)+,d4 ; restore
unlk a6

move.l (sp)+,a0 ; rts Pascal style
add.l #4,a7
jmp (a0)
```

END

Constants

This appendix describes HyperTalk's built-in constants. A **constant** is a named value that never changes. It's different from a variable because you can't change it, and it's different from a literal because it does not require quotation marks.

The values of some constants are the string of characters making up the name, while others are different. In some cases, it's more convenient to use a constant (such as pi) in place of a long string (such as 3.14159265358979323846). In other cases, it's more convenient to use a constant (such as formFeed) because the only other way to enter that character is with the numToChar function, requiring that you know the ASCII number of the character (as in the numToChar of 12).

You can't give a variable a name that is the same as that of any built-in constant; if you try, HyperCard displays an error dialog box.

Table B-1 is a list of all the built-in constants in HyperTalk.

Table B-1 HyperTalk constants

Constant name	Description The ":" character is equivalent to ASCII 58.
comma	The "," character, ASCII 44, is used as the default item delimiter by HyperCard.
down	The value returned by the commandKey, mouse, optionKey, or shiftKey function when the named key (or button, in the case of mouse), is currently pressed. Its value is the same as the literal "down".
empty	The null string; the same as the literal "".
eof	The end-of-file condition; used with the read and write commands.

Constants

 Table B-1
 HyperTalk constants (continued)

Constant name	Description
false	The opposite of true; one of the states tested by the if control structure and one of the possible results of evaluation of a logical expression. Its value is the same as the literal "false".
formFeed	The form feed character (ASCII 12), which starts a new page in some file formats.
lineFeed	The line feed character (ASCII 10), which starts a new line in some file formats.
pi	The mathematical value pi to 20 decimal places, denoting the ratio of the circumference of a circle to its diameter, represented by the number 3.14159265358979323846.
quote	The double quotation mark character. It is needed to build a string containing quotation marks because they are stripped out of the string when literals are evaluated:
	<pre>put "george" into It quotation marks are not in It put quote & "george" & quote into It quotation marks are in It</pre>
return	The return character (ASCII 13), which delimits the lines of a string or container.
space	The space character (ASCII 32), the same as the literal " ".
tab	The horizontal tab character (ASCII 9).
true	The opposite of false; one of the states tested by the if control structure and one of the possible results of evaluation of a logical expression. Its value is the same as the literal "true".
up	The value returned by the commandKey, mouse, optionKey, or shiftKey function when the named key (or button, in the case of mouse) is not currently pressed. Its value is the same as the literal "up".
zeroten	The numbers 0 through 10.

This appendix provides scripting hints and other techniques for getting the most performance out of HyperCard applications.

One of the key methods for increasing the speed of HyperCard is avoiding disk accesses whenever possible. If you remember a few good scripting techniques, you can keep disk access at a minimum. To avoid excessive disk accesses, do the following:

- Change stacks as seldom as possible.
- Use variables instead of fields for all operations.
- Refer to a remote card rather than going there.

Other good scripting techniques that generally improve the performance of HyperCard are as follows:

- Migrate to XCMDs and XFCNs for highly repetitive tasks, such as sorting.
- Set lockScreen to true to avoid needless redrawing.
- Set lockMessages to true to save time during card-to-card data collection.
- Combine multiple messages.
- Take unnecessary code out of loops.
- Always use quoted literals.
- Use in-line statements rather than handler calls.
- Do complex calculations once.
- Watch overuse of variable references.
- Do visible work first.

Each of the techniques is described in the sections that follow.

Change Stacks as Seldom as Possible

Changing stacks means going to a disk, hard disk, or CD-ROM to retrieve information and, in the case of a floppy disk and hard disk, to store information. The disk accessing process takes more time than any other HyperCard operation.

When you need to read or write data from another stack, go the stack only once. Whenever possible, get or put everything you need at the same time.

Keep related information in the same stack. This includes data that you regularly sort, search, or move between. If you plan to use cards with substantially different appearances within the same application (a HyperCard application could consist of several stacks) and you need to cross boundaries frequently, use multiple backgrounds in the same stack rather than separate stacks.

However, there are exceptions to this rule. Because you might want to put the finished stack on a floppy disk for ease of backup and transportation, you need to keep an eye on the size of stacks as you build them. If you have too much related data to put on a single floppy, you have to use multiple stacks rather than one stack. Alternatively, you could put the final stack on a CD-ROM.

Another exception to the single stack rule is command operations. The HyperCard sort and find commands can operate on the entire stack, and you may not want the entire stack sorted or searched.

Use Variables, Not Fields, for Operations

Whenever possible, do operations such as sorting, data collection, and calculations in variables rather than fields. HyperCard operations are much faster in variables.

Fields are for the display of data and for long-term storage; HyperCard keeps field information stored on disk and draws that information onto the screen. Variables, in contrast, are in RAM and are for storage and manipulation of transient data—data that doesn't appear on the screen and is lost when you quit HyperCard. For example, collecting data on different cards into variables is approximately 50 percent faster than collecting the same data into a field.

Do calculations in variables to get faster results: for example, adding the contents of a series of fields from different cards. Everything that goes into fields, including numbers, is converted to a string, regardless of its original format. The numeric content of variables, in contrast, is stored in binary format, making calculation more precise and less time consuming.

Refer to a Remote Card Rather Than Going There

Referring to a remote card is generally faster than going there but is dependent on the number of fields referred to per card. For example, when collecting data from fewer than 10 fields, referring to a remote card in the current stack is faster than going to the card. However, when collecting data from 10 fields or more, it is faster to go to that card and then collect the data. For example, this script refers to a remote card containing data needed from the fields on that card. The script works in the current card of the current stack.

```
on collectGoodies
  repeat with FieldNum = 1 to 8
    put (line 2 in card field FieldNum of card 4) & return¬
    & (line 3 in card field FieldNum of card 4) & return after¬
    field 3 of this card
  end repeat
end collectGoodies
```

If the data is needed from more than 10 fields on a remote card, the script might look like this:

```
on collectGoodies
set lockMessages to true
push card
lock screen
go to card 4
repeat with FieldNum = 1 to the number of bkgnd fields
put (line 2 in card field FieldNum of card 4) & return &¬
(line 3 in card field FieldNum of card 4) & return¬
after var
end repeat
pop card
put var into field 3
unlock screen
set lockMessages to false
end collectGoodies
```

Migrate to XCMDs and XFCNs for Repetitive Tasks

No matter how efficient your HyperTalk code is, sorting 500 items is still going to take a long time. Repetitive time-intensive tasks are best handled with XCMDs and XFCNs. XCMDs and XFCNs have the same calling interface as any other HyperCard command, so are not any harder to use in a script.

If you do not have the programming experience in another high-level language to create an appropriate XCMD for your application, public domain and shareware XCMDs may exist that provide all of the required functions that your application needs. These XCMDs can be found through HyperCard user groups, user bulletin boards, and other information services.

Set LockScreen to True to Avoid Needless Redrawing

Redrawing the screen takes time, and it makes no sense to change the screen if all you are doing is going to another card to collect data. Set lockScreen to true (or use the lock command) while your scripts collect data by going from card to card and stack to stack.

See the second script example in the section "Refer to a Remote Card Rather Than Going There."

Set LockMessages to True During Card-to-Card Data Collection

The lock messages command prevents HyperCard from sending the six open and close system messages associated with cards, backgrounds, and stacks. See Chapter 8, "System Messages," for more information about HyperCard system messages.

Combine Multiple Messages

Message sending is relatively time consuming because each message traverses the entire message-passing path. The techniques described here avoid excessive message sending and can save lots of time.

Operators are interpreted directly and don't incur the cost of message sending. Using the operators is in, is not in, and contains is faster than using offset() because they are interpreted directly and are not sent as messages.

Calling a built-in function with the or of is faster than calling with "()" because "()" functions traverse the message path. Therefore, using date() is slower than using the date.

Use put to move values directly, rather than using get to store a value in It and then using put to move the value out of It. As an example,

```
get x
put It into y
is slower than
put x into y
```

Take Unnecessary Code Out of Loops

The reason for removing unnecessary code from loops is fairly obvious but frequently overlooked. Shorter handlers with fewer lines of code take less time to run than longer handlers. This fact is magnified in loops. For example, a loop that comprises 6 lines and runs six iterations is equivalent to 25 lines of code. Every extra line in that six-iteration loop counts as an additional 6 lines. Unwrap your code where possible and avoid unnecessary lines. For example, don't start a loop with the line set the cursor to watch, because you get that for free.

Use In-Line Statements Rather Than Handler Calls

It always takes time to get from one place to another and back again in any HyperCard application and script. To save time, put all of your code in-line. Create utility handlers where possible to avoid calling back to handlers in the main module. Putting a lot of your code in-line can, however, make your code hard to read. You should consider whether the increase in speed is worth having code that is hard to read. A good solution is to save most of the in-line code for repetitive time-consuming tasks that you haven't written XCMDs to handle.

Do Complex Calculations Once

When you've figured something out, put the results in a variable, then refer to the variable. This also includes parameter values. Retrieve parameter values once rather than many times (assuming you know the values haven't changed). This technique results in the greatest time savings within loops.

Watch Overuse of Variable References

The speed increases seen by avoiding overusing variable references are minimal, but it is good scripting technique. The line add x to y is slightly faster than put x + y into y, because the former has fewer variable references (two) than the latter (three).

Extended ASCII Table

This appendix lists the character assignments for the 256 single-byte character values used by the Macintosh.

There are 256 possible 8-bit binary values, from 00000000 to 11111111. Of these, the first 128 (from 00000000 to 01111111) have been assigned to a standard set of characters and commands used in data processing and communication. These assignments form the ASCII character set. (*ASCII* stands for *American Standard Code for Information Interchange*.)

The remaining 128 binary values, those for which the most significant bit (first digit) is 1 instead of 0, are not assigned in the ASCII standard. Because they have higher numerical values than the first 128 characters, they are often referred to as high-ASCII characters.

This appendix lists all character values by their decimal equivalent.

Table D-1 lists the first 32 characters, the control characters, which have no printable-character representation, with the standard abbreviation for each and its meaning.

Table D-1 Control character assignments

Value	Name	Meaning	Value	Name	Meaning
0	NUL	Null	8	BS	Backspace
1	SOH	Start of heading	9	HT	Horizontal tab
2	STX	Start of text	10	LF	Line feed
3	ETX	End of text	11	VT	Vertical tab
4	EOT	End of transmission	12	FF	Form feed
5	ENQ	Enquiry	13	CR	Carriage return
6	ACK	Acknowledge	14	SO	Shift out
7	BEL	Bell	15	SI	Shift in

APPENDIX D

Extended ASCII Table

 Table D-1
 Control character assignments (continued)

Value	Name	Meaning	Value	Name	Meaning
16	DLE	Data link escape	24	CAN	Cancel
17	DC1	Device control 1	25	EM	End of medium
18	DC2	Device control 2	26	SUB	Substitute
19	DC3	Device control 3	27	ESC	Escape
20	DC4	Device control 4	28	FS	File separator
21	NAK	Negative acknowledge	29	GS	Group separator
22	SYN	Synchronous idle	30	RS	Record separator
23	ETB	End of transmission block	31	US	Unit separator

Table D-2 lists the remaining 224 character values with the characters to which they are assigned in the Macintosh Courier font.

 Table D-2
 Character assignments in Macintosh Courier font

Value	Character	Value	Character	Value	Character	Value	Character
32	Space	43	+	54	6	65	A
33	!	44	,	55	7	66	В
34	"	45	-	56	8	67	С
35	#	46	•	57	9	68	D
36	\$	47	/	58	:	69	E
37	%	48	0	59	;	70	F
38	&	49	1	60	<	71	G
39	•	50	2	61	=	72	Н
40	(51	3	62	>	73	I
41)	52	4	63	?	74	J
42	*	53	5	64	@	75	K

APPENDIX D

Extended ASCII Table

 Table D-2
 Character assignments in Macintosh Courier font (continued)

Value	Character	Value	Character	Value	Character	Value	Character
76	L	101	e	126	~	151	ó
77	M	102	f	127	Del	152	ò
78	N	103	g	128	Ä	153	ô
79	O	104	h	129	Å	154	ö
80	P	105	i	130	Ç	155	õ
81	Q	106	j	131	É	156	ú
82	R	107	k	132	Ñ	157	ù
83	S	108	1	133	Ö	158	û
84	T	109	m	134	Ü	159	ü
85	U	110	n	135	á	160	†
86	V	111	O	136	à	161	0
87	W	112	p	137	â	162	¢
88	Χ	113	q	138	ä	163	£
89	Y	114	r	139	ã	164	§
90	Z	115	S	140	å	165	•
91	[116	t	141	Ç	166	${\mathbb P}$
92	\	117	u	142	é	167	ß
93]	118	v	143	è	168	$^{\mathbb{R}}$
94	^	119	W	144	ê	169	©
95	_	120	X	145	ë	170	TM
96	•	121	y	146	í	171	,
97	a	122	Z	147	ì	172	
98	b	123	{	148	î	173	≠
99	С	124	1	149	ï	174	Æ
100	d	125	}	150	ñ	175	Ø

Extended ASCII Table

 Table D-2
 Character assignments in Macintosh Courier font (continued)

Value	Character	Value	Character	Value	Character	Value	Character
176	∞	200	»	224	‡	248	=
177	±	201	•••	225	•	249	V
178	≤	202	**	226	,	250	•
179	≥	203	À	227	"	251	•
180	¥	204	Ã	228	%	252	3
181	μ	205	õ	229	Â	253	"
182	9	206	Œ	230	Ê	254	•
183	\sum	207	œ	231	Á	255	~
184	Π	208	_	232	Ë		
185	π	209	_	233	È		
186	ſ	210	w.	234	Í		
187	a	211	"	235	Î		
188	0	212	1	236	Ï		
189	Ω	213	,	237	Ì		
190	æ	214	÷	238	Ó		
191	Ø	215	\Diamond	239	ô		
192	خ	216	ÿ	240			
193	i	217	Ÿ	241	Ò		
194	٦	218	/	242	Ú		
195	$\sqrt{}$	219	¤	243	Û		
196	f	220	<	244	Ù		
197	≈	221	>	245	ı		
198	Δ	222	fi	246	^	**Stands f	
199	«	223	fl	247	~	nonbrea	aking space

Operator Precedence Table

Table E-1 shows the order of precedence of HyperTalk's operators. In a complex expression containing more than one operator, HyperTalk performs the operation indicated by operators with lower-numbered precedence before those with higher-numbered precedence. Operators of equal precedence are evaluated left-to-right, except for exponentiation, which goes right-to-left. If you use parentheses, HyperTalk evaluates the innermost parenthetical expression first.

Chapter 7 discusses expression evaluation.

 Table E-1
 Operator precedence

Order	Operators	Type of operator
1	()	Grouping
2	-	Minus sign for numbers
	not	Logical negation for Boolean values
	there is a	Comparison for HyperCard items
	there is an	Comparison for HyperCard items
	there is not a	Comparison for HyperCard items
	there is not an	Comparison for HyperCard items
3	^	Exponentiation for numbers
4	* / div mod	Multiplication and division for numbers
5	+ -	Addition and subtraction for numbers
6	& &&	Concatenation of text
7	> < <= >= ≤ ≥	Comparison for numbers or text
	is in	Comparison for text

APPENDIX E

Operator Precedence Table

 Table E-1
 Operator precedence (continued)

Order	Operators contains	Type of operator Comparison for text
	is within	Boolean test for point within rectangle
	is not within	Boolean test for point within rectangle
	is not in	Comparison for text
	is a	Comparison for types
	is an	Comparison for types
	is not a	Comparison for types
	is not an	Comparison for types
8	= is	Comparison for numbers or text
	is not <> ≠	Comparison for numbers or text
9	and	Logical for Boolean values
10	or	Logical for Boolean values

HyperCard Synonyms

Table F-1 lists the alternative ways that HyperTalk terms can be used.

Table F-1	HyperTalk synonyms
-----------	--------------------

Synonym	Term		
abbr	abbrev	abbreviated	
bg	bkgnd	background	
bgs	bkgnds	backgrounds	
botRight	bottomRight		
btn	button		
btns	buttons		
cd	card		
cds	cards		
char	character		
chars	characters		
fld	field		
flds	fields		
grey	gray		
hilite	highlight	highlite	hilight
in	of		
loc	location		
mid	middle		
msg	message	message box	

HyperCard Synonyms

 Table F-1
 HyperTalk synonyms (continued)

Synonym	Term	
msg watcher	message watche	er
part	button	field
poly	polygon	
prev	previous	
rect	rectangle	
reg	regular	
sec	secs	seconds
spray	spray can	
tick	ticks	

HyperCard Limits

This appendix lists various minimum and maximum sizes and numbers of elements defined in HyperCard.

The maximum limits shown in Table G-1 are theoretical. Some of them are lower in practice. For example, HyperCard currently brings an entire card into memory at once, so the maximum size of a card is limited by available memory. It's possible that a card with a lot of text and long scripts, created while running HyperCard on a Macintosh with 2 MB of RAM, could not be opened on a Macintosh with 1 MB. The current useful size of a card (or background) is therefore between 50 and 100 KB.

The term *part*, in this appendix and internally in HyperCard, refers to buttons or fields. The value represented by LongInt is 2,147,483,647; the value represented by Integer is 32,767.

Table G-1 HyperCard limits

Item	Limit	
Stack limits		
Stack size	512 MB	
Minimum stack size	4896 bytes	
Maximum total number of bitmaps, cards, and backgrounds per stack	16,777,216	
Maximum stack name size	31 characters	
Maximum stack script size	30,000 characters	
Background limits		
Background size (bytes)	LongInt*	
Minimum background size	64 bytes	
Maximum parts per background	Integer	

HyperCard Limits

 Table G-1
 HyperCard limits (continued)

Item	Limit
Background limits (continued)	
Maximum total part size per background (bytes)	LongInt
Maximum background name size	31 characters
Maximum background script size	30,000 characters
Card limits	
Card size (bytes)	LongInt*
Minimum card size	64 bytes
Maximum parts per card	Integer
Maximum total part size per card (bytes)	LongInt
Maximum total text size per card (bytes)	LongInt
Maximum card name size	31 characters
Maximum card script size	30,000 characters
Part (button or field) limits	
Part size (bytes)	Integer [†]
Minimum overhead per part	30 bytes
Maximum part name size	31 characters
Maximum part text size	30,000 characters
Maximum part script size	30,000 characters
HyperTalk limits	
Maximum nested repeat structures	30
Maximum active variables (all pending handlers)	512
Maximum size card name with go command	31 characters
Maximum variable name size	31 characters
Maximum number format size	31 characters

HyperCard Limits

Table G-1 HyperCard limits (continued)

Item	Limit
HyperTalk limits (continued)	
Maximum size of command with arguments	254 characters
Maximum handler name size	254 characters
Maximum script size	30,000 characters
Maximum variable value size	Limited by available memory

 $^{^{\}ast}~$ Limited by HyperCard stack size; less than 100 KB for practical use.

 $^{^{\}dagger}$ The sum of the other elements in the button or field must be less than the part size.

This appendix lists HyperTalk's built-in commands (Table H-1) and functions (Table H-2), showing the syntax of their parameters.

HyperTalk's built-in commands and functions are described in more detail in Chapters 10 and 11, respectively. A brief description for each is included in Appendix I.

Syntax Description Notation

The syntax descriptions use the following typographic conventions. Words or phrases in this type are HyperTalk language elements that you type to the computer literally, exactly as shown. Words in *italic* type are metasymbols (used to describe general elements), not specific names—you must substitute the actual instances. Brackets ([]) enclose optional elements that may be included if you need them. (Don't type the brackets.) In some cases, optional elements change what the message does; in other cases they are helper words that have no effect except to make the message more readable.

It doesn't matter whether you use uppercase or lowercase letters; names that are formed from two words are shown in lowercase letters with a capital in the middle (likeThis) merely to make them more readable. The HyperTalk prepositions of and in are interchangeable—the syntax descriptions use the one that sounds more natural.

The terms *factor* and *expression* are defined in Chapter 7. Briefly, a factor can be a constant, literal, function, property, number, or container, and an expression can be a factor or a complex expression built with factors and operators. Also, a factor can be an expression within parentheses.

HyperCard Syntax Summary

Table H-1 HyperTalk command syntax

```
add number to [chunk of] container
answer file [promptText] [of type fileType]
answer program [promptText] [of type processType]
answer question with reply
answer question with reply1 or reply2
answer question with reply1 or reply2 or reply3
arrowKey direction
ask file promptText [with [default] fileName]
ask password [clear] question [with defaultAnswer]
ask question [with defaultAnswer]
beep [number]
choose toolName tool
choose tool toolNumber
click at point [with key]
click at point with key, key2
click at point with key, key2, key3
close [docPathname [with|in]] appPathname
close file fileName
close printing
close window windowName
commandKeyDown char
controlkey keyNumber
convert [chunk of] container | literal [from format [and format]] to format-
  [and format]
create menu menuName
```

Table H-1 HyperTalk command syntax (continued)

```
create stack stackName [with background] [in a new window]
debug checkpoint
delete chunk [of container]
delete menu
delete menuItem of menu
delete partName
dial number
dial number with [modem [modemCommands]]
disable [card|background] button
disable menu
disable menuItem of menu
divide [chunk of] container by number
do expression [as scriptLanguage]
doMenu itemName [ ,menuName][without dialog] [with modifierKey [ ,modifierKey ] ]
drag from point1 to point2
drag from point1 to point2 with key
drag from point1 to point2 with key, key2
drag from point1 to point2 with key, key2, key3
edit script of object
enable button
enable menu
enable menuItem of menu
enterInField
enterKey
export paint to file fileName
```

HyperCard Syntax Summary

Table H-1 HyperTalk command syntax (continued)

```
find chars [international] text [in field] [of marked cards]
find [international] text [in field] [of marked cards]
find string [international] text [in field] [of marked cards]
find whole [international] text [in field] [of marked cards]
find word [international] text [in field] [of marked cards]
functionKey keyNumber
get expression
get [the] property [of object]
go back
go forth
go [to] background [of [stack] stackName] [in a new window]¬
  [without dialog]
go [to] card [of background] [of [stack] stackName]¬
  [in a new window] [without dialog]
go [to] ordinal
go [to] position
go [to] [stack] stackName [in a new window] [without dialog]
help
hide background picture
hide card picture
hide groups
hide menuBar
hide object
hide picture of background
hide picture of card
hide titlebar
```

HyperCard Syntax Summary

Table H-1 HyperTalk command syntax (continued)

```
hide window stackName
hide window windowName
import paint from file fileName
keyDown char
lock error dialogs
lock messages
lock recent
lock screen
mark all cards
mark card
mark cards by finding chars text [in field]
mark cards by finding string text [in field]
mark cards by finding text [in field]
mark cards by finding whole text [in field]
mark cards by finding word text [in field]
mark cards where expression
multiply [chunk of] container by number
open file fileName
open [fileName with] application
open printing [with dialog]
open report printing [with dialog]
open report printing [with template templateName]
palette paletteName[, point]
picture [fileName, fileType, windowStyle, visible, depth, floatingLayer]
play sound [tempo tempo] [notes]
```

HyperCard Syntax Summary

Table H-1 HyperTalk command syntax (continued)

```
play stop
pop card [preposition [chunk of] container]
print button
print card [from point1 to point2]
print expression
print field
print fileName with application
print marked cards
print number cards
push background [of stack stackName]
push card
push card [of stack stackName]
push stack
put expression [preposition [chunk of] container]
put itemName preposition [menuItem of] menu [with menuMsg message]
read from file fileName at start for numberOfChars
read from file fileName for numberOfChars
read from file fileName until char
read from file fileName until constant
reply expression [with keyword aeKeyword]
reply error expression
request appleEvent data|class|id|sender|return id|sender id
request appleEvent data with keyword aeKeyword
request expression from program
request expression of from program id programID
```

Table H-1 HyperTalk command syntax (continued)

```
request expression of from this program
reset menubar
reset paint
reset printing
returnInField
returnKey
save stack stackName as fileName
save [this] stack as [stack] fileName
select empty
select object
select [preposition] chunk of field
select [preposition] text of field
selectedButton(family)
the selectedButton of family
set [the] property [of element] to value
show all cards
show background picture
show card picture
show cards
show groups
show marked cards
show menuBar
show [number] cards
show object [at point]
show picture of background
```

Table H-1 HyperTalk command syntax (continued)

```
show picture of card
show titlebar
show window stackName
show window windowName [at point]
sort [lines|items of] container [sortDirection] ¬
[sortType] [by sortKey]
sort [[[marked] cards of] background][sortDirection] ¬
[sortType] [by sortKey]
sort [[marked] cards of [this]]stack [sortDirection] ¬
[sortType] [by sortKey]
start using stack stackName
stop using stack stackName
subtract number from [chunk of] container
tabKey
type text
type text with key
type text with key, key2
type text with key, key2, key3
unlock error dialogs
unlock messages
unlock recent
unlock screen [with effectName]
unmark all cards
unmark card
unmark cards by finding chars text in field
unmark cards by finding string text in field
```

Table H-1 HyperTalk command syntax (continued)

```
unmark cards by finding text in field
unmark cards by finding whole text in field
unmark cards by finding word text in field
unmark cards where expression
visual [effect] effectName [speed] [to image]
wait [for] time [seconds]
wait until condition
wait while condition
write text to file fileName
write text to file fileName at end
write text to file fileName at eof
write text to file fileName at start
```

Table H-2 HyperTalk function syntax

```
the abs of factor
abs(expression)
annuity(rate, periods)
the atan of factor
atan(expression)
average(list)
average function
the charToNum of factor
charToNum(expression)
the clickChunk
```

Table H-2 HyperTalk function syntax (continued)

```
clickChunk()
the clickH
clickH()
the clickLine
clickLine()
the clickLoc
clickLoc()
the clickText
clickText()
the clickV
clickV()
the commandKey
commandKey()
compound(rate, periods)
the cos of factor
cos(expression)
the [adjective] date
date()
the destination
destination()
the diskSpace
diskSpace()
the exp of factor
exp(expression)
the expl of factor
```

Table H-2 HyperTalk function syntax (continued)

```
exp1(expression)
the exp2 of factor
exp2(expression)
the foundChunk
foundChunk()
the foundField
foundField()
the foundLine
foundLine()
the foundText
foundText()
the heapSpace
the length of factor
length(expression)
the ln of factor
ln(expression)
the ln1 of factor
ln1(expression)
the log2 of factor
log2(expression)
\max(list)
the menus
menus()
min(list)
the mouse
```

Table H-2 HyperTalk function syntax (continued)

```
mouse()
the mouseClick
mouseClick()
the mouseH
mouseH()
the mouseLoc
mouseLoc()
the mouseV
mouseV()
[the] number of objects
[the] number of chunks in expression
[the] number of backgrounds [in this stack]
[the] number of cards in background
[the] number of cards [in this stack]
[the] number of marked cards
[the] number of menus
[the] number of menuItems of menu
[the] number of [card|background] parts
[the] number of windows
the numToChar of factor
numToChar(expression)
offset(string1, string2)
the optionKey
optionKey()
the param of factor
```

Table H-2 HyperTalk function syntax (continued)

```
param(expression)
the paramCount
paramCount()
the params
params()
the programs
programs()
the random of factor
random(expression)
the result
result()
the round of factor
round(expression)
the screenRect
screenRect()
the seconds
seconds()
the selectedButton of family
selectedButton (family)
the selectedChunk
selectedChunk()
the selectedField
selectedField()
the selectedLine [of button | field]
selectedLine([button|field])
```

Table H-2 HyperTalk function syntax (continued)

```
the selectedLoc
selectedLoc()
the selectedText [of button|field]
selectedText([button|field])
the shiftKey
shiftKey()
the sin of factor
sin(expression)
the sound
sound()
the sqrt of factor
sqrt(expression)
the stacks
stacks()
the stackSpace
stackSpace()
sum(list)
the systemVersion
systemVersion()
the tan of factor
tan(expression)
the target
the ticks
ticks()
the [adjective] time
```

Table H-2 HyperTalk function syntax (continued)

```
time()
the tool
tool()
the trunc of factor
trunc(expression)
the value of factor
value(expression)
the windows
windows()
```

HyperTalk Vocabulary

Table I-1 lists and defines, in alphabetical order, HyperTalk's native vocabulary—the names of its built-in commands and functions, its system messages, keywords, the names of objects and their properties, and various adjectives, constants, ordinals, and other terms.

This list is not exhaustive—there are other terms with specific meanings recognized by HyperCard in particular contexts, and they are described with the primary term to which they relate. For example, the names of the various visual effects are listed with the visual command in Chapter 10.

The parameter syntax of HyperTalk's built-in commands and functions is shown in Appendix H.

Table I-1	HyperTalk vocabulary

Term	Category	Meaning
abbr[ev[iated]]	Adjective	Modifies the value returned by the date function or the name or ID property.
abs	Function	Returns the absolute value of a number.
add	Command	Adds the value of an expression to a value in a container.
address	Property	Returns the path of the currently executing HyperCard program.
after	Preposition	Used with put command, directing HyperCard to append a new value following any preexisting value in a container.
all	Adjective	Specifies total number of cards in stack to show cards command.
annuity	Function	Computes present or future value of an ordinary annuity.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
answer	Command	Displays a dialog box with question and reply buttons.
answer file	Command	Presents the standard dialog box for locating a file; used for opening files of a specified type.
answer program	Command	Presents the standard dialog box for locating a progam to link to.
any	Ordinal	Special ordinal used with object or chunk to specify a random element within its enclosing set.
appleEvent	System message	Sent to the current card when an Apple event is received.
arrowKey	Command	Takes you to another card.
arrowKey	System message	Sent to current card when an arrow key is pressed.
ask	Command	Displays a dialog box with a question and default answer.
ask file	Command	Presents the standard dialog box for locating where to save a file; used for saving files.
ask password	Command	Displays a dialog box with a field for a password.
atan	Function	Returns trigonometric arc tangent of a number.
autoHilite	Property	Determines whether or not a button's hilite property is affected by the message mouseDown. Also determines whether or not a field behaves as a list.
autoTab	Property	Determines whether the specified nonscrolling field sends the tabKey message to the current card.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
average	Function	Returns the average value of numbers in a list.
background	Object	Generic name of background object; used with specific designation (go to next background). Also used to specify containing object for buttons and, optionally, fields (background button 2).
backgrounds	Object type	Specifies backgrounds as type of object to the number function.
beep	Command	Causes Macintosh to make a beep sound.
before	Preposition	Used with put command, directing HyperCard to place a new value at the beginning of any preexisting value in a container.
bg	Object	Abbreviation for background.
bkgnd	Object	Abbreviation for background.
bkgnds	Object type	Specifies backgrounds as type of object to the number function.
blindTyping	Property	Allows typing into Message box when hidden.
botRight	Property	Abbreviation for bottomRight.
bottom	Property	Determines or changes the value of item 4 of the rectangle property when applied to the specified object or window.
bottomRight	Property	Determines or changes items 3 and 4 of the value of the rectangle property when applied to the specified object or window.
browse	Tool	Name of tool from Tools palette; used with choose command or returned by the tool function.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
brush	Property	Determines the current brush shape.
brush	Tool	Name of tool from Tools palette; used with choose command or returned by the tool function.
btn	Object	Abbreviation for button.
bucket	Tool	Name of tool from Tools palette; used with choose command or returned by the tool function.
button	Object	Generic name of button object; used with a specific designation (hide button one).
button	Tool	Name of tool from Tools palette; used with choose command or returned by the tool function.
buttonCount	Property	Determines the number of buttons in an open palette XCMD displayed by the palette command.
buttons	Object type	Specifies buttons as type of object to the number function.
cantAbort	Property	Determines if a script can be stopped by pressing Command-period.
cantDelete	Property	Determines if a background, card, or stack can be deleted.
cantModify	Property	Determines if a stack can be modified. Can be used with a password to prevent anyone without the password from modifying a stack.
cantPeek	Property	Determines if the outline is shown around buttons and fields when the Command- Option or Command-Option-Shift keys are pressed.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
card	Object	Generic name of a card object; used with a specific designation (go to card "fred"). Also used to specify containing object for fields and, optionally, buttons (card field "date").
cards	Object type	Specifies cards as type of object to the number function or show command.
cd	Object	Abbreviation for card.
center	Adjective	Specifies center alignment of text in a field.
centered	Property	Determines whether shapes are drawn from the center or from the corner.
char[acter]	Chunk	A character of text in any container or expression.
char[acter]s	Chunk type	Specifies characters as type of chunk to the number function.
charToNum	Function	Returns ASCII value of a character.
checkMark	Property	Determines check character for a menu item.
choose	Command	Changes the current tool.
click	Command	Causes same actions as clicking at a specified location.
clickChunk	Function	Returns chunk information about text that is clicked.
clickH	Function	Returns horizontal position of last mouse click.
clickLine	Function	Returns line information about text that is clicked.
clickLoc	Function	Returns location of most recent click.
clickText	Function	Returns text information about word or group phrase that is clicked.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
close	Command	Closes an application, document opened by another application, or desk accessory.
clickV	Function	Returns vertical position of last mouse click.
close	System message	Sent to the current card when you close a stack window with the close window command or by clicking the close box.
closeBackground	System message	Sent to current card just before you leave the current background.
closeCard	System message	Sent to current card just before you leave it.
closeField	System message	Sent to unlocked field when it closes.
close file	Command	Closes a previously opened disk file.
closePalette	System message	Sent to the current card when a palette that was opened with the palette command is closed.
closePicture	System message	Sent to the current card when a window that was created with the picture command is closed.
close printing	Command	Ends a print job.
closeStack	System message	Sent to current card just before you leave the current stack.
close window	Command	Closes a stack or picture window.
commandChar	Property	Determines the character to use with the Command key to invoke a menu item.
commandKey	Function	Returns the state of the Command key: up or down.
commandKeyDown	Command	Causes a built-in HyperCard response, depending on key pressed with Command key.
commandKeyDown	System message	Sent to current card when a combination of the Command key and another key is pressed.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
commands	Property	Returns a list of the commands associated with the buttons in an open palette displayed by the palette command.
compound	Function	Computes present or future value of a compound interest–bearing account.
controlKey	Command	Sends the controlKey system message.
controlKey	System message	Sent to current card when a combination of the Control key and another key is pressed.
convert	Command	Converts a date or time to specified format.
create menu	Command	Creates a new menu with the specified name.
create stack	Command	Creates a new stack with the specified name and background.
cos	Function	Returns the cosine of the angle that is passed to it.
cursor	Property	Sets image appearing at pointer location on screen. You can only set cursor; you can't get it.
curve	Tool	Name of tool from Tools palette; used with choose command or returned by the tool function.
date	Function	Returns a string representing the current date.
debug checkpoint	Command	Sets a checkpoint in a script to invoke the built-in debugger.
debugger	Property	Determines the debugger to use.
delete (menu)	Command	Deletes a menu.
delete (menu items)	Command	Deletes a menu item.
delete (object)	Command	Deletes a button or field.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
delete (part)	Command	Deletes a button or field.
delete (text)	Command	Removes a chunk of text from a container.
deleteBackground	System message	Sent to current card just before the background is deleted.
deleteButton	System message	Sent to a button just before it is deleted.
deleteCard	System message	Sent to current card just before it is deleted.
deleteField	System message	Sent to a field just before it is deleted.
deleteStack	System message	Sent to the current card just before a stack is deleted.
destination	Function	Returns the name of a stack to which HyperCard is going.
dial	Command	Generates touch-tone sounds through audio output or modem attached to serial port.
dialingTime	Property	Determines how long HyperCard waits before closing the serial connection to a modem after dialing.
dialingVolume	Property	Determines the volume of the touch tones generated through the speaker by the dial command.
disable	Command	Disables the specified menu, menu item, or button.
diskSpace	Function	Displays the amount of free space available on the disk containing the current stack.
dithering	Property	Determines whether or not the picture opened by the picture command is dithered.
divide	Command	Divides the value in a container by the value of an expression.
do	Keyword	Sends the value of an expression as a message to the current card.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
doMenu	Command	Performs a specified menu command.
doMenu	System message	Sent to current card when any menu item is chosen.
dontSearch	Property	Determines whether a card, background, or field can be searched by the find command.
dontWrap	Property	Determines whether the text in a field wraps onto the next line.
down	Constant	Value returned by various functions to describe the state of a key or the mouse button.
drag	Command	Performs same action as a manual drag.
dragSpeed	Property	Sets pixels-per-second speed at which pointer moves with drag command.
editBkgnd	Property	Determines whether manipulation of buttons, fields, or paintings occurs on current card or background.
edit script	Command	Opens the script of a specified object.
eight	Constant	String representation of the numerical value 8.
eighth	Ordinal	Designates object or chunk number eight within its enclosing set.
else	Keyword	Optionally follows then clause in an if structure to introduce an alternative action clause.
empty	Constant	The null string; same as the literal "".
enable	Command	Enables the specified button, menu, or menu item.
enabled	Property	Determines whether the specified button, menu, or menu item is enabled.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
end	Keyword	Marks the end of a message handler, function handler, repeat loop, or multiple-statement then or else clause of an if structure.
enterInField	Command	Closes a field that is open for text editing.
enterInField	System message	Sent to the field when the Enter key is pressed while there is an insertion point or selection in the field.
enterKey	Command	Sends contents of Message box to the current card.
enterKey	System message	Sent to the current card when the Enter key is pressed unless the text insertion point is in a field.
environment	Property	Determines whether HyperCard Player or a fully enabled development version of HyperCard is running.
eraser	Tool	Name of tool from Tools palette; used with choose command or returned by the tool function.
exit	Keyword	Immediately ends execution of a message handler, function handler, or repeat loop.
exitField	System message	Sent to a field when the pointer leaves the field's rectangle.
exp	Function	Returns the mathematical exponential of its argument.
expl	Function	Returns one less than the mathematical exponential of its argument.
export paint	Command	Creates a Macintosh paint file with the image of the current card.
exp2	Function	Returns the value of 2 raised to the power specified by the argument.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
false	Constant	Boolean value resulting from evaluation of a comparative expression and returned from some functions.
family	Property	Groups a set of buttons to function in a coordinated manner.
field	Container	Generic name of field container; used with specific designation (put the time into card field "time").
field	Object	Generic name of field object; used with specific designation (get name of first field).
field	Tool	Name of tool from Tools palette; used with choose command or returned by the tool function.
fields	Object type	Specifies fields as type of object to the number function.
fifth	Ordinal	Designates object or chunk number five within its enclosing set.
filled	Property	Determines the Draw Filled setting.
find	Command	Searches card and background fields for text strings derived from an expression.
first	Ordinal	Designates object or chunk number one within its enclosing set.
five	Constant	String representation of the numerical value 5.
fixedLineHeight	Property	Determine whether or not a field has fixed line spacing.
formFeed	Constant	The form feed character (ASCII 12), which starts a new page in some file formats.
foundChunk	Function	Returns a chunk expression describing the text found with the find command.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
foundField	Function	Returns an expression describing the field the text was found in with the find command.
foundLine	Function	Returns an expression describing the line the text was found in with the find command.
foundText	Function	Returns the text found with the find command.
four	Constant	String representation of the numerical value 4.
fourth	Ordinal	Designates object or chunk number four within its enclosing set.
freeSize	Property	Determines the amount of free space available in a specified stack.
function	Keyword	Marks the beginning of a function handler. Connects the handler with a particular function call.
functionKey	Command	Performs Undo, Cut, Copy, or Paste operations with parameter values of 1, 2, 3, or 4, respectively.
functionKey	System message	Sent to current card when any function key on the Apple Extended Keyboard is pressed.
get	Command	Puts the value of an expression into the local variable It.
global	Keyword	Declares specified variables to be valid beyond current execution of current handler.
globalLoc	Property	Determines the location of a window created with the picture command in global coordinates.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
globalRect	Property	Determines the rectangle of a window created with the picture command in global coordinates.
go	Command	Takes you to a specified card or stack.
grid	Property	Determines the Grid setting.
hBarLoc	Property	Determines the location of the horizontal bar in the Variable Watcher window.
heapSpace	Function	Returns an integer representing the amount of heap space available to HyperCard.
help	Command	Takes you to the first card in the stack named HyperCard Help.
help	System message	Sent to the current card, just before leaving that card, when Help is chosen from the Gomenu (or Command-? is pressed).
height	Property	Determines or changes the vertical distance in pixels occupied by the rectangle of the specified button or field.
hide	Command	Hides the specified window from view.
hide groups	Command	Hides the gray underline displayed beneath text by the show groups command.
hideIdle	Property	Determines whether or not the "Hide idle" checkbox is checked in the Message Watcher window.
hide menubar	System message	Hides the HyperCard menu bar.
hideUnused	Property	Determines whether or not the "Hide unused messages" checkbox is checked in the Message Watcher window.
hilite	Property	Determines whether a specified button is highlighted.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
hilitedButton	Property	Determines whether a button is highlighted in a palette XCMD displayed by the palette command.
icon	Property	Determines the icon that is displayed with a specified button.
ID	Property	Determines the permanent ID number of a specified background, card, field, or button.
idle	System message	Sent to the current card repeatedly whenever nothing else is happening.
if	Keyword	Introduces a conditional structure containing statements to be executed only if a specified condition is true.
import paint	Command	Reads in a Macintosh paint file and makes it the current selection.
in	Operator	Used with the comparison operators is in and is not in.
in	Preposition	Used as a connective preposition in chunk expressions—for example, card 12 in this stack.
into	Preposition	Used with put command, directing HyperCard to replace any preexisting value in a container with a new value.
It	Container	Local variable that is the default destination for get, ask, answer, read, request, and convert commands.
item	Chunk	A piece of text delimited by commas in any container or expression.
itemDelimiter	Property	Determines the character that delimits items in a container.
items	Chunk type	Specifies items as type of chunk to the number function.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
keyDown	Command	Causes HyperCard to enter the character passed with the command at the insertion point.
keyDown	System message	Sent to the current card when a key is pressed.
language	Property	Used to choose language in which scripts are displayed.
lasso	Tool	Name of tool from Tools palette; used with choose command or returned by the tool function.
last	Ordinal	Special ordinal used with object or chunk to specify the element whose number is equal to the total number of elements in its enclosing set.
length	Function	Returns the number of characters in the text string derived from an expression.
left	Adjective	Specifies left-justified alignment of text in a field.
left	Property	Determines or changes the value of item 1 of the rectangle property when applied to the specified object or window.
line	Chunk	A piece of text delimited by return characters in any container.
line	Tool	Name of tool from Tools palette; used with choose command or returned by the tool function.
lineFeed	Constant	The line feed character (ASCII 10), which starts a new line in some file formats.
lines	Chunk type	Specifies lines as type of chunk to the number function.
lineSize	Property	Determines the thickness of lines drawn with line and shape tools.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
ln	Function	Returns the base- e (natural) logarithm of the number passed to it.
ln1	Function	Returns the base- e (natural) logarithm of the sum of the number passed to it plus 1.
loc	Property	Determines the location at which a picture window created with the picture command is displayed.
loc[ation]	Property	Determines the location at which a window, field, or button is displayed.
lock	Command	Prevents updating of the screen from card to card.
lockErrorDialogs	Property	Allows or prevents HyperCard from displaying error messages.
lockMessages	Property	Allows or prevents HyperCard from sending all automatic messages such as openCard.
lockRecent	Property	Allows or prevents HyperCard from adding miniature representations to the Recent card.
lockScreen	Property	Determines whether the screen is updated when moving from card to card.
lockText	Property	Determines whether text editing is allowed in a specified field.
log2	Function	Returns the base-2 logarithm of the number passed to it.
long	Adjective	Modifies value returned by date function and by name and ID properties.
longWindowTitles	Property	Determines whether the window title bar contains the full pathname of a stack or the short name.
mark	Command	Marks cards.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
markChar	Property	Determines the checkmark character used to indicate a menu item is chosen.
marked	Property	Determines whether or not a specified card is marked.
max	Function	Returns the highest-value number from a list of numbers.
me	Object	The object containing the executing handler.
menu	Function	Returns a list of the menu items in a specified menu.
menuMessage	Property	Determines the message to be sent by a specified menu item.
menus	Function	Returns a list of the menu names in the HyperCard menu bar.
message [box]	Container	The Message box.
messageWatcher	Property	Determines the message watcher to use.
mid[dle]	Ordinal	Special ordinal used with object or chunk to specify the element whose number is equal to one more than half the total number of elements in its enclosing set.
min	Function	Returns the lowest-value number from a list of numbers.
mouse	Function	Returns state of the mouse button: up or down.
mouseClick	Function	Returns whether the mouse button has been clicked.
mouseDoubleClick	System message	Sent to a button, locked field, or the current card when the mouse button is double-clicked.
mouseDown	System message	Sent to a button, locked field, or the current card when the mouse button is pressed down.
		continued

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
mouseDownInPicture	System message	Sent to the current card when the mouse button is down while the pointer is in a window created with the picture command.
mouseEnter	System message	Sent to a button or field when the pointer is first moved inside its rectangle.
mouseH	Function	Returns the horizontal offset in pixels of the pointer from the left edge of the card window.
mouseLeave	System message	Sent to a button or field when the pointer is first removed from its rectangle.
mouseLoc	Function	Returns the point on the screen where the pointer is currently located.
mouseStillDown	System message	Sent to a button, locked field, or the current card repeatedly when the mouse button is held down.
mouseUp	System message	Sent to a button, locked field, or the current card when the mouse button is released after having been previously pressed down within the same object's rectangle.
mouseUpInPicture	System message	Sent to the current card when the mouse button is released after being down while the pointer is in a window created with the picture command.
mouseV	Function	Returns the vertical offset in pixels of the pointer from the top of the screen.
mouseWithin	System message	Sent to a button or field repeatedly while the pointer remains inside its rectangle.
moveWindow	System message	Sent to a card when you change a card window's location property with HyperTalk, drag or zoom the card window, or change the location of the card window with the show command.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
msg [box]	Container	The Message box.
multiple	Property	Determines whether multiple images are drawn with a shape tool.
multipleLines	Property	Used to determine or change whether multiple-line selections are allowed in a field configured as a list field.
multiply	Command	Multiplies the value in a container by the value derived from an expression.
multiSpace	Property	Determines the space between objects drawn when the multiple property is true.
name	Property	Determines the name of a stack, background, card, field, button, menu, or menu item.
next	Keyword	Ends execution of current iteration of a repeat loop, beginning next iteration.
next	Object modifier	Used with card or background to refer to the one following the current one.
newBackground	System message	Sent to the current card as soon as a background has been created.
newButton	System message	Sent to a button as soon as it has been created.
newCard	System message	Sent to a card as soon as it has been created.
newField	System message	Sent to a field as soon as it has been created.
newStack	System message	Sent to the current card as soon as a stack has been created.
nine	Constant	String representation of the numerical value 9.
ninth	Ordinal	Designates object or chunk number nine within its enclosing set.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
number	Function	Returns the number of buttons or fields on the current card or background, the number of marked cards, the number of HyperCard menus, the number of menu items in a menu, the number of windows in HyperCard, or the number of a specified type of chunk within a value.
number	Property	Determines the number of a background, card, field, or button.
numberFormat	Property	Determines the precision with which results of mathematical operations are displayed.
numToChar	Function	Returns the character whose ASCII equivalent value is that of the integer passed to it.
offset	Function	Returns the number of characters from the beginning of the source string.
on	Keyword	Marks the beginning of a message handler and connects it with a particular message.
one	Constant	String representation of the numerical value 1.
open	Command	Launches the specified application.
openBackground	System message	Sent to a card when you go to it and its background is different from the one you were formerly on.
openCard	System message	Sent to a card when you go to it.
openField	System message	Sent to an unlocked field when you place the insertion point in it for text editing.
open file	Command	Opens the specified file for a read or write command operation.
openPalette	System message	Sent to the current card when a palette is opened with the palette command.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
openPicture	System message	Sent to the current card when a palette is opened with the picture command.
open printing	Command	Begins a print job.
open report printing	Command	Begins a print job for a specified report.
openStack	System message	Sent to a card when you go to it and it's in a stack different from the one containing the card you were formerly on.
optionKey	Function	Returns the state of the Option key: up or down.
oval	Tool	Name of tool from Tools palette; used with choose command or returned by the tool function.
owner	Property	For a card, determines its background; for a window, determines its creator.
palette	Command	Invokes the specified palette XCMD.
param	Function	Returns a parameter value from the parameter list passed to the currently executing handler.
paramCount	Function	Returns the number of parameters passed to the currently executing handler.
params	Function	Returns the entire parameter list passed to the currently executing handler.
partNumber	Property	Determines the position of a button or field among all the buttons <i>and</i> fields of its enclosing card or background.
pass	Keyword	Ends execution of a message handler or function handler and sends the invoking message or function call to the next object in the hierarchy.
pattern	Property	Determines the Paint pattern.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
pencil	Tool	Name of tool from Tools palette; used with choose command or returned by the tool function.
pi	Constant	The mathematical value pi to 20 decimal places, equal to the number 3.14159265358979323846.
picture	Command	Displays the specified picture file in an external window.
play	Command	Starts the HyperCard sound-playing feature.
poly[gon]	Tool	Name of tool from Tools palette; used with choose command or returned by the tool function.
polySides	Property	Determines the number of sides created by the Regular Polygon tool.
pop card	Command	Returns you to last card saved with the push card command.
powerKeys	Property	Provides keyboard shortcuts of commonly used painting actions.
prev[ious]	Object modifier	Used with card or background to refer to the one preceding the current one.
print	Command	Prints the specified file.
print card	Command	Prints the current card or a specified number of cards beginning with the current card.
printMargins	Property	Determines or sets the current page print margin.
printTextAlign	Property	Determines or sets the text alignment for fields when printing.
printTextFont	Property	Determines or sets the text font for fields when printing.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
printTextHeight	Property	Determines or sets the line height for fields when printing.
printTextSize	Property	Determines or sets the text size for fields when printing.
printTextStyle	Property	Determines or sets the text style for fields when printing.
programs	Function	Returns a list of the System 7–friendly programs running on your machine.
properties	Property	Returns a list of the names of the palette properties supported by a palette XCMD displayed by the palette command.
push	Command	Saves the identification of a specified card in a LIFO memory stack for later retrieval.
put	Command	Copies the value of an expression into a container.
quit	System message	Sent to the current card when you choose Quit HyperCard from the File menu (or press Command-Q), just before HyperCard goes away.
quote	Constant	The straight double quotation mark character.
random	Function	Returns a random integer between 1 and the integer derived from a specified expression.
read	Command	Reads a file previously opened with the open file command into the local variable It. See also write.
rect	Property	Determines the rectangle property for a variable watcher window and for windows created with the picture command.
rect[angle]	Property	Determines the rectangle occupied by a specified window, field, or button.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
rect[angle]	Tool	Name of tool from Tools palette; used with choose command or returned by the tool function.
reg[ular] poly[gon]	Tool	Name of tool from Tools palette; used with choose command or returned by the tool function.
repeat	Keyword	Introduces a repeat loop, an iterative structure containing a block of one or more statements executed multiple times.
reply	Command	Used to answer an incoming Apple event.
reportTemplates	Property	A read-only stack property that returns the names of the report templates for a stack.
request	Command	Sends an "evaluate expression" Apple event to another application.
reset menubar	Command	Reinstates the default values of all the HyperCard menus and removes any user-defined menus.
reset paint	Command	Reinstates the default values of all the painting properties.
reset printing	Command	Reinstates the default values of all the printing properties.
result	Function	Returns the status of commands previously executed in current handler.
resume	System message	Sent to the current card when HyperCard resumes running after having been suspended.
resumeStack	System message	Sent to the current card when HyperCard returns to a stack.
return	Keyword	Returns a value from a function handler or message handler.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning	
returnInField	Command	Enters a return character into a field that is open for text editing.	
returnInField	System message	Sent to a field when the Return key is pressed and there is an insertion point or selection in the field.	
returnKey	Command	Sends any statement in the Message box to the current card.	
returnKey	System message	Sent to current card when Return key is pressed.	
right	Adjective	Specifies right-justified alignment of text in a field.	
right	Property	Determines or changes the value of item 3 of the rectangle property when applied to the specified object or window.	
round	Function	Returns the number derived from an expression, rounded off to the nearest integer.	
round rect[angle]	Tool	Name of tool from Tools palette; used with choose command or returned by the tool function.	
save	Command	Saves a copy of the specified stack with a specified name.	
screenRect	Function	Returns the size of the screen HyperCard's menu bar is in.	
script	Property	Retrieves or replaces the script of the specified stack, background, card, field, or button.	
scriptEditor	Property	Determines the script editor to use.	
scriptingLanguage	Property	Used to set HyperCard objects to accept scripts written in the scripting language you choose.	

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning	
scriptTextFont	Property	Determines the font displayed in the script editor.	
scriptTextSize	Property	Determines the size of text displayed in the script editor.	
scroll (fields)	Property	Determines the amount of material that is hidden above the top of the specified scrolling field's rectangle.	
scroll (windows)	Property	Determines the position of the window over the card or picture.	
second	Ordinal	Designates object or chunk number two within its enclosing set.	
seconds	Function	Returns the number of seconds between midnight, January 1, 1904, and the current time.	
select	Command	Selects an object, a tool, a chunk of text, or a line in a list field or pop-up button.	
select	Tool	Name of tool from Tools palette; used with choose command or returned by the tool function.	
selectedButton	Function	Returns the descriptor of the currently highlighted button.	
selectedChunk	Function	Returns a chunk expression describing the selected text in a field.	
selectedField	Function	Returns an expression describing the field the selected text is in.	
selectedLine	Function	Returns an expression describing the line in a field where the selected text is.	
selectedLoc	Function	Returns the point at which the selected text begins.	
selectedText	Function	Returns the selected text in a field.	

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning	
selection	Container	Currently selected area of text in a field.	
send	Keyword	Sends a specified message directly to a specified object; sends a do script Appl event to another application.	
set	Command	Changes the state of a specified global, painting, window, or object property.	
seven	Constant	String representation of the numerical value 7.	
seventh	Ordinal	Designates object or chunk number seven within its enclosing set.	
sharedHilite	Property	Determines or sets whether a background button shares the same highlight state on each card.	
sharedText	Property	Determines or sets whether a background field shares the same text on each card. If set to true, it also sets the dontSearch property of the field to true.	
shiftKey	Function	Returns the state of the Shift key: up or down.	
short	Adjective	Modifies value returned by date function and by name and ID properties.	
show	Command	Displays a specified window or object.	
show cards	Command	Displays a specified number of cards in the current stack.	
showLines	Property	Determines whether or not the text baselines are visible in a field.	
show menubar	System message	Displays the menu bar if it was hidden.	
showName	Property	Determines whether or not the name of a specified button is displayed in its rectangle on the screen.	

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Category	Meaning	
Property	Determines whether or not a specified card or background picture is displayed.	
Command	Shows the title bar of the current card window if it was hidden.	
Function	Returns the sine of the angle that is passed to it.	
Constant	String representation of the numerical value 6.	
Ordinal	Designates object or chunk number six within its enclosing set.	
Property	Returns the size of a specified stack.	
System message	Sent to the current card when the card window is resized.	
Command	Puts all of the cards in a specified stack in specified order.	
Function	Returns the name of the sound that is currently playing.	
Constant	The space character (ASCII 32); same as the literal " ".	
Tool	Name of tool from Tools palette; used with choose command or returned by the tool function.	
Function	Returns the square root of a number.	
Object	Generic name of stack object; used with specific name (go to stack "help").	
Function	Returns a list of the currently open stacks.	
Property	Determines the current list of stacks in the message-passing hierarchy.	
Function	Returns the amount of space remaining on the Macintosh Operating System stack.	
	Property Command Function Constant Ordinal Property System message Command Function Constant Tool Function Object Function Property	

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning	
startUp	System message	Sent to the current card (first card of the Home stack) when HyperCard first begins running.	
start using	Command	Specifies a stack to add to the message- passing hierarchy.	
stop using	Command	Specifies a stack to remove from the message-passing hierarchy.	
style	Property	Determines the style of a specified field or button.	
subtract	Command	Subtracts the value of an expression from the value in a container.	
sum	Function	Returns the sum of a list of numbers.	
suspend	System message	Sent to the current card when HyperCard suspended by launching another application with the open command.	
suspendStack	System message	Sent to the current card when you leave a open stack to go to another.	
systemVersion	Function	Returns a decimal string representing the running version of system software.	
tab	Constant	The horizontal tab character (ASCII 9).	
tabKey	Command	Places the insertion point in the next unlocked field on the current background or card.	
tabKey	System message	Sent to the current card or a field when Takey is pressed.	
tan	Function	Returns the tangent of an angle.	
target	Function	Indicates the object that initially received the message that initiated execution of the current handler.	
ten	Constant	String representation of the numerical value 10.	

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning	
tenth	Ordinal	Designates object or chunk number ten within its enclosing set.	
text	Tool	Name of tool from Tools palette; used with choose command or returned by the too function.	
textAlign	Property	Determines the alignment of characters created with the Paint Text tool, or those in a field, or those in the name of a button.	
textArrows	Property	Determines the functions of the arrow keys.	
textFont	Property	Determines the font of characters created with the Paint Text tool, or those in a field, or those in the name of a button.	
textHeight	Property	Determines the space between the baseline and characters created with the Paint Text tool or those in a field.	
textSize	Property	Determines the size of Paint text, or text in a field, or text in the name of a button.	
textStyle	Property	Determines the style of Paint text, text in a field, text in the name of a button, or text of a menu item.	
the	Special	Precedes a function name to indicate a function call to one of the built-in functions of HyperCard. You can't call a user-defined function with the. Also allowed, but not required, preceding special container names (the Message box) and properties.	
then	Keyword	Follows the conditional expression in an if structure to introduce the action clause.	
third	Ordinal	Designates object or chunk number three within its enclosing set.	
this	Modifier	Used with card, background, or stack to refer to the current one.	

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning	
three	Constant	String representation of the numerical value 3.	
ticks	Function	Determines the number of ticks since the Macintosh was turned on or restarted.	
time	Function	Returns the current time as a text string.	
titleWidth	Property	Determines or changes the width of the area in a pop-up button which displays its name.	
to	Preposition	Used to specify ranges (3 to 5), connect a message to its destination when used with send, specify a format for the convert command, assign a container for the add command, and connect values to object properties.	
tool	Function	Returns the name of the currently chosen tool.	
top	Property	Determines or changes the value of item 2 of the rectangle property when applied to the specified object or window.	
topLeft	Property	Determines or changes items 1 and 2 of the value of the rectangle property when applied to the specified object or window.	
traceDelay	Property	Determines or changes the delay between the execution of lines of HyperTalk during a debugger trace.	
true	Constant	Boolean value resulting from evaluation of a comparative expression and returned from some functions.	
trunc	Function	Determines the integer part of a number.	
two	Constant	String representation of the numerical value 2.	

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
type	Command	Inserts the specified text at the insertion point.
unlock	Command	Allows updating of the screen.
unmark	Command	Unmarks the specified marked card.
up	Constant	Value returned by various functions to describe the state of a key or the mouse button.
userLevel	Property	Determines the user level from 1 to 5.
userModify	Property	Determines or changes whether or not the user can type into fields or use Paint tools on a stack that has been write-protected.
value	Function	Evaluates an expression.
variableWatcher	Property	Determines the variable watcher to use.
vBarLoc	Property	Determines the location of the vertical bar in the Variable Watcher window.
version	Property	Returns the version number of the currently running HyperCard application.
visible	Property	Determines whether or not a window, field, or button appears on the screen.
visual	Command	Sets up a specified visual transition to the next card opened.
wait	Command	Causes HyperCard to pause before executing the rest of the current handler.
wideMargins	Property	Determines whether or not additional space is displayed in the margins of a specified field.
width	Property	Determines or changes the horizontal distance in pixels occupied by the rectangle of the specified button or field.

HyperTalk Vocabulary

 Table I-1
 HyperTalk vocabulary (continued)

Term	Category	Meaning
windows	Function	Returns a list of the windows currently available to HyperCard.
within	Operator	Tests whether or not a point lies inside a specified rectangle.
word	Chunk	Piece of text delimited by spaces in any container or expression.
words	Chunk type	Specifies words as type of chunk to the number function.
write	Command	Copies specified text into a specified disk file starting at a specified point.
zero	Constant	String representation of the numerical value 0 .
zoom	Property	Zooms a window created with the picture command in or out.

Glossary

actual parameters See parameters.

'aete' resource Apple event terminology extension resource. This resource includes the "grammar" for a scriptable application, including the events that the application can respond to and the classes of objects that it supports, with their relevant properties and their default data types. The 'aete' resource allows scripting components to map scripts written in human terms to the corresponding Apple events understood by the application.

algorithm A step-by-step procedure for solving a problem or accomplishing a task. Writing HyperTalk handlers or programs in other languages often begins with figuring out a suitable algorithm for a task.

Apple event A high-level event that adheres to the Apple Event Interprocess Messaging Protocol. An Apple event consists of attributes (including the event class and event ID, which identify the event and its task) and, usually, parameters (which contain data used by the target application of the event). See also Apple event attribute, Apple event parameter.

Apple event attribute A keyword-specified descriptor record that identifies the event class, event ID, target application, or some other characteristic of an Apple event. Taken together, the attributes of an Apple event identify the event and denote the task to be performed on the data

specified in the Apple event's parameters. Compared to parameters (which contain data used only by the target application of the Apple event), attributes contain information that can be used by both the Apple Event Manager and the target application. See also **Apple event parameter**.

Apple Event Interprocess Messaging Protocol (AEIMP) A standard defined by Apple Computer, Inc., for communication and data sharing among applications. High-level events that adhere to this protocol are called Apple events.

Apple event parameter A keyword-specified descriptor record that contains data that the target application of an Apple event must use. Compared to attributes (which contain information that can be used by both the Apple Event Manager and the target application), parameters contain data used only by the target application of the Apple event. See also Apple event attribute, direct parameter, optional parameter, required parameter.

AppleScript Component A scripting system integrated at the system level that utilizes the Component Manager. This technology, through the use of its scripting language, AppleScript, enables users to create scripts to control applications and the system.

background A type of HyperCard object; a template shared by a number of cards. Each card with the same background has the same background picture, background fields, and background buttons in its background layer. Like other HyperCard objects, every background has a script. You can place handlers in a background script that you want to be accessible to all the cards with that background.

background button A button that is common to all cards sharing a background. Compare with **card button**.

background field A field that is common to all cards sharing a background; its size, position, and default text format remain constant on all cards associated with that background, but its text can change from card to card. Compare with card field.

background picture The graphics in the background layer; the entire picture that is common to all cards sharing a background. You see the background picture by choosing Background from the Edit menu. Compare with card picture.

Browse tool The tool you use to click buttons and to set the insertion point in fields.

button A type of HyperCard object; a rectangular "hot spot" on a card or background that responds when you click it according to the instructions in its script. For example, clicking a right arrow button with the Browse tool can take you to the next card. See also background button, card button.

Button tool The tool you use to create, change, and select buttons.

card A type of HyperCard object; a rectangular area that can hold buttons, fields, and graphics. All cards in a stack are the same size. Each layer can contain its own buttons, fields, and graphics.

card button A button that belongs to a card; it appears on, and its actions apply to, a single card. Compare with background button.

card field A field that belongs to a card; its size, position, text attributes, and contents are limited to the card on which the field is created. Compare with **background field**.

card picture A picture that belongs to and applies only to a specific card. Compare with **background picture**.

chunk A piece of a character string represented as a chunk expression. Chunks can be specified as any combination of characters, words, items, or lines in a container or other source of value.

chunk expression A HyperTalk description of a unique chunk of the contents of any container or other source of value.

coercion handler A routine that coerces data from one Apple event descriptor type to another.

command A response to a particular message; a command is a built-in message handler residing in HyperCard. See also **external command.**

Command key The key at the lower-left side of the keyboard that has a propeller-shaped symbol. This key also has an Apple symbol and is sometimes called the *Apple key*.

comments Descriptive lines of text in a script or program that are intended not as instructions for the computer but as explanations for people to read. Comments are set off from instructions by symbols called delimiters, which vary from language to language. In HyperTalk, two hyphens (--) indicate the beginning of a comment.

Component Manager The Component Manager provides a database service that classifies software objects by function. In much the same way that the Resource Manager allows applications that are running to access data objects dynamically, the Component Manager provides services that allow run-time location of and access to functional objects.

constant A named value that never changes. For example, the constant empty stands for the null string, a value that can also be represented by the literal expression " ". Compare with **variable**.

container A place where you can store a value (text or a number). Examples are fields, the Message box, the selection, and variables.

control structure A block of HyperTalk statements defined with keywords that enable a script to control the order or conditions under which specific statements execute.

Core suite The suite of core Apple event constructs that are common to all or nearly all applications. These definitions form the basic vocabulary for interapplication communication. Using only the constructs defined in the Core suite, applications can perform a wide range of useful tasks. This suite includes such events as Get Data, Set Data, and Count Elements. The Core suite of Apple events is described in the *Apple Event Registry*. Apple Computer, Inc., recommends that all applications support the core Apple events.

current (adj.) Applies to the card, background, or stack you're using now. For example, the current card is the one you can see on your screen.

debug To locate and correct an error or the cause of a problem or malfunction in a computer program, such as a HyperTalk script.

delimiter A character or characters used to mark the beginning or end of a sequence of characters; that is, to define limits. For example, in HyperTalk double quotation marks act as delimiters for literals, and comments are set off with two hyphens at the beginning of the comment and a return character at the end.

descriptor The combination of an object's generic name, immediately followed by its particular name, number, or ID number.

direct parameter The parameter in an Apple event that contains the data to be used by the server application. For example, a list of documents to be opened is

specified in the direct parameter of the Open Documents event. See also **Apple** event parameter.

dynamic path A series of extra objects inserted into the path through which a message passes when its static path does not include the current card. The dynamic path comprises the current card, current background, and current stack. Compare **static path.**

event handler Any part of an application that deals with any event. Sometimes the term *event handler* is used to refer to any object that is eligible to handle menu commands.

expression A description of how to get a value; a source of value or complex expression built from sources of value and operators.

external command (XCMD) A command written in a computer language other than HyperTalk but made available to HyperCard to extend its built-in command set. External commands can be attached to a specific stack or to HyperCard itself. See also external function.

external function (XFCN) A function written in a computer language other than HyperTalk but made available to HyperCard to extend its built-in function set. External functions can be attached to a specific stack or to HyperCard itself. See also external command.

factor A single element of value in an expression. See also **value**. Factoring is the separation of the interface links to the application and the core functionality. By

factoring an application, all features are accessed through event handlers via **Apple events.**

field A type of HyperCard object; a container in which you type field text (as opposed to Paint text). HyperCard has two kinds of fields—card fields and background fields.

Field tool The tool you use to create, change, and select fields.

formal parameters See parameter variables.

function A named value that HyperCard calculates each time it is used. The way in which the value is calculated is defined internally for HyperTalk's built-in functions, and you can define your own functions with function handlers.

function call The use of a function name in a HyperTalk statement or in the Message box, invoking either a function handler or a built-in function.

function handler A handler that executes in response to a function call matching its name.

generic scripting component A special scripting component that establishes connections dynamically with the appropriate scripting component for each script that a client application attempts to manipulate or execute.

global properties The properties that determine aspects of the overall HyperCard environment. For example, userLevel is a global property that determines the current user level setting.

global variable A variable that is valid for all handlers in which it is declared. You declare a global variable by preceding its name with the keyword global. Compare with **local variable.**

handler A block of HyperTalk statements in the script of an object that executes in response to a message or a function call. The first line in a handler must begin with the word on, and the last line must end with the word end. Both on and end must be followed by the name of the message or function. HyperTalk has message handlers and function handlers.

hierarchy See message-passing hierarchy.

HyperTalk HyperCard's built-in script language for HyperCard users.

identifier A character string of any length, beginning with an alphabetic character; it can contain any alphanumeric character and the underscore character. Identifiers are used for variable and handler names.

keyboard equivalent key A key you press together with the Command key to issue a menu command.

keyword Any one of the 14 words that have a predefined meaning in HyperTalk. Examples of keywords are on, if, do, and repeat.

layer The order of a button or field relative to other buttons or fields on the same card or background. The object created most recently is ordinarily the topmost object (that is, on the front layer).

literal A string of characters intended to be taken literally. In HyperTalk, you use quotation marks (" ") as delimiters to set off a string of characters as a literal, such as the name of an object or a group of words you want to be treated as a text string.

local variable A variable that is valid only within the handler in which it is used (local variables need not be declared). Contrast with **global variable**.

loop A section of a handler that is repeated until a limit or condition is met, such as in a repeat structure.

message A string of characters sent to an object from a script or the Message box, or that HyperCard sends in response to an event. Messages that come from the system—from events such as mouse clicks, keyboard actions, or menu commands—are called system messages. Examples of HyperTalk messages are mouseUp, go, and push card. See also handler.

Message box A container that you use to send messages to objects or to evaluate expressions.

message handler A handler that executes in response to a message matching its name.

message-passing hierarchy The ordering of HyperCard objects that determines the path through which messages pass.

metasymbol A word used in a syntax statement as a placeholder for an element that is different for each specific use of the statement. For example, the metasymbol *filename* is used to show where you put the name of a file you want a command to act on. In this book, metasymbols are shown as italics.

number A character string consisting of any combination of the numerals 0 through 9, optionally including one period (.) representing a decimal value. A number can be preceded by a hyphen or a minus sign to represent a negative value.

object An element of the HyperCard environment that has a script associated with it and that can send and receive messages. There are five kinds of HyperCard objects: buttons, fields, cards, backgrounds, and stacks.

object class An application defines specific objects as distinct classes. In HyperCard, each of its objects (stack, background, card, button, and field) can be an individual class.

object descriptor Designation used to refer to an object. An object descriptor is formed by combining the name of the type of object with a specific name, number, or ID number. For example, background button 3 is an object descriptor. Stacks do not have a number or ID number, so only the name can be used for a stack descriptor.

object properties The properties that determine how HyperCard objects look and act. For example, the location property of a button determines where it appears on the screen.

object specifier A specific data type that contains references to specific classes (objects) and their relating specifiers (such as names, indexes, or IDs). For HyperCard, the metaphor that chunk expressions describe is an example of an object specifier.

online help Assistance you can get from an application program while it's running. In HyperCard, online help refers to the HyperCard disk-based Help system.

Open Scripting Architecture (OSA) A standard proposed by Apple Computer, Inc., to provide a uniform way for applications to provide or utilize scripting functionality.

operator A character or group of characters that causes a particular calculation or comparison to occur. In HyperTalk, operators operate on values. For example, the plus sign (+) is an arithmetic operator that adds numerical values.

optional parameter A supplemental parameter in an Apple event used to specify data that the server application should use in addition to the data specified in the **direct parameter.** Optional parameters are listed in the attribute identified by the keyOptionalKeywordAttr keyword. Applications use this attribute to specify or determine whether data exists in the form of optional parameters. Optional parameters need not be included in an Apple event; default values for optional parameters are part of the event definition. It is the responsibility of the server application that handles the event to supply values if optional parameters are omitted. See also **Apple event attribute**, **Apple** event parameter.

painting properties The properties that control aspects of the HyperCard painting environment, which is invoked when

you choose a Paint tool. For example, the brush property determines the shape of the Brush tool.

Paint text Text you type using the Paint Text tool. Paint text can appear anywhere, while regular text must appear in a field created with the Field tool. Paint text is part of a card or background picture.

Paint tool Any HyperCard tool you use to make pictures. Paint tools include Lasso, Brush, Spray, Eraser, and many others.

palette A small window that displays icons or patterns you can select by clicking. You can see two of HyperCard's palettes, the Tools palette and the Patterns palette, simply by "tearing off" their respective menus. To see the Navigator palette, type palette "navigator" in the Message box. See also tear-off menu.

parameters Values passed to a handler by a message or function call. Any expressions after the first word in a message are evaluated to yield the parameters; the parameters to a function call are enclosed in parentheses, or, if there is only one, it can follow of.

parameter variables Local variables in a handler that receive the values of parameters passed with the message or function call initiating the handler's execution.

picture Any graphic or part of a graphic, created with a Paint tool or imported from an external file, that is part of a card or background.

pixel Short for "picture element"; the smallest dot you can draw on the screen. The position of the pointer is often represented by two numbers separated by commas. These numbers are horizontal and vertical distances of the pointer from the left and top edges of the card window, measured in pixels. The upper-left corner of the screen has the coordinates 0, 0.

point (1) A location on the screen described by two integers, separated by a comma, representing horizontal and vertical offsets, measured in pixels from the top-left corner of the card window or (in the case of the card window itself) of the screen. (2) In printing, the unit of measurement of the height of a text character; one point is about ½2 of an inch. When you select a font, you can also select a point size, such as 10 point, 12 point, and so on.

power key One of a number of keys on the Macintosh keyboard you can press to initiate a menu action when a Paint tool is active. Power keys are enabled when you choose Power Keys from the Options menu or you check Power Keys on the Preferences card in the Home stack.

properties The defining characteristics of any HyperCard object and of HyperCard's environment. For example, setting the user level to Scripting changes the userLevel property of HyperCard to the value 5. Properties are often selected as options in dialog boxes or on palettes, or they can be set from handlers.

Recent A special dialog box that holds pictorial representations of the last 42 unique cards viewed. Choose Recent from

the Go menu to get the dialog box. Also, an adjective describing the card you were on immediately prior to the current card, as in recent card.

recursion The repetition of an operation or group of operations. Recursion occurs when a handler calls itself.

regular text Text you type in a field. You use the Browse tool to set an insertion point in a field and then type. Regular text is editable and searchable, while Paint text is not.

required parameter A keyword-specified descriptor record in an Apple event that must be specified. For example, a list of documents to open is a required parameter for the Open Documents event. Direct parameters are often required, and other additional parameters may be required. Optional parameters are never required.

Required suite The smallest of the standard Apple event suites, it includes definitions of four Apple events and four descriptor types. The Apple events defined in this suite, known as required Apple events, are sent to all applications that support high-level events and all applications that call the new Standard File routines under system software version 7.0 and later. All applications that support system software version 7.0 and later should support the Required suite. The events in this suite are the Open Application, Open Document, Print Document, and Quit Application events.

resource fork The part of a file that contains resources such as fonts, icons, and sounds, and so on.

script A collection of handlers written in HyperTalk and associated with a particular object. You use the script editor to add to and revise an object's script. Every object has a script, even though some scripts are empty: that is, they contain nothing.

scriptable The capability of an application to respond to Apple events sent to it by a scripting component. To qualify as scriptable, an application is required to respond to appropriate standard Apple events and include an 'aete' resource.

script editor A window in which you can type and edit a script. The title bar of the script editor describes the object to which the script belongs. You can use the Edit menu, the Script menu, and keyboard commands to edit text in the script editor. See also handler, object, and script.

scripting component A program that responds appropriately to calls made to the standard scripting component routines. Most scripting components implement scripting languages—for example, the AppleScript component implements the AppleScript scripting language.

search path When you open a file from within HyperCard, HyperCard attempts to locate the stack, document, or application you want by searching the folders listed on the appropriate Search Paths card in the Home stack. Each line on a Search Paths card indicates the location of a folder, including the disk name (and folder and subfolder names, if any). This information is called a *search path*. Items in a search path are separated by a colon, like this: my disk: HyperCard folder: my stacks:

Search Path cards Three cards in the Home stack used to store information about the location of stacks, documents, and applications that you open while HyperCard is running. See also **search path**.

selection A container that holds the currently selected area of text. Note that text found by the find command is not selected.

shared text Field text that appears on every card in a background. Shared text can be edited only from the background layer. Text in shared fields cannot be searched.

source of value HyperTalk's most basic expressions; the language elements from which values can be derived: constants, containers, functions, literals, and properties.

stack A type of HyperCard object that consists of a collection of cards; a HyperCard document.

statement A line of HyperTalk code inside a handler. A handler can contain many statements. Statements within handlers are first sent as messages to the object containing the handler and then to succeeding objects in the message-passing hierarchy.

static path The message-passing route defined by an object's own hierarchy. For example, the static path followed by a message sent to (but not handled by) a button would include the card to which the button belongs, the background associated with that card, and the stack containing them. Compare dynamic path.

string A sequence of characters. You can compare and combine strings in different ways by using operators. In HyperTalk, for example, 23 + 23 will result in 46; but 23 & 23 will result in 2323.

suite A group of Apple event constructs that define an area of functionality. Suites provide the common vocabulary for applications. A suite can define constructs such as Apple events, Apple event object classes, descriptor types, key forms, comparison operators, or constants.

syntax A description of the way in which language elements fit together to form meaningful phrases. A syntax statement for a command shows the command in its most generalized form, including placeholders (sometimes called metasymbols) for elements you must fill in as well as optional elements.

System file Software a Macintosh computer uses to perform its basic operations.

system message A message sent by HyperCard to an object in response to an event such as a mouse click, keyboard action, or menu command. Examples of HyperCard system messages are mouseUp, doMenu, and newCard.

target The object that first receives a message.

tear-off menu A menu that you can convert to a palette by dragging the pointer beyond the menu's edge. HyperCard has two tear-off menus—Tools and Patterns. When torn off, these menus are referred to as **palettes**.

text field See field.

text property A quality or attribute of a character's appearance. Text properties include style, font, and size.

tick Approximately one-sixtieth (1/60) of a second. The wait command assumes a value in ticks unless you specify seconds by adding secs or seconds.

tool An implement you use to do work. HyperCard has tools for browsing through cards and stacks, creating text fields, editing text, making buttons, and creating and editing pictures.

user level A property of HyperCard, ranging from 1 to 5, that determines which of HyperCard's capabilities are available. You can select the user level on the Preferences card in the Home stack. Each user level makes all the options from the lower levels available, and also gives you additional capabilities. The five user levels are Browsing, Typing, Painting, Authoring, and Scripting.

value A piece of information on which HyperCard operates. All HyperCard values can be treated as strings of characters—they are not formally separated into types. For example, a numeral could be interpreted as a number or as text, depending on what you do with it in a HyperTalk handler.

variable A named container that can hold a value consisting of a character string of any length. You can create a variable to hold some value (either numbers or text) simply by using its name with the put command and putting the value into it. HyperCard has local variables and global variables. Compare with constant.

window properties The properties that determine how the Message box and the Tools and Patterns palettes are displayed. For example, the visible property determines whether or not the specified window is displayed on the screen.

Index

306-307, 307 && (ampersand, double) operator 113 & (ampersand) operator 113 & operator 118 () (parentheses) operator 114 () parentheses operator 114 * (asterisk) operator 114 (chunk) 120 -- (double hyphen) comment character 26, 112 - (minus sign) operator 114 (not equal sign) operator 115 / (slash) operator 113 + (plus sign) operator 115 < (less than sign) operator 114 <= (less than or equal to sign) operator 114 = (equal sign) operator 113 > (greater than sign) 113 >= (greater than or equal to sign) operator 114 ^ (caret) operator 113 ≠ (not equal sign) operator 114 \leq (less than or equal to sign) operator 114 \geq , >= (greater than or equal to sign) operator 114

Α

Symbols

abbr date format 191 abbrev date format 191 abbreviated (adjective) 84 abbreviated date format 191 abbreviated time format 191 abbrev time format 191 abbr time format 191 abs function 291 accessing XCMDs and XFCNs 504

char 120 actual parameters 78 add command 167-168 address property 17,378 after (prepositon) 251 all (preposition) 271 ambiguous stack descriptors 91 ampersand, double operator (&&) 113 ampersand operator (&) 113 and operator 115 annuity function 291-292 annuity. See also compound It as destination 106 answer command 168-172 answer file command 168-172 answer for ask command 176 answer program command 15, 168-172 any (ordinal) 87 appleEvent message 20 appleEvent system message 132 AppleScript 5 and HyperTalk, comparing 6 application, stand-alone, building 14 arithmetic operators 113, 118 arrow cursor 395 arrowKey command 173-174 arrowKey system message 132, 173-174 ASCII codes 561-564 ask It as destination 106 ask command 174-176 ask file command 174-176 ask password command 174-176 assigning menu names 93 asterisk (*) operator 114 atan function 292-293 autoHilite property 17,379

autoSelect property 380–381 autoTab property 381–382 average function 293–294	button properties 365-367 autoHilite 379 bottom 383-384 bottomRight 384-385 enabled 402-403 family 404-406 height 411
showLines 470-471 background properties 360-361 cantDelete 388-389 cantModify 389-390 dontSearch 398-399 ID 416-418 name 439-441 number 441 script 460-461 scriptingLanguage 462-463 showPict 472	number 441 partNumber 444 rectangle 455-458 right 459-460 script 460-461 scriptingLanguage 462-463 sharedHilite 468-469 showName 471 style 475 style 475
backgrounds current 25 defined 25 descriptors for 82–87	textAlign 477 textFont 479-480 textHeight 480-481 textSize 481-482 textStyle 482-484
beep command 177 before (preposition) 251 bkgnd (object) 82 blindTyping property 382 bottom property 17, 383–384 bottomRight property 17, 384–385	titleWidth 486 top 486-488 topLeft 488-489 version 496-497 wideMargins 499
brush property 386 brush tool name 178 btn (object) 82 bucket tool name 178 built-in functions 100	buttons as containers 105 defined 24 descriptors for 82–87 editing scripts of 33–41 messages to 58
busy cursor 395 buttonCount palette property 237 button dialog modifications 7–8 Button Info dialog 7–8 button Info dialog box 35	new features 8–12 system messages and 126–128 button text text alignment 477 button tool name 178

C	defined 118
	— as a destination 123
cantAbort property 387–388	chunk expression 118–124
cantDelete property 388-389	ranges in 121
cantModify property 389-390	syntax of 119
cantPeek property 390-391	clickChunk function 295–296
Can't understand error message 56	click command 180-181
card (object) 82	location 180
card fields 82	clickH function 296, 299–300
Card Info dialog box 82	clickLine function 296-297
card properties 361–362	clickLoc function 297–298
cantDelete 388-389	clickText function 298-299
cantModify 389-390	closeBackground system message 133
dontSearch 398-399	closeCard system message 133
ID 416-418	close command 15, 181-??
marked 432	closeField system message 129
name $439-441$	close file command 183-184
number 441	closePalette message 20
owner 443	closePalette system message 133
rectangle 455-458	closePicture message 20
right 460-461	closePicture system message 133
scriptingLanguage 462-463	close printing command 185,233
showPict 472	closeStack system message 133
wideMargins 499	close system message 132
cards	close window.command 186
current 25	closing external windows 540
defined 25	cmdChar property 393—394
descriptors for 82–87	Command-hyphen 39
editing scripts of 34–41	commandKeyDown command 187–188
system messages and 131–138	commandKey function 300
card window	commandKey system message 133
current 96	commands 165–287
card window properties	add 167–168
scroll 466-467	answer 168-172
card windows 28	answer file 168-172
defined 28	answer program 15,168-172
cd (object) 82	arrowKey 173-174
centered property 391	ask 174–176
characters as chunk expressions 120	ask file 174-176
charToNum function 294	ask password 174-176
checkMark property 392-393	beep 177
checkpoints 43, 45, 196–197	choose 178-179
choose command 178–179	click 180-181
chunk	close 15.181-??

close file 183-184 open 15 close printing 185,233 overriding 142 close window 186 palette 235-237 commandKeyDown 187-188 palette property 237 controlKey 188-190 picture 15,238-242 convert 3, 15, 191-194 play 243-245 create menu 194-195 play stop 243-245 create stack 195-196 pop card 245-246 print 246-248 debug checkpoint 196-197 print card 248-250 defined 165 delete 15, 197-200, 575 push card 250-251 dial 200-201 put 16, 251–254 disable 15,201-202 read 254-256 divide 202-203 read from file 16 doMenu 15, 203-205 reply 16,256-?? drag 205-207 request 258-260 edit script 207 request from 16 enable 15,208 reset menubar 260-261 enterInField 209 reset paint 261-262 enterKey 209-210 reset printing 262 export paint 210-211 returnInField 262-263 find 15,211-214 returnKey 263 find chars 15 save stack 264 select 264-266 find string 15 find whole 15 send ??-162 find word 15 set 266-267 functionKey 215-216 show 268-270 get 216-217 show cards 271-272 go 218-219 sort 272-274 sort 16-?? help 219 hide 220-222 start using 274-275 import paint 223 stop using 275, 276 keyDown 224-?? subtract 277 lock 225 syntax notation 166-167 lock error dialogs 15 syntax summary 574–581 lock recent 225 tabKey 277-278 lock recent 15 type 278-279 lock screen 225 unlock 279-280 lock 15 unlock error dialogs 279-280 mark 226-227,228-229 unlock recent 279-280 open 229-231 unlock screen 279-280 open file 231-232 unmark 281-282 open printing 232-233 visual 16,282-284 open report printing 234-235 wait 284-285

write 285-287	dateItems format 191
write to file 16	debug checkpoint command 196-197
comment character 112	debugger 43–49
comment character () 26	command summary 49
comment command 39	defined 43
commenting scripts 39	exiting 45
comparison operators 113–118	stepping through scripts 44
complex expressions 111–112	tracing through scripts 45
compound function 301-302	debugger checkpoints 45
compound function. See also annuity function	Debugger menu 43
constant, defined 99	debugger property 396
constants 553–554	debugger tools 45
containers 103–109	debugger windows 45-48
chunk expressions and 122–124	debugging environment 43
defined 103	deleteBackground system message 133, 139
fields 104	deleteButton system message 127
Message box 108–109	deleteCard system message 133,139
the selection 107	delete command 15,197–200
variables 78, 105	deleteField system message 129
contains operator 115	deleteStack system message 134,139
controlKey command 188-190	destination function 16,304
controlKey system message 133, 189	dial command 200-201
control structures 141–163	dialingTime property 17,397
convert command 3, 15, 191-194	dialingVolume property 17,398
cos function 302	dialog modifications
create menu command 194-195	button 7–8
create. See also disable, disabled, enable,	field 12
enabled, text, textStyle, markChar,	dialog window layer 544
cmdChar,, and put	disable command 15, 201–202
create stack command 195-196	. See also enable command
creating menus 194	disabling background buttons 201–202
cross cursor 395	disabling card buttons 201–202
current hierarchy 59–60	disabling menu items 201–202
current objects 25	disabling menus 201–202
cursor property 394–395	diskSpace function 16,305
cursors 395	divide command 202–203
curve tool name 178	div operator 115
cutCard system message 139	document window layer 544
	do keyword 158–159
	doMenu command 15, 203–205
D	intercepting 166
D	intercepting handler 204
date function 302–304	doMenu system message 134
uate fullchon 304-304	dontSearch property 398-399

dontWrap property 399-400	exit repeat statement 153
double hyphen () 26, 39, 40, 112	exit statement 147
down constant 553	exp function 306
drag command 205–207	exp1 function 306–307
dragSpeed property 400–401	export paint command 210-211
Draw Centered setting 373, 391	expressions 99–109, 111–124
Draw Filled setting 373	complex 111–118
Draw Multiple setting 373, 436	exp2 function 307
	external commands and functions 503–552
dynamic path 67–71	external window callbacks 522–529
go command and 67	
invoking 67	external window events 536–540
send keyword and 67, 69–??, 70, ??–71	xCloseEvt 537
	xCursorWithin 539
	xDebugErrorEvt 540
Е	xDebugFinishedEvt 540
<u> </u>	xEditClear 538
editBkgnd property 402	xEditCopy 538
edit script command 207	xEditCut 538
. I	xEditPaste 538
eighth (ordinal) 84	xEditUndo 538
else keyword 155–158	xGetPropEvt 538
empty (constant) 105, 553	xGiveUpEditEvt 537
enable command 15, 208	xGiveUpSoundEvt 538
. See also disable command	xMBarClickedEvt 540
enabled property 18, 402–403	xMenuEvt 539
. See also disable command, enable	xOpenEvt 537
command	xScriptErrorEvt 540
end keyword 26, 143, 154	xSendEvt 538
end repeat statement 154	xSetPropEvt 538
end statement 147	xShowWatchInfoEvt 540
enhancements	external windows 522-529, 534-545
HyperTalk 15–21	closing 540
enterInField command 209	event handling 528
enterInField system message 129	O
enterKey command 209-210	
enterKey message 209,210	
enterKey system message 134	F
environmental properties 368	
environment property 18,404	factors 111–112
equal sign (=) 113	false constant 554
eraser tool name 178	family property 18,404-406
example XCMD 545	field dialog modifications 12
exitField system message 129	Field Info dialog 12
exit keyword 72, 143, 153	field properties 362–364

autoSelect 380-381	find string command 15
autoTab 381-382	find whole command 15
bottom 383-384	find word command 15
bottomRight 384-385	first (ordinal) 84
dontSearch 398-399	five (constant) 84
dontWrap 399-400	fixedLineHeight property 407-408
fixedLineHeight 407-408	formFeed constant 554
height 411	foundChunk function 307–308
ID 416-418	. See also find command
left 421-422	foundField function 308-309
location 423-425	foundLine function 309-310
lockText 429-430	foundText function 310
name 439-441	four (constant) 84
new features 13-14	fourth (ordinal) 84
number 441	freeSize property 408-409
partNumber 444	function 100
rectangle 455-458	redefining 290
right 459-460	function calls 27, 289
script 460-461	function handlers 27–32, 146–149
scriptingLanguage 462-463	example 149
scroll 465-466	keywords in 145–149
style 475	overriding 146
textAlign 477	parameter passing into 78
textFont 479-480	user-defined 146
textHeight 480-481	functionKey command 215-216
textSize 481-482	functionKey system message 134
textStyle 482-484	function keyword 146
top 486-488	functions 289–355
topLeft 488-489	abs 291
version 496-497	annuity 291-292
wideMargins 498,499	atan 292-293
fields 104	average 293-294
as containers 104	charToNum 294
descriptors for 82–89	clickChunk 295-296
system messages and 128-131	clickH 296,299-300
fields properties	clickLine 296-297
multipleLines 437-??	clickLoc 297-298
field text 477	clickText 298-299
field tool name 178	commandKey 300
fifth (ordinal) 84	compound 301-302
filled property 406	cos 302
find chars command 15	date 302-304
find command 15,211-214	defined 289
dontSearch property 399	destination 16,304

diskSpace 16,305	sqrt 345
exp 306	stacks 345-??
exp1 306-307	stackSpace 346
exp2 307	sum 17,346
foundChunk 307-308	syntax notation 290
foundField 308-309	systemVersion 17,347
foundLine 309-310	tan 347-348
foundText 310	target 348-349
heapSpace 310-311	ticks 349-350
length 311-312	time 350-351
ln 312	tool 351-352
ln1 313	trunc 353-354
log2 313	value 354-355
max 314	windows 355
menus 315	
min 315-316	
mouse 316-317	
mouseClick 317-318	G
mouseH 318	1 01/ 01/
mouseLoc 319	get command 216–217
mouseV 320	It as destination 106
number 16,320-322	global keyword 106, 159
numToChar 322-323	global properties 369–372
offset 323-324	address 378
optionKey 324-325	blindTyping 382
param 325-326,??-328	cursor 394-395
paramCount 326-327	debugger 396
parameters of 289	dialingTime 397
params 327-??	dialingVolume 398
programs 16,328	dragSpeed 400-401
random 329	editBkgnd 402
result 330-331	environment 404
round 332	itemDelimiter 418-419
screenRect 333	Language 420
seconds 333-334	lockErrorDialogs 425-426
selectedButton 17,334-335	lockMessages 426-427
selectedChunk 335-336	lockRecent 427-428
selectedField 336-337	lockScreen 428–429
selectedLine 17,337-339	longWindowTitle 430
selectedLoc 339-340	messageWatcher 435
selectedText 17,340-341	numberFormat 442-443
shiftKey 341-342	powerKeys 447
sin 343	printMargin 448
sound 343-344	printTextAlign 449

printTextFont 450-??	hide (object) 221
printTextHeight ??-450,451	hide command 220–222
printTextSize 452-453	hideIdle property 412
printTextStyle 453	hide menuBar system message 135
scriptEditor 461-462	hideUnused property 413
scriptTextFont 463-464	hiding card windows 220
scriptTextSize 464-465	hiding objects 221–222
stacksInUse 474	hiding picture windows 220
textArrows 478	hiding stack windows 220
textFont 479-480	hierarchy, message-passing 56–70, 73–76
traceDelay 489-490	current 56
userLevel 490-491	defined 56
userModify 491-492	objects in 58
variableWatcher 492-493	hilitedButton palette property 237
global statement 159–160	hilite property 18,414-415
global variables 47, 106, 159–160	. See also autoHilite property, and family
go command 218–219	property, sharedHilite property
greater than (>) operator 113	HyperCard
grid property 409	enhancements since HyperCard 2.0 1-21
Grid setting 373	and Open Scripting Architecture 4–7
	and other scripting systems 3-4
	performance hints 555–560
11	system requirements 1–2
Н	system requirements 1–2 and WorldScript compatibility 2, 3
hand cursor 395	and WorldScript compatibility 2, 3
hand cursor 395 handler 126	and WorldScript compatibility 2, 3 HyperCard properties
hand cursor 395 handler 126 handlers 26–27, 62	and WorldScript compatibility 2, 3 HyperCard properties ID 416–418
hand cursor 395 handler 126 handlers 26–27, 62 calling 71–73	and WorldScript compatibility 2, 3 HyperCard properties ID 416–418 version 494–495
hand cursor 395 handler 126 handlers 26–27, 62 calling 71–73 defined 26	and WorldScript compatibility 2, 3 HyperCard properties ID 416–418 version 494–495 HyperTalk, enhancements 15–21
hand cursor 395 handler 126 handlers 26–27, 62 calling 71–73 defined 26 function 27–32, 78, 145–149	and WorldScript compatibility 2, 3 HyperCard properties ID 416–418 version 494–495 HyperTalk, enhancements 15–21 hyphen (-) as minus arithmetic operator 112
hand cursor 395 handler 126 handlers 26–27, 62 calling 71–73 defined 26 function 27–32, 78, 145–149 intercepting commands 78, 166	and WorldScript compatibility 2, 3 HyperCard properties ID 416–418 version 494–495 HyperTalk, enhancements 15–21 hyphen (-) as minus arithmetic operator 112
hand cursor 395 handler 126 handlers 26–27, 62 calling 71–73 defined 26 function 27–32, 78, 145–149 intercepting commands 78, 166 intercepting messages 76	and WorldScript compatibility 2, 3 HyperCard properties ID 416–418 version 494–495 HyperTalk, enhancements 15–21 hyphen (-) as minus arithmetic operator 112 hyphen, double () comment character 112
hand cursor 395 handler 126 handlers 26–27, 62 calling 71–73 defined 26 function 27–32, 78, 145–149 intercepting commands 78, 166 intercepting messages 76 message 27	and WorldScript compatibility 2, 3 HyperCard properties ID 416–418 version 494–495 HyperTalk, enhancements 15–21 hyphen (-) as minus arithmetic operator 112
hand cursor 395 handler 126 handlers 26–27, 62 calling 71–73 defined 26 function 27–32, 78, 145–149 intercepting commands 78, 166 intercepting messages 76 message 27 nesting 72	and WorldScript compatibility 2, 3 HyperCard properties ID 416–418 version 494–495 HyperTalk, enhancements 15–21 hyphen (-) as minus arithmetic operator 112 hyphen, double () comment character 112
hand cursor 395 handler 126 handlers 26–27, 62 calling 71–73 defined 26 function 27–32, 78, 145–149 intercepting commands 78, 166 intercepting messages 76 message 27 nesting 72 recursion 72–73	and WorldScript compatibility 2, 3 HyperCard properties ID 416–418 version 494–495 HyperTalk, enhancements 15–21 hyphen (-) as minus arithmetic operator 112 hyphen, double () comment character 112 I, J I-beam cursor 395
hand cursor 395 handler 126 handlers 26–27, 62 calling 71–73 defined 26 function 27–32, 78, 145–149 intercepting commands 78, 166 intercepting messages 76 message 27 nesting 72 recursion 72–73 sharing 74–75	and WorldScript compatibility 2, 3 HyperCard properties ID 416–418 version 494–495 HyperTalk, enhancements 15–21 hyphen (-) as minus arithmetic operator 112 hyphen, double () comment character 112 I, J I-beam cursor 395 icon property 415–416
hand cursor 395 handler 126 handlers 26–27, 62 calling 71–73 defined 26 function 27–32, 78, 145–149 intercepting commands 78, 166 intercepting messages 76 message 27 nesting 72 recursion 72–73 sharing 74–75 statements within 26	and WorldScript compatibility 2, 3 HyperCard properties ID 416–418 version 494–495 HyperTalk, enhancements 15–21 hyphen (-) as minus arithmetic operator 112 hyphen, double () comment character 112 I, J I-beam cursor 395 icon property 415–416 identifying a stack 90–91
hand cursor 395 handler 126 handlers 26–27, 62 calling 71–73 defined 26 function 27–32, 78, 145–149 intercepting commands 78, 166 intercepting messages 76 message 27 nesting 72 recursion 72–73 sharing 74–75 statements within 26 as subroutines 71	and WorldScript compatibility 2, 3 HyperCard properties ID 416–418 version 494–495 HyperTalk, enhancements 15–21 hyphen (-) as minus arithmetic operator 112 hyphen, double () comment character 112 I, J I-beam cursor 395 icon property 415–416 identifying a stack 90–91 idle system message 52, 135
hand cursor 395 handler 126 handlers 26–27, 62 calling 71–73 defined 26 function 27–32, 78, 145–149 intercepting commands 78, 166 intercepting messages 76 message 27 nesting 72 recursion 72–73 sharing 74–75 statements within 26 as subroutines 71 hBarLoc property 410	and WorldScript compatibility 2, 3 HyperCard properties ID 416–418 version 494–495 HyperTalk, enhancements 15–21 hyphen (-) as minus arithmetic operator 112 hyphen, double () comment character 112 I, J I-beam cursor 395 icon property 415–416 identifying a stack 90–91 idle system message 52, 135 ID property 18, 88, 416–418
hand cursor 395 handler 126 handlers 26–27, 62 calling 71–73 defined 26 function 27–32, 78, 145–149 intercepting commands 78, 166 intercepting messages 76 message 27 nesting 72 recursion 72–73 sharing 74–75 statements within 26 as subroutines 71 hBarLoc property 410 heapSpace function 310–311	and WorldScript compatibility 2, 3 HyperCard properties ID 416–418 version 494–495 HyperTalk, enhancements 15–21 hyphen (-) as minus arithmetic operator 112 hyphen, double () comment character 112 I, J I-beam cursor 395 icon property 415–416 identifying a stack 90–91 idle system message 52, 135 ID property 18, 88, 416–418 if structure 155–158
hand cursor 395 handler 126 handlers 26–27, 62 calling 71–73 defined 26 function 27–32, 78, 145–149 intercepting commands 78, 166 intercepting messages 76 message 27 nesting 72 recursion 72–73 sharing 74–75 statements within 26 as subroutines 71 hBarLoc property 410 heapSpace function 310–311 height property 18, 411	and WorldScript compatibility 2, 3 HyperCard properties ID 416–418 version 494–495 HyperTalk, enhancements 15–21 hyphen (-) as minus arithmetic operator 112 hyphen, double () comment character 112 I, J I-beam cursor 395 icon property 415–416 identifying a stack 90–91 idle system message 52, 135 ID property 18, 88, 416–418 if structure 155–158 multiple-statement 156–158
hand cursor 395 handler 126 handlers 26–27, 62 calling 71–73 defined 26 function 27–32, 78, 145–149 intercepting commands 78, 166 intercepting messages 76 message 27 nesting 72 recursion 72–73 sharing 74–75 statements within 26 as subroutines 71 hBarLoc property 410 heapSpace function 310–311	and WorldScript compatibility 2, 3 HyperCard properties ID 416–418 version 494–495 HyperTalk, enhancements 15–21 hyphen (-) as minus arithmetic operator 112 hyphen, double () comment character 112 I, J I-beam cursor 395 icon property 415–416 identifying a stack 90–91 idle system message 52, 135 ID property 18, 88, 416–418 if structure 155–158

import paint command 223	L
in (preposition) 92, 119, 166	
Info menu 34	Language property 420
intercepting messages 76–77, 433	lasso tool name 178
doMenu 433	last (ordinal) 87
menu 433	layered buttons and fields 58
interrupting executing handlers 72	left property 421–422
into (preposition) 251	length function 311-312
is an operator 115	less than (<) operator 114
is a operator 115	less than or equal to (<=) operator 114
is in operator 115	less than or equal to (≤) operator 114
is not an operator 115	lineFeed constant 554
is not a operator 115	lines as chunk expressions 121
is not in operator 115	lineSize property 422-423
is not operator 115	line tool and 422
is operator 115	shape tool and 422
It (container) 106	line tool name 178
itemDelimiter property 18,418-419	literal strings 100
items as chunk expressions 120	ln1 function 313
It variable 106	ln function 312
	local variables 47, 106
	location 180
	location property 423-425
K	point 424
1.004.00	lock command 15, 225
keyDown command 224–??	lock error dialogs command 15
keyDown system message 135	lockErrorDialogs property 19,425-426
keywords 53, 59, 141–163	lockMessages property 426-427
defined 141	lock recent command 15,225
do 158–159	lockRecent property 427-428
else 155-158	lock screen command 225
end 143, 154	lockScreen property 428-429
exit 143,153	lockText property 19, 429–430
function 145,146	log2 function 313
global 159	long (adjective) 84
next 154	long date format 191
on 142–143	long time format 192
pass 143	longWindowTitle property 430
repeat 150	
return 144	
send 160	
	M

markChar property 431

mark command 226-227, 228-229	creating 94
marked property 432	defined 30
max function 314	disabling 201–202
me (special object descriptor) 89	enabling 208
menu	number of 321
disable command 202	referring to by number 93
enable command 208	menus function 315
number of 320	Message box 53, 108
menu bar properties	message handlers 26, 141–144
rectangle 455-458	example 144
visible 496-497	keywords in 142–145
menu command 204	syntax of 141
menu commands 126	message name 77
menu item names 93, 94	message-passing hierarchy
menu item properties 375–376	current 59–60
checkMark 392-393	user-defined 62-65
checkMark. See also put	using 73–76
cmdChar 393-394	messages 51–79
. See also menuMsg command; put command	appleEvent 20
enabled 402-403	to a button 53, 58
markChar 431	to a card 52
menuMsg 433-434	closePalette 20
name 439-441	closePicture 20
textStyle 484-485	commands 26
textSyle. See also put	from external commands 54
menu items 31, 251	handling 51
adding messages for 251	intercepting 76
defined 31	keywords in 53
disabling 201–202	matching message names 55–56
enable 208	mouseDoubleClick 21
referring to by number 94	openPalette 21
menuMessage property 434	openPicture 21
menu messages 31, 251	receiving 55
defined 31	resulting from commands 54
intercepting 433	sending 52
menuMsg property 433-434	sent to a field 128–131
. See also doMenu command; put command	sent to a locked field 53
menu names 93, 94	sent to buttons 126
menu numbers 93	sent to current card 131-138
menu properties	system 52
enabled 402-403	system messages in 56
name 439-441	to fields 58
menus 30, 81	message sending order 26
controlling through HyperTalk 93-95	Message Watcher 46–47

messageWatcher property 435 Message Watcher window properties 376–377	newBackground system message 137, 139 newButton system message 128
hideIdle 412 hideUnused 413	newCard system message 137, 139
middle (ordinal) 87	newField system message 130 newStack system message 137, 139
min function 315–316	next keyword 154
miniwindow layer 544	next repeat statement 154
minus sign (-) operator 114	next special object descriptor 89
modems, dial command and 200–201	nine (constant) 84
mod operator 116	ninth (ordinal) 84
mouseClick function 317–318	nonexistent chunks 124
mouseDoubleClick message 21	not equal sign () operator 115
mouseDoubleClick system message 127, 129,	not equal sign (<>, ≠) operator 114
136	not operator 116
mouseDownInPicture system message 136	numberFormat property 442-443
mouseDown message 53	number function 16, 320–322
mouseDown system message 127, 130, 136	number handling 103
mouseEnter message 52	number property 19,441
mouseEnter system message 127, 130	number property. See also number function
mouse function 316–317	numbers 101–103
mouseH function 318	decimal string precision 102
mouseLeave message 52	numberFormat property and 102
mouseLeave system message 127, 130	SANE numeric values 102
mouseLoc function 319	. See also number property
mouseStillDown system message 127, 130, 136	numToChar function 322-323
mouseUpInPicture system message 136	. See also charToNum function
mouseUp message 53	
mouseUp system message 128, 130, 136	
mouseV function 320	0
mouseWithin message 52	0
mouseWithin system message 128, 130	-linet
moveWindow system message 136	object
multipleLines property 437-??	ID number 88–89
multiple property 436	script 26
multiSpace property 438-439	object descriptors 82
	combining 92
	descriptor phasing 83 object hierarchy 56
N	
IN	message-passing 56–?? message-passing in ??–78
name property 19, 84, 439–441	object ID number 88–89
naming menus 93	object names 83
naming objects 82–83, 91	object numbers 84
naming stacks 91	integer 84
Imming omeno /1	ineger or

numeric constants 84	operators 113–118
ordinal constants 84	ampersand (&) 113
reassigning 87	ampersand, double (&&) 113
special ordinals 87	and 115
tab order 87	asterisk (*) 114
object properties 358	caret (^) 113
ID 88	comparison 113
name 84	contains 115
objects 24,81	div 115
background buttons 82	equal sign (=) 113
backgrounds 25	and expression type 118
buttons 24	greater than (>) 113
cards 25	greater than or equal to sign (≥, >=) 114
fields 24, 81	is 115
generic names 82	is a 115
referring directly to 92	is in 115
stacks 25	is not 115
Objects menu 33	is not a 115
of (preposition) 92, 119, 166	is not an 115
offset function 323–324	is not in 115
one (constant) 84	less than or equal to sign (≤, <=) 114
on keyword 26, 142–143	less than sign (<) 114
open	minus sign (-) 114
document with application 229	mod 116
openBackground system message 137	not 116
openCard message 52	not equal sign () 115
openCard system message 137	not equal sign $(<>, \neq)$ 114
open command 15, 229–231	numeric values 118
openField message 53	or 116
openField system message 130	parentheses () 114
open file command 231–232	plus sign (+) 115
opening	precedence of 117–118
documents 231	slash (/) 113
files for reading or writing 232	there is a 116
openPalette message 21	there is an 116
openPalette system message 137	there is not a 116
openPicture message 21	there is not an 116
openPicture system message 137	within 116
open printing command 232–233	optionKey function 324-325
open report printing command 234-235	. See also commandKey function
Open Scripting Architecture (OSA) 4–7	ordinal constant 119
and AppleScript 5	or operator 116
openStack system message 137	oval tool name 178
operator precedence 565	overriding commands 142
operator precedence 500	Overmania communa 172

owner of <i>card</i> property 19 owner of <i>window</i> property 19 owner property 443	part properties scriptingLanguage 462–463 pass keyword 55, 67, 143 pass statement 147
P	pasteCard system message 139 pattern property 445—446 Patterns palette 445
painting properties 372–373 brush 386 centered 391 filled 406 grid 409 lineSize 422–423 multiple 436 multiSpace 438–439 pattern 445–446 polySides 446 textAlign 477 textFont 479–480 textHeight 480–481 textSize 481–482 textStyle 482–484 Paint text 104, 477 Paint Text tool 477 palette command 235–237 palette properties properties 237 palette properties buttonCount 237 commands 237 hilitedButton 237 paramCount function 326–327	pencil tool name 178 pi constant 554 picture command 15, 238–242 globalRect 239, 240 loc 240 rect 239 scale 241 scroll 240 picture window properties rect 454–455 scroll 466–467 play command 243–245 playing notes 243 playing sound 244 play stop command 243–245 plus cursor 395 plus sign (+) operator 115 polygon tool name 178 polySides property 446 pop card command 245–246 . See also push card command pop-up button properties, titleWidth 486 powerKeys property 447 previous special object descriptor 89 print marked cards 248
parameter list 78, 142	marked cards 248 print card command 248–250
parameter passing 78	print command 246-248
to handlers 78	document with application 247
parameters	expression 247
defined 77	field 247
in function handlers 78	printing cards 248–250
parameter variables 78 param function 325–326, ??–328	printing fields 246–248
param function 325–326, ??–326 param. See also paramCount, params	printing marked cards 248–250
	printing reports 235
params function 327–??	printMargin property 448
partNumber property 19,444	printTextAlign property 449

450.00	1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1
printTextFont property 450-??	hilite 18,414-415
printTextHeight property ??-450, 451	hilitedButton 237
printTextSize property 452–453	icon 415–416
printTextStyle property 453	ID 18, 416–418
programs function 16,328	itemDelimiter 18,418-419
properties 357–499	Language 420
20	left 421-422
address 17,378	lineSize 422-423
autoHilite 17,379	location 423-425
autoSelect 380-381	lockErrorDialogs 19,425-426
autoTab 381-382	lockMessages 426-427
blindTyping 382	lockRecent 427-428
bottom 17,383-384	lockScreen 428-429
bottomRight 17,384-385	lockText 19,429-430
brush 386	longWindowTitle 430
buttonCount 237	markChar 431
cantAbort 387-388	marked 432
cantDelete 388-389	menuMsg 433-434
cantModify 389-390	messageWatcher 435
cantPeek 390-391	multiple 436
centered 391	multipleLines 437-??
checkMark 392-393	multiSpace 438-439
cmdChar 393-394	name 19,439-441
commands 237	number 19,441
cursor 394-395	numberFormat 442-443
debugger 396	owner 443
defined 101	owner of card 19
dialingTime 17,397	owner of window 19
dialingVolume 17,398	partNumber 19,444
dontSearch 398-399	pattern 445-446
dontWrap 399-400	polySides 446
dragSpeed 400-401	powerKeys 447
editBkqnd 402	printMargin 448
enabled 18,402-403	printTextAlign 449
environment 18,404	printTextFont 450-??
family 18,404-406	printTextHeight ??-450,451
filled 406	printTextSize 452-453
fixedLineHeight 407-408	printTextStyle 453
freeSize 408-409	properties 237
grid 409	rect 19,454-455
hBarLoc 410	rectangle 455-458
height 18,411	reportTemplates 458-459
hideIdle 412	right 19,459-460
hideUnused 413	script 460-461
III acollabea 110	2011bc 100 101

scriptEditor 461-462	Q
scriptingLanguage 19,462-463 scriptTextFont 463-464	quit system message 137
scriptTextSize 464-465	quote constant 554
scroll (fields) 465–466	1
scroll (windows) 466-467	
sharedHilite 468-469	_
sharedText 469-470	R
showLines 470-471	
showName 471	random function 329
showPict 472	ranges of chunks 121
size 473-474	read command 106, 254–256
stacksInUse 474	It as destination 106, 255
style 475	limits 255
style of button 20	until character 255
textAlign 477	read from file command 16
textArrows 478	reading files 254–256
textFont $479-480$	reassigning object numbers 87
textHeight 480-481	recent special object descriptor 89
textSize 481-482	rectangle 364
textStyle (buttons, fields, painting	rectangle properties 367
environment) 482–484	bottom 383–384
textStyle (menu items) 484-485	bottomRight 384-385
titleWidth 20,486	constant 488
top 486–488	height 411
topLeft 20,488-489	left 421–422
traceDelay 489-490	right 459-460
userLevel 490-491	top 486-488
userModify 491-492	topLeft 488-489
variableWatcher 492-493	rectangle property 455–458
vBarLoc 493-494	rectangle tool name 178
version 494-495	rect property 19,454–455
visible 20,496-497	recursion 72
wideMargins 498	redefining commands 165–166
width 20,499	redefining commands 165–166
properties syntax 377	hints 166
property name 101	redefining functions 290
Protect Stack dialog box 389, 390	referring to card windows 96
push card command 250-251	referring to external windows 97
put command 16, 124, 251–254	referring to fields 104
. See also cmdChar property; enabled	referring to menu items 94
property; menuMsg property; text	referring to menus 93
property; and textStyle property	referring to windows 97
	referring to windows //

repeat forever statement 150	S
repeat for statement 151	save stack command 264
repeat keyword 150	
repeat statement 150–?? forms of 150–153	screen rectangles 367, 457
	screenRect function 333
repeat for 151	script attachability 6–7
repeat forever 150	script comments 26
repeat until 151	script debugger 43
repeat while 152	script editor 35–42
repeat with 152-153	automatic formatting 40
repeat withdown to 152-153	breaking long line statements 41
repeat withto 152	command summary 41
repeat statements ??–154	comments 40
repeat structure 149–154	enhancements 7
repeat until statement 151	formatting scripts 40
repeat while statement 152	manipulating text 37, 38
repeat withdown to statement 152-153	opening multiple scripts 35
repeat with statement 152-153	replacing text 39
repeat withto statement 152	saving a script 35
reply command 16, 256-??	script size 41
reportTemplates property 458-459	searching 38
request command 258–260	shortcuts 35
request from command 16	scriptEditor property 461-462
reserved words (keywords) 141–163	scriptingLanguage property 19,462-463
reset menubar command 260-261	scripting systems, other 3–4
reset paint command 261-262	scripting userLevel 34
reset printing command 262	script property 460-461
result function 330-331	scripts 26
resumeStack system message 137	attachability 6–7
resume system message 137, 139	background, editing the script of 34
retrieving properties 357–376	background buttons 35
return, soft 41	background fields 35
return constant 554	button, editing the script of 35
returnInField command 262-263	closing 35
returnInField system message 131	current card, editing the script of 34
returnKey command 263	fields, editing the script of 35
returnKey system message 137	function handlers within 27
return keyword 144	getting to object scripts 33
return statement 148	opening 33–35
right property 19,459-460	saving 35
round function 332	scripting shortcuts 35
round rectangle tool name 178	shortcuts for opening 35
	stack, editing the script of 34
	scriptTextFont property 463-464
	1 1 /

scriptTextSize property 464-465	object form 268
scroll (fields) property 465-466	picture of background form 268
scroll (windows) property 466–467	picture of card form 268
searching, find command 212	. See also hide command; set command
second (ordinal) 84	titlebar form 268
seconds format 192	window stackName form 268
seconds function 333-334	window windowName form 268
secondsfunction	showing card windows 268
. See also convert command	showing picture windows 268
select command 264-266	showing stack windows 268
selectedButton function 17,334-335	showLines property 470–471
selectedChunk function 335-336	show marked cards 271
selectedField function 336-337	showName property 471
selectedLine function 17,337-339	showPict property 472
selectedLoc function 339-340	show system message 137
selected text 108	sin function 343
selectedText function 17,340-341	six (constant) 84
select tool name 178	sixth (ordinal) 84
send command 53, ??-162	size property 473–474
send keyword 73, 160	sizeWindow system message 138
send statement 160-163	slash (/) operator 113
set command 266–267	soft return 41
set. See also properties	sort command 16-??, 272-274
setting properties 266, 357–376	sound function 343-344
seven (constant) 84	. See also play command
seventh (ordinal) 84	sources of value
sharedHilite property 468-469	constants 99
sharedText property 469-470	functions 100
sharing handlers 74	literals 100
shiftKey function 341-342	numbers 101
short (adjective) 84	properties 101
shortcuts	space constant 554
closing scripts 35	special object descriptors 89
opening scripts 35	me 89
short date format 192	next 89
short time format 192	prev 89
show	previous 89
picture 269	recent 89
show cards command 271–272	this 89
marked cards form 271	special ordinals 87, 119
show command 268-270	spray can tool name 178
background picture form 268	sgrt function 345
card picture form 268	stack
groups form 268	identifying 90
	, 0

naming 91	stop using command 275,276
referring to 90	structures
stack builder, integrated stand-alone 14	if 155-158
stack name 90	multiple-statement 156-158
stack properties 359–360	single-statement 155–156
cantAbort 387-388	style of button property 20
cantDelete 388-389	style property 475
cantModify 389-390,390-391	subroutine calls 71–72
freeSize 408-409	calling handler 72
name 439-441	subroutine handler 72
reportTemplates 458-459	subtract command 277
script 460-461	sum function 17,346
scriptingLanguage 462-463	suspendStack system message 138
size 473-474	suspend system message 138
version 494-495	syntax
stacks	notation for commands 166–167
current 25	notation for functions 290
defined 25	summary for commands 574–581
descriptors for 90, 91	summary for functions 581–587
stacks function 345–??	system message order 138–139
stacksInUse property 474	system messages 52, 125–139
stackSpace function 346	appleEvent 132
stack window properties	arrowKey 132
rect 454-455	close 132
scroll 466-467	closeBackground 133
stand-alone application, building 14	closeCard 133
startUp system message 138, 139	closeField 129
start using command 274-275	closePalette 133
statements 26	closePicture 133
defined 26	closeStack 133
end 147	commandKey 133
end repeat 154	controlKey 133
exit 147	cutCard 139
exit repeat 153	deleteBackground 133,139
formatting 40	deleteButton 127
global 159-160	deleteCard 133,139
as messages 53	deleteField 129
next repeat 154	deleteStack 134,139
pass 147	doMenu 134
repeat 150-154	enterInField 129
return 148	enterKey 134
send 160-163	entry point in hierarchy 58
static path 67	exitField 129
stepping through scripts 44	functionKey 134

help 134	Т
hide menuBar 135	
idle 135	tab constant 554
is an 115	tabKey command 277-278
keyDown 135	tabKey. See also tabKey system message
mouseDoubleClick 127,129,136	tabKey system message 131, 138
mouseDown 127, 130, 136	tab order 87
mouseDownInPicture 136	tan function 347–348
mouseEnter 127,130	target function 61,348-349
mouseLeave 127,130	temporary checkpoints 45
mouseStillDown 127,130,136	ten (constant) 84
mouseUp 128, 130, 136	tenth (ordinal) 84
mouseUpInPicture 136	textAlign property 477
mouseWithin 128,130	textArrows property 478
moveWindow 136	textFont property 479-480
newBackground 137,139	textHeight property 480-481
newButton 128	text operators 118
newCard 137,139	textSize property 481-482
newField 130	textStyle property (buttons, fields, painting
newStack 137,139	environment) 482–484
openBackground 137	textStyle property (menu items) 484–485
openCard 137	text tool name 178
openField 130	there is an operator 116
openPalette 137	there is a operator 116
openPicture 137	there is not an operator 116
openStack 137	there is not a operator 116
pasteCard 139	the result function 144
quit 137	the selection container 107
resume 137,139	third (ordinal) 84
resumeStack 137	This 561
returnInField 131	three (constant) 84
returnKey 137	ticks function 349–350
show 137	time function 350–351
sizeWindow 138	titleWidth property 20, 486
startUp 138, 139	to (preposition) 121
suspend 138	tool function 351–352
suspendStack 138	. See also choose command
tabKey 131,138	topLeft property 20, 488–489
systemVersion function 17,347	top property 20, 486–488
System CISION Interior 17,547	traceDelay property 489-490
	tracing through scripts 45
	true constant 554
	trunc function 353–354
	two (constant) 84

type command 278–279	vBarLoc property 493–494 version property 494–495 visible property 20, 496–497 visual command 16, 282–284 visual effects 283
unlock command 279–280 unlock error dialogs command 279–280 unlock recent command 279–280 unlock screen	vocabulary list 589–621
with visual effect 280 unlock screen command 279–280 unmark command 281–282 up constant 554 user-defined (custom) menus 93 user-defined message-passing hierarchy 62–65 adding stacks 275 deleting stacks 276 handlers in 65 userLevel property 490–491	wait command 284-285 watch cursor 395 wideMargins property 498 width property 20,499 window layers defined 543 window properties 374-375 bottom 383-384 bottomRight 384-385 height 411
V value function 354-355 values 99-109	ID 416-418 left 421-422 location 423-425 owner 443 rectangle 455-458 right 459-460 top 486-488 topLeft 488-489
variable name 105 variables 105–106 as containers 105 defined 105 global 106 It 106 local 106 and numbers 102	visible 496—497 windows 28,81 windows function 355 within operator 116 words as chunk expressions 120 write command 285—287 . See also close file command; open file command; read command
parameter variables 78, 106 values stored in 102 Variable Watcher 47–48 Variable Watcher properties 376–377 variableWatcher property 492–493 Variable Watcher window properties hBarLoc 410 rect 454–455 vBarLoc 493–494	X,Y XCmdBlock parameter block 509 XCMDs and XFCNs 503 accessing 504

SaveXWScript 531 attaching the resource 508 ScanToReturn 514 callback fields 511 callback procedures and functions 512-534 ScanToZero 514 AbortScript 533 SendCardMessage 513 SendHCEvent 521 BeginXSound 520 BeginXWEdit 529 SendHCMessage 513 BoolToStr 515 SendWindowMessage 522 CloseXWindow 524 SetCheckPoints 532 CountHandlers 532 SetFieldByID 519 EndXSound 520 SetFieldByName 519 EndXWEdit 530 SetFieldByNum 519 EvalExpr 513 SetFieldTE 519 ExtToStr 515 SetGlobal 514 FormatScript 530 SetObjectScript 532 Front DocWindow 520 SetVarValue 533 SetXWIdleTime 526 GetCheckPoints 531 GetFieldByID 518 ShowHCPalettes 526 GetFieldByName 518 StackNameToNum 522 StepScript 534 GetFieldByNum 518 GetFieldTE 519 StringEqual 515 GetFilePath 521 StringLength 515 StringMatch 515 GetGlobal 514 GetHandlerInfo 533 StrToBool 517 GetNewXWindow 522 StrToExt 517 GetObjectName 532 StrToLong 517 GetObjectScript 532 StrToNum 517 GetStackCrawl 534 StrToPoint 517 GetVarValue 533 StrToRect 517 GetXResInfo 521 TraceScript 534 GoScript 534 XWAllowReEntrancy 528 HCWordBreakProc 530 XWAlwaysMoveHigh 527 HideHCPalettes 525 XWHasInterruptCode 526 LongToStr 516 ZeroBytes 514 ZeroTermHandle 515 NewXWindow 523 Notify 521 ZeroToPas 518 NumToHex 516 debugger callbacks 533 NumToStr 516 entryPoint 511 PasToZero 516 external window callbacks 522-529 PointToStr 516 field callbacks 518-519 PrintTEHandle 530 guidelines for writing 507 RectToStr 516 HyperTalk callbacks 513 RegisterXWMenu 525 inArgs 512 ReturnToPas 517 invoking 505 RunHandler 513 maximum parameters 505

```
memory callbacks 514
  in the message-passing hierarchy 505
  miscellaneous utility callbacks 520-522
  outArgs 512
  paramCount field 510
  parameter block 509
  params array 510
 passFlag 511
  passing back results 510
  passing information 509
  passing parameters 510
  request 511
  result 511
  returnValue 510
  script editor callbacks 530-532
  special XCmdBlock values 540
    Debugger 542
    Message Watcher 541
    script editor 541
    Variable Watcher 541
  string callbacks 514–515
  string conversion callbacks 515-518
  text editing callbacks 524-??, 529-530
  uses for 504
  Variable Watcher callbacks 533
  XCmdBlock 509
XTalkObject fields
 bkgndID 542
 buttonID 543
  cardID 543
  fieldID 543
  objectKind 542
  stackNum 542
XTalkObject structure 542-543
```

Ζ

zero..ten constant 554

This Apple manual was written, edited, and composed on a desktop publishing system using Apple Macintosh computers and FrameMaker software. Proof pages were created on an Apple LaserWriter IINTX printer. Final page negatives were output directly from the text and graphic files. Line art was created using Adobe TI Illustrator. PostScript the page-description language for the LaserWriter, was developed by Adobe Systems Incorporated.

Text type is Palatino[®] and display type is Helvetica[®]. Bullets are ITC Zapf Dingbats[®]. Some elements, such as program listings, are set in Apple Courier.

WRITERS

Julie Callahan, Cheryl Chambers, Steve Schwander, and Alan Spragens

DEVELOPMENTAL EDITORS
Jeanne Woodward and Beverly Zegarski

ILLUSTRATOR Barbara Carey

PRODUCTION EDITOR

Rex Wolf

COVER DESIGNER Barbara Smyth

PROJECT MANAGER

Patricia Eastman